



MOSEK Optimizer API for C
Release 9.0.96

MOSEK ApS

26 June 2019

Contents

1	Introduction	1
1.1	Why the Optimizer API for C?	2
2	Contact Information	3
3	License Agreement	4
4	Installation	6
4.1	Testing the Installation and Compiling Examples	7
5	Design Overview	9
5.1	Modeling	9
5.2	“Hello World!” in MOSEK	9
6	Optimization Tutorials	11
6.1	Linear Optimization	11
6.2	Quadratic Optimization	18
6.3	Conic Quadratic Optimization	28
6.4	Power Cone Optimization	33
6.5	Conic Exponential Optimization	37
6.6	Semidefinite Optimization	41
6.7	Integer Optimization	47
6.8	Geometric Programming	53
6.9	Library of basic functions	58
6.10	Problem Modification and Reoptimization	65
6.11	Parallel optimization	70
7	Solver Interaction Tutorials	73
7.1	Accessing the solution	73
7.2	Errors and exceptions	77
7.3	Input/Output	80
7.4	Setting solver parameters	81
7.5	Retrieving information items	83
7.6	Progress and data callback	83
7.7	MOSEK OptServer	86
8	Debugging Tutorials	90
8.1	Understanding optimizer log	91
8.2	Addressing numerical issues	94
8.3	Debugging infeasibility	97
8.4	Python Console	101
9	Advanced Numerical Tutorials	103
9.1	Solving Linear Systems Involving the Basis Matrix	103
9.2	Calling BLAS/LAPACK Routines from MOSEK	110
9.3	Computing a Sparse Cholesky Factorization	112
9.4	Converting a quadratically constrained problem to conic form	115

10	Technical guidelines	119
10.1	Memory management and garbage collection	119
10.2	Names	119
10.3	Multithreading	119
10.4	Efficiency	120
10.5	The license system	121
10.6	Deployment	122
10.7	Strings	122
11	Case Studies	123
11.1	Portfolio Optimization	123
11.2	Logistic regression	152
11.3	Concurrent optimizer	155
12	Problem Formulation and Solutions	160
12.1	Linear Optimization	160
12.2	Conic Optimization	163
12.3	Semidefinite Optimization	167
12.4	Quadratic and Quadratically Constrained Optimization	168
13	Optimizers	170
13.1	Presolve	170
13.2	Linear Optimization	172
13.3	Conic Optimization - Interior-point optimizer	178
13.4	The Optimizer for Mixed-integer Problems	182
14	Additional features	187
14.1	Problem Analyzer	187
14.2	Automatic Repair of Infeasible Problems	188
14.3	Sensitivity Analysis	192
15	API Reference	200
15.1	API Conventions	200
15.2	Functions grouped by topic	205
15.3	Functions in alphabetical order	213
15.4	Parameters grouped by topic	357
15.5	Parameters (alphabetical list sorted by type)	369
15.6	Response codes	409
15.7	Enumerations	427
15.8	Data Types	451
15.9	Function Types	452
15.10	Nonlinear interfaces (obsolete)	455
16	Supported File Formats	457
16.1	The LP File Format	458
16.2	The MPS File Format	463
16.3	The OPF Format	474
16.4	The CBF Format	483
16.5	The PTF Format	497
16.6	The Task Format	501
16.7	The JSON Format	502
16.8	The Solution File Format	509
17	List of examples	512
18	Interface changes	514
18.1	Backwards compatibility	514
18.2	Functions	514
18.3	Parameters	516

18.4	Constants	517
18.5	Response Codes	518
	Bibliography	520
	Symbol Index	521
	Index	537

Chapter 1

Introduction

The **MOSEK** Optimization Suite 9.0.96 is a powerful software package capable of solving large-scale optimization problems of the following kind:

- linear,
- conic:
 - conic quadratic (also known as second-order cone),
 - involving the exponential cone,
 - involving the power cone,
 - semidefinite,
- convex quadratic and quadratically constrained,
- integer.

In order to obtain an overview of features in the **MOSEK** Optimization Suite consult the [product introduction](#) guide.

The most widespread class of optimization problems is *linear optimization problems*, where all relations are linear. The tremendous success of both applications and theory of linear optimization can be ascribed to the following factors:

- The required data are simple, i.e. just matrices and vectors.
- Convexity is guaranteed since the problem is convex by construction.
- Linear functions are trivially differentiable.
- There exist very efficient algorithms and software for solving linear problems.
- Duality properties for linear optimization are nice and simple.

Even if the linear optimization model is only an approximation to the true problem at hand, the advantages of linear optimization may outweigh the disadvantages. In some cases, however, the problem formulation is inherently nonlinear and a linear approximation is either intractable or inadequate. *Conic optimization* has proved to be a very expressive and powerful way to introduce nonlinearities, while preserving all the nice properties of linear optimization listed above.

The fundamental expression in linear optimization is a linear expression of the form

$$Ax - b \geq 0.$$

In conic optimization this is replaced with a wider class of constraints

$$Ax - b \in \mathcal{K}$$

where \mathcal{K} is a *convex cone*. For example in 3 dimensions \mathcal{K} may correspond to an ice cream cone. The conic optimizer in **MOSEK** supports a number of different types of cones \mathcal{K} , which allows a surprisingly large number of nonlinear relations to be modeled, as described in the **MOSEK** [Modeling Cookbook](#), while preserving the nice algorithmic and theoretical properties of linear optimization.

1.1 Why the Optimizer API for C?

The Optimizer API for C provides low-level access to all functionalities of **MOSEK** from any C compatible language. It consists of a single header file and a set of library files which an application must link against when building. This interface has the smallest possible overhead, however other interfaces might be considered more convenient to use for the project at hand.

The Optimizer API for C provides access to:

- Linear Optimization (LO)
- Conic Quadratic (Second-Order Cone) Optimization (CQO, SOCO)
- Power Cone Optimization
- Conic Exponential Optimization (CEO)
- Convex Quadratic and Quadratically Constrained Optimization (QO, QCQO)
- Semidefinite Optimization (SDO)
- Mixed-Integer Optimization (MIO)

as well as additional interfaces for:

- problem analysis,
- sensitivity analysis,
- infeasibility analysis,
- BLAS/LAPACK linear algebra routines.

Chapter 2

Contact Information

Phone	+45 7174 9373	
Website	mosek.com	
Email		
	sales@mosek.com	Sales, pricing, and licensing
	support@mosek.com	Technical support, questions and bug reports
	info@mosek.com	Everything else.
Mailing Address		
	MOSEK ApS	
	Fruebjergvej 3	
	Symbion Science Park, Box 16	
	2100 Copenhagen O	
	Denmark	

You can get in touch with **MOSEK** using popular social media as well:

Blogger	https://blog.mosek.com/
Google Group	https://groups.google.com/forum/#!forum/mosek
Twitter	https://twitter.com/mosektw
Google+	https://plus.google.com/+Mosek/posts
Linkedin	https://www.linkedin.com/company/mosek-aps

In particular **Twitter** is used for news, updates and release announcements.

Chapter 3

License Agreement

Before using the **MOSEK** software, please read the license agreement available in the distribution at <MSKHOME>/mosek/9.0/mosek-eula.pdf or on the **MOSEK** website <https://mosek.com/products/license-agreement>.

MOSEK uses some third-party open-source libraries. Their license details follows.

zlib

MOSEK includes the *zlib* library obtained from the [zlib website](#). The license agreement for *zlib* is shown in [Listing 3.1](#).

Listing 3.1: *zlib* license.

```
zlib.h -- interface of the 'zlib' general purpose compression library
version 1.2.7, May 2nd, 2012

Copyright (C) 1995-2012 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied
warranty. In no event will the authors be held liable for any damages
arising from the use of this software.

Permission is granted to anyone to use this software for any purpose,
including commercial applications, and to alter it and redistribute it
freely, subject to the following restrictions:

1. The origin of this software must not be misrepresented; you must not
   claim that you wrote the original software. If you use this software
   in a product, an acknowledgment in the product documentation would be
   appreciated but is not required.
2. Altered source versions must be plainly marked as such, and must not be
   misrepresented as being the original software.
3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly          Mark Adler
jloup@gzip.org            madler@alumni.caltech.edu
```

fplib

MOSEK includes the floating point formatting library developed by David M. Gay obtained from the [netlib website](#). The license agreement for *fplib* is shown in [Listing 3.2](#).

Listing 3.2: *fplib* license.

```
/*****
 *
```

(continues on next page)


```
* The author of this software is David M. Gay.
*
* Copyright (c) 1991, 2000, 2001 by Lucent Technologies.
*
* Permission to use, copy, modify, and distribute this software for any
* purpose without fee is hereby granted, provided that this entire notice
* is included in all copies of any software which is or includes a copy
* or modification of this software and in all copies of the supporting
* documentation for such software.
*
* THIS SOFTWARE IS BEING PROVIDED "AS IS", WITHOUT ANY EXPRESS OR IMPLIED
* WARRANTY. IN PARTICULAR, NEITHER THE AUTHOR NOR LUCENT MAKES ANY
* REPRESENTATION OR WARRANTY OF ANY KIND CONCERNING THE MERCHANTABILITY
* OF THIS SOFTWARE OR ITS FITNESS FOR ANY PARTICULAR PURPOSE.
*
*****/
```

Zstandard

MOSEK includes the *Zstandard* library developed by Facebook obtained from [github/zstd](https://github.com/facebook/zstd). The license agreement for *Zstandard* is shown in [Listing 3.3](#).

Listing 3.3: *Zstandard* license.

```
BSD License

For Zstandard software

Copyright (c) 2016-present, Facebook, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification,
are permitted provided that the following conditions are met:

* Redistributions of source code must retain the above copyright notice, this
  list of conditions and the following disclaimer.

* Redistributions in binary form must reproduce the above copyright notice,
  this list of conditions and the following disclaimer in the documentation
  and/or other materials provided with the distribution.

* Neither the name Facebook nor the names of its contributors may be used to
  endorse or promote products derived from this software without specific
  prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND
ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED
WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE
DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR
ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES
(INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES;
LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON
ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS
SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

Chapter 4

Installation

In this section we discuss how to install and setup the **MOSEK** Optimizer API for C.

Important: Before running this **MOSEK** interface please make sure that you:

- Installed **MOSEK** correctly. Some operating systems require extra steps. See the [Installation guide](#) for instructions and common troubleshooting tips.
 - Set up a license. See the [Licensing guide](#) for instructions.
-

Compatibility

The Optimizer API for C is compatible with the following compiler tool chains:

Platform	Supported compiler	Framework
Linux 64 bit	gcc (≥ 4.5)	glibc (≥ 2.12)
Mac OS 64 bit	Xcode (≥ 5)	MAC OS SDK (≥ 10.7)
Windows 32 and 64 bit	Visual Studio (≥ 2010)	

In many cases older versions can also be used.

Locating files in the MOSEK Optimization Suite

The relevant files of the Optimizer API for C are organized as reported in [Table 4.1](#).

Table 4.1: Relevant files for the Optimizer API for C.

Relative Path	Description	Label
<MSKHOME>/mosek/9.0/tools/platform/<PLATFORM>/h	Header files	<HEADERDIR>
<MSKHOME>/mosek/9.0/tools/platform/<PLATFORM>/bin	Libraries and DLLs	<LIBDIR>
<MSKHOME>/mosek/9.0/tools/examples/c	Examples	<EXDIR>
<MSKHOME>/mosek/9.0/tools/examples/data	Additional data	<MISCDIR>

where

- <MSKHOME> is the folder in which the **MOSEK** Optimization Suite has been installed,
- <PLATFORM> is the actual platform among those supported by **MOSEK**, i.e. win32x86, win64x86, linux64x86 or osx64x86.

Setting up the paths

To compile and link C code using the Optimizer API for C, the relevant path to the header file and library must be included, and run-time dependencies must be resolved. Hence to compile, one should add appropriate compiler and linker options. Details vary depending on the operating system and compiler. See the `Makefile` included in the distribution under <MSKHOME>/mosek/9.0/tools/examples/c for a full working example. Examples are given below.

Linux

```
gcc file.c -o file -I<HEADERDIR> -L<LIBDIR> -Wl,-rpath-link,<LIBDIR> -Wl,-rpath=  
-><LIBDIR> -lmosek64
```

The shared library libmosek64.so.9.0 must be available at runtime.

Windows, 64bit

```
cl.exe /I<HEADERDIR> file.c /link /LIBPATH:<LIBDIR> /out:file.exe mosek64_9_0.lib
```

The shared library mosek64_9_0.dll must be available at runtime.

Windows, 32bit

```
cl.exe /I<HEADERDIR> file.c /link /LIBPATH:<LIBDIR> /out:file.exe mosek9_0.lib
```

The shared library mosek9_0.dll must be available at runtime.

Mac OS

```
clang file.c -o file -I<HEADERDIR> -L<LIBDIR> -Wl,-headerpad,128 -lmosek64  
install_name_tool -change libmosek64.9.0.dylib <LIBDIR>/libmosek64.9.0.dylib file
```

The shared library libmosek64.9.0.dylib must be registered and available at runtime.

4.1 Testing the Installation and Compiling Examples

This section describes how to verify that **MOSEK** has been installed correctly, and how to build and execute the C examples distributed with **MOSEK**.

4.1.1 Windows

Compiling examples using NMake

The example directory <EXDIR> contains makefiles for use with Microsoft NMake. These makefiles requires that the Visual Studio tool chain is setup. Usually, the submenu containing Visual Studio also contains a Visual Studio *Command Prompt* which does the necessary setup.

To build the examples, open a DOS box and change directory to <EXDIR>. This directory contains a makefile named *Makefile*. To compile all examples, run the command

```
nmake /f Makefile all
```

To build only a single example instead of all examples, replace *all* by the corresponding executable name. For example, to build *lo1.exe* type

```
nmake /f Makefile lo1.exe
```

Compiling from command line

To compile and execute a distributed example, such as *lo1.c*, do the following:

1. Compile the example into an executable *lo1.exe* (we assume that the Visual Studio C compiler *cl.exe* is available). For 64-bit Windows:

```
cl <EXDIR>\lo1.c /I <HEADERDIR> /link <LIBDIR>\mosek64_9_0.lib
```

2. To run the compiled example, enter

```
lo1.exe
```

Adding MOSEK to a Visual Studio Project

The following walk-through is specific for Microsoft Visual Studio 2012, but may work for other versions too. To compile a project linking to **MOSEK** in Visual Studio, the following steps are necessary:

1. Create a project or open an existing project in Visual Studio.
2. In the **Solution Explorer** right-click on the relevant project and select **Properties**. This will open the **Property pages** dialog.
3. In the selection box **Configuration:** select **All Configurations**.
4. In the tree-view open **Configuration Properties** → **C/C++** → **General**.
5. In the properties click the **Additional Include Directories** field and select edit.
6. Click on the **New Folder** button and write the *full path* to the **h** header file or browse for the file. For example, for 64-bit Windows use <HEADERDIR>.
7. Click **OK**.
8. Back in the **Property Pages** dialog select from the tree-view **Configuration Properties** → **Linker** → **Input**.
9. In the properties view click in the **Additional Dependencies** field and select edit. This will open the **Additional Dependencies** dialog.
10. Add the full path of the **MOSEK lib**. For example, for 64-bit Windows:

<LIBDIR>\mosek64_9_0.lib
11. Click **OK**.
12. Back in the **Property Pages** dialog click **OK**.

If you have selected to link with the 64 bit version of **MOSEK** you must also target the 64-bit platform. To do this follow the steps below:

1. Open the **property pages** for that project.
2. Click **Configuration Manager** to open the Configuration Manager Dialog Box.
3. Click the **Active Solution Platform** list, and then select the **New** option to open the New Solution Platform Dialog Box.
4. Click the Type or select the new platform drop-down arrow, and then select the x64 platform.
5. Click **OK**. The platform you selected in the preceding step will appear under Active Solution Platform in the Configuration Manager dialog box.

4.1.2 Mac OS and Linux

The example directory <EXDIR> contains makefiles for use with GNU Make. To build the examples enter

```
make -f Makefile all
```

To build one example instead of all examples, replace **all** by the corresponding executable name. For example, to build the **lo1** executable enter

```
make -f Makefile lo1
```

Chapter 5

Design Overview

5.1 Modeling

Optimizer API for C is an interface for specifying optimization problems directly in matrix form. It means that an optimization problem such as:

$$\begin{array}{ll}\text{minimize} & c^T x \\ \text{subject to} & Ax \leq b, \\ & x \in \mathcal{K}\end{array}$$

is specified by describing the matrix A , vectors b, c and a list of cones \mathcal{K} directly.

The main characteristics of this interface are:

- **Simplicity:** once the problem data is assembled in matrix form, it is straightforward to input it into the optimizer.
- **Exploiting sparsity:** data is entered in sparse format, enabling huge, sparse problems to be defined and solved efficiently.
- **Efficiency:** the Optimizer API incurs almost no overhead between the user's representation of the problem and **MOSEK**'s internal one.

Optimizer API for C does not aid with modeling. It is the user's responsibility to express the problem in **MOSEK**'s standard form, introducing, if necessary, auxiliary variables and constraints. See [Sec. 12](#) for the precise formulations of problems **MOSEK** solves.

5.2 “Hello World!” in MOSEK

Here we present the most basic workflow pattern when using Optimizer API for C.

Creating an environment and task

Every interaction with **MOSEK** using Optimizer API for C begins by creating a **MOSEK environment**. It coordinates the access to **MOSEK** from the current process.

In most cases the user does not interact directly with the environment, except for creating optimization **tasks**, which contain actual problem specifications and where optimization takes place. An environment can host multiple tasks.

Defining tasks

After a task is created, the input data can be specified. An optimization problem consists of several components; objective, objective sense, constraints, variable bounds etc. See [Sec. 6](#) for basic tutorials on how to specify and solve various types of optimization problems.

Retrieving the solutions

When the model is set up, the optimizer is invoked with the call to *MSK_optimize*. When the optimization is over, the user can check the results and retrieve numerical values. See further details in Sec. 7.

We refer also to Sec. 7 for information about more advanced mechanisms of interacting with the solver.

Source code example

Below is the most basic code sample that defines and solves a trivial optimization problem

$$\begin{array}{ll}\text{minimize} & x \\ \text{subject to} & 2.0 \leq x \leq 3.0.\end{array}$$

For simplicity the example does not contain any error or status checks.

Listing 5.1: “Hello World!” in MOSEK

```
#include "mosek.h"
#include <stdio.h>

/* Error checking not included */
int main() {
    MSKrescodee      r, trmcode;
    MSKenv_t         env = NULL;
    MSKtask_t        task = NULL;
    double           xx = 0.0;

    MSK_makeenv(&env, NULL);           // Create environment
    MSK_maketask(env, 0, 1, &task);    // Create task

    MSK_appendvars(task, 1);           // 1 variable x
    MSK_putcj(task, 0, 1.0);          // c_0 = 1.0
    MSK_putvarbound(task, 0, MSK_BK_RA, 2.0, 3.0); // 2.0 <= x <= 3.0
    MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MINIMIZE); // Minimize

    MSK_optimizetrm(task, &trmcode);  // Optimize

    MSK_getxx(task, MSK_SOL_ITR, &xx); // Get solution
    printf("Solution x = %f\n", xx);    // Print solution

    MSK_deletetask(&task); // Clean up task
    MSK_deleteenv(&env);   // Clean up environment
    return 0;
}
```

Chapter 6

Optimization Tutorials

In this section we demonstrate how to set up basic types of optimization problems. Each short tutorial contains a working example of formulating problems, defining variables and constraints and retrieving solutions.

6.1 Linear Optimization

The simplest optimization problem is a purely linear problem. A *linear optimization problem* is a problem of the following form:

Minimize or maximize the objective function

$$\sum_{j=0}^{n-1} c_j x_j + c^f$$

subject to the linear constraints

$$l_k^c \leq \sum_{j=0}^{n-1} a_{kj} x_j \leq u_k^c, \quad k = 0, \dots, m-1,$$

and the bounds

$$l_j^x \leq x_j \leq u_j^x, \quad j = 0, \dots, n-1.$$

The problem description consists of the following elements:

- m and n — the number of constraints and variables, respectively,
- x — the variable vector of length n ,
- c — the coefficient vector of length n

$$c = \begin{bmatrix} c_0 \\ \vdots \\ c_{n-1} \end{bmatrix},$$

- c^f — fixed term in the objective,
- A — an $m \times n$ matrix of coefficients

$$A = \begin{bmatrix} a_{0,0} & \cdots & a_{0,(n-1)} \\ \vdots & \cdots & \vdots \\ a_{(m-1),0} & \cdots & a_{(m-1),(n-1)} \end{bmatrix},$$

- l^c and u^c — the lower and upper bounds on constraints,
- l^x and u^x — the lower and upper bounds on variables.

Please note that we are using 0 as the first index: x_0 is the first element in variable vector x .

6.1.1 Example LO1

The following is an example of a small linear optimization problem:

$$\begin{aligned} & \text{maximize} && 3x_0 &+& 1x_1 &+& 5x_2 &+& 1x_3 \\ & \text{subject to} && 3x_0 &+& 1x_1 &+& 2x_2 && = & 30, \\ & && 2x_0 &+& 1x_1 &+& 3x_2 &+& 1x_3 & \geq & 15, \\ & && && 2x_1 && &+& 3x_3 & \leq & 25, \end{aligned} \tag{6.1}$$

under the bounds

$$\begin{aligned} 0 &\leq x_0 \leq \infty, \\ 0 &\leq x_1 \leq 10, \\ 0 &\leq x_2 \leq \infty, \\ 0 &\leq x_3 \leq \infty. \end{aligned}$$

Solving the problem

To solve the problem above we go through the following steps:

1. Create an environment.
2. Create an optimization task.
3. Load a problem into the task object.
4. Optimization.
5. Extracting the solution.

Below we explain each of these steps.

Create an environment.

Before setting up the optimization problem, a **MOSEK** environment must be created. All tasks in the program should share the same environment.

```
r = MSK_makeenv(&env, NULL);
```

Create an optimization task.

Next, an empty task object is created:

```
/* Create the optimization task. */
r = MSK_maketask(env, numcon, numvar, &task);

/* Directs the log task stream to the 'printstr' function. */
if (r == MSK_RES_OK)
    r = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);
```

We also connect a call-back function to the task log stream. Messages related to the task are passed to the call-back function. In this case the stream call-back function writes its messages to the standard output stream. See [Sec. 7.3](#).

Load a problem into the task object.

Before any problem data can be set, variables and constraints must be added to the problem via calls to the functions *MSK_appendcons* and *MSK_appendvars*.

```
/* Append 'numcon' empty constraints.
   The constraints will initially have no bounds. */
if (r == MSK_RES_OK)
    r = MSK_appendcons(task, numcon);

/* Append 'numvar' variables.
   The variables will initially be fixed at zero (x=0). */
if (r == MSK_RES_OK)
    r = MSK_appendvars(task, numvar);
```

New variables can now be referenced from other functions with indexes in $0, \dots, \text{numvar} - 1$ and new constraints can be referenced with indexes in $0, \dots, \text{numcon} - 1$. More variables and/or constraints can be appended later as needed, these will be assigned indexes from $\text{numvar}/\text{numcon}$ and up.

Next step is to set the problem data. We loop over each variable index $j = 0, \dots, \text{numvar} - 1$ calling functions to set problem data. We first set the objective coefficient $c_j = c[j]$ by calling the function *MSK_putcj*.

```
/* Set the linear term c_j in the objective.*/
if (r == MSK_RES_OK)
    r = MSK_putcj(task, j, c[j]);
```

Setting bounds on variables

The bounds on variables are stored in the arrays

```
const MSKboundkey bkg[] = {MSK_BK_LO,    MSK_BK_RA, MSK_BK_LO,    MSK_BK_LO    };
const double      blx[] = {0.0,         0.0,    0.0,         0.0        };
const double      bux[] = { +MSK_INFINITY, 10.0,    +MSK_INFINITY, +MSK_INFINITY };
```

and are set with calls to *MSK_putvarbound*.

```
/* Set the bounds on variable j.
   blx[j] <= x_j <= bux[j] */
if (r == MSK_RES_OK)
    r = MSK_putvarbound(task,
                        j,          /* Index of variable.*/
                        bkg[j],    /* Bound key.*/
                        blx[j],    /* Numerical value of lower bound.*/
                        bux[j]);  /* Numerical value of upper bound.*/
```

The *Bound key* stored in *bkg* specifies the type of the bound according to Table 6.1.

Table 6.1: Bound keys as defined in the enum *MSKboundkey*.

Bound key	Type of bound	Lower bound	Upper bound
<i>MSK_BK_FX</i>	$u_j = l_j$	Finite	Identical to the lower bound
<i>MSK_BK_FR</i>	Free	$-\infty$	$+\infty$
<i>MSK_BK_LO</i>	$l_j \leq \dots$	Finite	$+\infty$
<i>MSK_BK_RA</i>	$l_j \leq \dots \leq u_j$	Finite	Finite
<i>MSK_BK_UP</i>	$\dots \leq u_j$	$-\infty$	Finite

For instance $\text{bkg}[0] = \text{MSK_BK_LO}$ means that $x_0 \geq l_0^x$. Finally, the numerical values of the bounds on variables are given by

$$l_j^x = \text{blx}[j]$$

and

$$u_j^x = \text{bux}[j].$$

Defining the linear constraint matrix.

Recall that in our example the A matrix is given by

$$A = \begin{bmatrix} 3 & 1 & 2 & 0 \\ 2 & 1 & 3 & 1 \\ 0 & 2 & 0 & 3 \end{bmatrix}.$$

This matrix is stored in sparse format in the arrays:

```
const MSKint32t    aptrb[] = {0, 2, 5, 7},
                   aptre[] = {2, 5, 7, 9},
                   asub[]  = { 0, 1,
                               0, 1, 2,
                               0, 1,
                               1, 2
                             };
const double       aval[]  = { 3.0, 2.0,
                               1.0, 1.0, 2.0,
                               2.0, 3.0,
                               1.0, 3.0
                             };
```

The `aptrb`, `aptre`, `asub`, and `aval` arguments define the constraint matrix A in the column ordered sparse format (for details, see [Sec. 15.1.4](#)).

Using the function `MSK_putacol` we set column j of A

```
r = MSK_putacol(task,
                j,                /* Variable (column) index.*/
                aptre[j] - aptrb[j], /* Number of non-zeros in column j.*/
                asub + aptrb[j],    /* Pointer to row indexes of column j.*/
                aval + aptrb[j]); /* Pointer to Values of column j.*/
```

There are many alternative formats for entering the A matrix. See functions such as `MSK_putarow`, `MSK_putarowlist`, `MSK_putaijlist` and similar.

Finally, the bounds on each constraint are set by looping over each constraint index $i = 0, \dots, \text{numcon} - 1$

```
/* Set the bounds on constraints.
   for i=1, ..., numcon : blc[i] <= constraint i <= buc[i] */
for (i = 0; i < numcon && r == MSK_RES_OK; ++i)
    r = MSK_putconbound(task,
                        i,                /* Index of constraint.*/
                        bkc[i],          /* Bound key.*/
                        blc[i],          /* Numerical value of lower bound.*/
                        buc[i]);        /* Numerical value of upper bound.*/
```

Optimization

After the problem is set-up the task can be optimized by calling the function `MSK_optimizetrm`.

```
r = MSK_optimizetrm(task, &trmcode);
```

Extracting the solution.

After optimizing the status of the solution is examined with a call to `MSK_getsolsta`. If the solution status is reported as `MSK_SOL_STA_OPTIMAL` the solution is extracted in the lines below:

```
MSK_getxx(task,
           MSK_SOL_BAS, /* Request the basic solution. */
           xx);
```

The `MSK_getxx` function obtains the solution. **MOSEK** may compute several solutions depending on the optimizer employed. In this example the *basic solution* is requested by setting the first argument to `MSK_SOL_BAS`.

Source code

The complete source code `1o1.c` of this example appears below. See also `1o2.c` for a version where the *A* matrix is entered row-wise.

Listing 6.1: Linear optimization example.

```
#include <stdio.h>
#include "mosek.h"

/* This function prints log output from MOSEK to the terminal. */
static void MSKAPI printstr(void *handle,
                           const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char *argv[])
{
    const MSKint32t    numvar = 4,
                      numcon = 3;

    const double       c[]    = {3.0, 1.0, 5.0, 1.0};
    /* Below is the sparse representation of the A
       matrix stored by column. */
    const MSKint32t    aptrb[] = {0, 2, 5, 7},
                      aptre[] = {2, 5, 7, 9},
                      asub[]  = { 0, 1,
                                0, 1, 2,
                                0, 1,
                                1, 2
                                };

    const double       aval[] = { 3.0, 2.0,
                                1.0, 1.0, 2.0,
                                2.0, 3.0,
                                1.0, 3.0
                                };

    /* Bounds on constraints. */
    const MSKboundkeye bkc[] = {MSK_BK_FX, MSK_BK_LO, MSK_BK_UP };
    const double       blc[] = {30.0, 15.0, -MSK_INFINITY};
    const double       buc[] = {30.0, +MSK_INFINITY, 25.0 };
    /* Bounds on variables. */
    const MSKboundkeye bvx[] = {MSK_BK_LO, MSK_BK_RA, MSK_BK_LO, MSK_BK_LO };
    const double       blx[] = {0.0, 0.0, 0.0, 0.0 };
    const double       bux[] = { +MSK_INFINITY, 10.0, +MSK_INFINITY, +MSK_INFINITY };
    MSKenv_t           env = NULL;
    MSKtask_t           task = NULL;
    MSKrescodee         r;
    MSKint32t           i, j;

    /* Create the mosek environment. */
    r = MSK_makeenv(&env, NULL);

    if (r == MSK_RES_OK)
    {
        /* Create the optimization task. */
        r = MSK_maketask(env, numcon, numvar, &task);
    }
}
```

(continues on next page)

```

/* Directs the log task stream to the 'printstr' function. */
if (r == MSK_RES_OK)
    r = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

/* Append 'numcon' empty constraints.
   The constraints will initially have no bounds. */
if (r == MSK_RES_OK)
    r = MSK_appendcons(task, numcon);

/* Append 'numvar' variables.
   The variables will initially be fixed at zero (x=0). */
if (r == MSK_RES_OK)
    r = MSK_appendvars(task, numvar);

for (j = 0; j < numvar && r == MSK_RES_OK; ++j)
{
    /* Set the linear term c_j in the objective.*/
    if (r == MSK_RES_OK)
        r = MSK_putcj(task, j, c[j]);

    /* Set the bounds on variable j.
       blx[j] <= x_j <= bux[j] */
    if (r == MSK_RES_OK)
        r = MSK_putvarbound(task,
                               j,           /* Index of variable.*/
                               bkc[j],     /* Bound key.*/
                               blx[j],     /* Numerical value of lower bound.*/
                               bux[j]);    /* Numerical value of upper bound.*/

    /* Input column j of A */
    if (r == MSK_RES_OK)
        r = MSK_putacol(task,
                          j,           /* Variable (column) index.*/
                          aptre[j] - aptrb[j], /* Number of non-zeros in column j.*/
                          asub + aptrb[j], /* Pointer to row indexes of column j.*/
                          aval + aptrb[j]); /* Pointer to Values of column j.*/
}

/* Set the bounds on constraints.
   for i=1, ..., numcon : blc[i] <= constraint i <= buc[i] */
for (i = 0; i < numcon && r == MSK_RES_OK; ++i)
    r = MSK_putconbound(task,
                          i,           /* Index of constraint.*/
                          bkc[i],     /* Bound key.*/
                          blc[i],     /* Numerical value of lower bound.*/
                          buc[i]);    /* Numerical value of upper bound.*/

/* Maximize objective function. */
if (r == MSK_RES_OK)
    r = MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE);

if (r == MSK_RES_OK)
{
    MSKrescodeee trmcode;

    /* Run optimizer */
    r = MSK_optimizetrm(task, &trmcode);

    /* Print a summary containing information

```

```

    about the solution for debugging purposes. */
    MSK_solutionsummary(task, MSK_STREAM_LOG);

    if (r == MSK_RES_OK)
    {
        MSKsolstae solsta;

        if (r == MSK_RES_OK)
            r = MSK_getsolsta(task,
                               MSK_SOL_BAS,
                               &solsta);

        switch (solsta)
        {
            case MSK_SOL_STA_OPTIMAL:
            {
                double *xx = (double*) calloc(numvar, sizeof(double));
                if (xx)
                {
                    MSK_getxx(task,
                               MSK_SOL_BAS,    /* Request the basic solution. */
                               xx);

                    printf("Optimal primal solution\n");
                    for (j = 0; j < numvar; ++j)
                        printf("x[%d]: %e\n", j, xx[j]);

                    free(xx);
                }
                else
                    r = MSK_RES_ERR_SPACE;

                break;
            }
            case MSK_SOL_STA_DUAL_INFEAS_CER:
            case MSK_SOL_STA_PRIM_INFEAS_CER:
                printf("Primal or dual infeasibility certificate found.\n");
                break;
            case MSK_SOL_STA_UNKNOWN:
            {
                char symname[MSK_MAX_STR_LEN];
                char desc[MSK_MAX_STR_LEN];

                /* If the solutions status is unknown, print the termination code
                   indicating why the optimizer terminated prematurely. */

                MSK_getcodedesc(trmcode,
                               symname,
                               desc);

                printf("The solution status is unknown.\n");
                printf("The optimizer terminated with code: %s\n", symname);
                break;
            }
            default:
                printf("Other solution status.\n");
                break;
        }
    }
}

if (r != MSK_RES_OK)

```

(continued from previous page)

```
{
    /* In case of an error print error code and description. */
    char symname[MSK_MAX_STR_LEN];
    char desc[MSK_MAX_STR_LEN];

    printf("An error occurred while optimizing.\n");
    MSK_getcodedesc(r,
                    symname,
                    desc);
    printf("Error %s - '%s'\n", symname, desc);
}

/* Delete the task and the associated data. */
MSK_deletetask(&task);
}

/* Delete the environment and the associated data. */
MSK_deleteenv(&env);

return r;
}
```

6.2 Quadratic Optimization

MOSEK can solve quadratic and quadratically constrained problems, as long as they are convex. This class of problems can be formulated as follows:

$$\begin{aligned} & \text{minimize} && \frac{1}{2}x^T Q^o x + c^T x + c^f \\ & \text{subject to} && \begin{aligned} l_k^c &\leq \frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{k,j} x_j &\leq u_k^c, & k = 0, \dots, m-1, \\ l_j^x &\leq x_j &\leq u_j^x, & j = 0, \dots, n-1. \end{aligned} \end{aligned} \quad (6.2)$$

Without loss of generality it is assumed that Q^o and Q^k are all symmetric because

$$x^T Q x = \frac{1}{2} x^T (Q + Q^T) x.$$

This implies that a non-symmetric Q can be replaced by the symmetric matrix $\frac{1}{2}(Q + Q^T)$.

The problem is required to be convex. More precisely, the matrix Q^o must be positive semi-definite and the k th constraint must be of the form

$$l_k^c \leq \frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{k,j} x_j \quad (6.3)$$

with a negative semi-definite Q^k or of the form

$$\frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{k,j} x_j \leq u_k^c.$$

with a positive semi-definite Q^k . This implies that quadratic equalities are *not* allowed. Specifying a non-convex problem will result in an error when the optimizer is called.

A matrix is positive semidefinite if all the eigenvalues of Q are nonnegative. An alternative statement of the positive semidefinite requirement is

$$x^T Q x \geq 0, \quad \forall x.$$

If the convexity (i.e. semidefiniteness) conditions are not met **MOSEK** will not produce reliable results or work at all.

6.2.1 Example: Quadratic Objective

We look at a small problem with linear constraints and quadratic objective:

$$\begin{aligned} & \text{minimize} && x_1^2 + 0.1x_2^2 + x_3^2 - x_1x_3 - x_2 \\ & \text{subject to} && 1 \leq x_1 + x_2 + x_3 \\ & && 0 \leq x. \end{aligned} \tag{6.4}$$

The matrix formulation of (6.4) has:

$$Q^o = \begin{bmatrix} 2 & 0 & -1 \\ 0 & 0.2 & 0 \\ -1 & 0 & 2 \end{bmatrix}, c = \begin{bmatrix} 0 \\ -1 \\ 0 \end{bmatrix}, A = \begin{bmatrix} 1 & 1 & 1 \end{bmatrix},$$

with the bounds:

$$l^c = 1, u^c = \infty, l^x = \begin{bmatrix} 0 \\ 0 \\ 0 \end{bmatrix} \text{ and } u^x = \begin{bmatrix} \infty \\ \infty \\ \infty \end{bmatrix}$$

Please note the explicit $\frac{1}{2}$ in the objective function of (6.2) which implies that diagonal elements must be doubled in Q , i.e. $Q_{11} = 2$ even though 1 is the coefficient in front of x_1^2 in (6.4).

Setting up the linear part

The linear parts (constraints, variables, objective) are set up using exactly the same methods as for linear problems, and we refer to Sec. 6.1 for all the details. The same applies to technical aspects such as defining an optimization task, retrieving the solution and so on.

Setting up the quadratic objective

The quadratic objective is specified using the function `MSK_putqobj`. Since Q^o is symmetric only the lower triangular part of Q^o is inputted. In fact entries from above the diagonal may *not* appear in the input.

The lower triangular part of the matrix Q^o is specified using an unordered sparse triplet format (for details, see Sec. 15.1.4):

```
qsubi[0] = 0;  qsubj[0] = 0;  qval[0] = 2.0;
qsubi[1] = 1;  qsubj[1] = 1;  qval[1] = 0.2;
qsubi[2] = 2;  qsubj[2] = 0;  qval[2] = -1.0;
qsubi[3] = 2;  qsubj[3] = 2;  qval[3] = 2.0;
```

Please note that

- only non-zero elements are specified (any element not specified is 0 by definition),
- the order of the non-zero elements is insignificant, and
- *only* the lower triangular part should be specified.

Finally, this definition of Q^o is loaded into the task:

```
r = MSK_putqobj(task, NUMQNZ, qsubi, qsubj, qval);
```

Source code

Listing 6.2: Source code implementing problem (6.4).

```
#include <stdio.h>

#include "mosek.h" /* Include the MOSEK definition file. */

#define NUMCON 1 /* Number of constraints. */
#define NUMVAR 3 /* Number of variables. */
#define NUMANZ 3 /* Number of non-zeros in A. */
#define NUMQNZ 4 /* Number of non-zeros in Q. */

static void MSKAPI printstr(void *handle,
                           const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char *argv[])
{
    double          c[]    = {0.0, -1.0, 0.0};

    MSKboundkey     bkc[]  = {MSK_BK_LO};
    double          blc[]  = {1.0};
    double          buc[]  = { +MSK_INFINITY };

    MSKboundkey     bkc[]  = {MSK_BK_LO,
                              MSK_BK_LO,
                              MSK_BK_LO
                              };
    double          blx[]  = {0.0,
                              0.0,
                              0.0
                              };
    double          bux[]  = { +MSK_INFINITY,
                              +MSK_INFINITY,
                              +MSK_INFINITY
                              };

    MSKint32t       aptrb[] = {0, 1, 2},
    aptre[]         = {1, 2, 3},
    asub[]          = {0, 0, 0};
    double          aval[]  = {1.0, 1.0, 1.0};

    MSKint32t       qsubi[ NUMQNZ ];
    MSKint32t       qsubj[ NUMQNZ ];
    double          qval[ NUMQNZ ];

    MSKint32t       i, j;
    double          xx[ NUMVAR ];

    MSKenv_t        env = NULL;
    MSKtask_t       task = NULL;
    MSKrescodee     r;

    /* Create the mosek environment. */
    r = MSK_makeenv(&env, NULL);

    if (r == MSK_RES_OK)
    {
        /* Create the optimization task. */
        r = MSK_maketask(env, NUMCON, NUMVAR, &task);
    }
}
```

(continues on next page)


```

if (r == MSK_RES_OK)
{
    r = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

    /* Append 'NUMCON' empty constraints.
       The constraints will initially have no bounds. */
    if (r == MSK_RES_OK)
        r = MSK_appendcons(task, NUMCON);

    /* Append 'NUMVAR' variables.
       The variables will initially be fixed at zero (x=0). */
    if (r == MSK_RES_OK)
        r = MSK_appendvars(task, NUMVAR);

    /* Optionally add a constant term to the objective. */
    if (r == MSK_RES_OK)
        r = MSK_putcfix(task, 0.0);
    for (j = 0; j < NUMVAR && r == MSK_RES_OK; ++j)
    {
        /* Set the linear term c_j in the objective.*/
        if (r == MSK_RES_OK)
            r = MSK_putcj(task, j, c[j]);

        /* Set the bounds on variable j.
           blx[j] <= x_j <= bux[j] */
        if (r == MSK_RES_OK)
            r = MSK_putvarbound(task,
                                j,           /* Index of variable.*/
                                bkc[j],     /* Bound key.*/
                                blx[j],     /* Numerical value of lower bound.*/
                                bux[j]);    /* Numerical value of upper bound.*/

        /* Input column j of A */
        if (r == MSK_RES_OK)
            r = MSK_putacol(task,
                                j,           /* Variable (column) index.*/
                                aptre[j] - aptrb[j], /* Number of non-zeros in column j.*/
                                asub + aptrb[j], /* Pointer to row indexes of column j.*/
                                aval + aptrb[j]); /* Pointer to Values of column j.*/
    }

    /* Set the bounds on constraints.
       for i=1, ..., NUMCON : blc[i] <= constraint i <= buc[i] */
    for (i = 0; i < NUMCON && r == MSK_RES_OK; ++i)
        r = MSK_putconbound(task,
                                i,           /* Index of constraint.*/
                                bkc[i],     /* Bound key.*/
                                blc[i],     /* Numerical value of lower bound.*/
                                buc[i]);    /* Numerical value of upper bound.*/

    if (r == MSK_RES_OK)
    {
        /*
         * The lower triangular part of the Q
         * matrix in the objective is specified.
         */

        qsubi[0] = 0;   qsubj[0] = 0;   qval[0] = 2.0;
        qsubi[1] = 1;   qsubj[1] = 1;   qval[1] = 0.2;
    }
}

```

```

qsubi[2] = 2;   qsubj[2] = 0;   qval[2] = -1.0;
qsubi[3] = 2;   qsubj[3] = 2;   qval[3] = 2.0;

/* Input the Q for the objective. */

r = MSK_putqobj(task, NUMQNZ, qsubi, qsubj, qval);
}

if (r == MSK_RES_OK)
{
    MSKrescodee trmcode;

    /* Run optimizer */
    r = MSK_optimizetrm(task, &trmcode);

    /* Print a summary containing information
       about the solution for debugging purposes*/
    MSK_solutionsummary(task, MSK_STREAM_MSG);

    if (r == MSK_RES_OK)
    {
        MSKsolsta solsta;
        int j;

        MSK_getsolsta(task, MSK_SOL_ITR, &solsta);

        switch (solsta)
        {
            case MSK_SOL_STA_OPTIMAL:
                MSK_getxx(task,
                        MSK_SOL_ITR, /* Request the interior solution. */
                        xx);

                printf("Optimal primal solution\n");
                for (j = 0; j < NUMVAR; ++j)
                    printf("x[%d]: %e\n", j, xx[j]);

                break;

            case MSK_SOL_STA_DUAL_INFEAS_CER:
            case MSK_SOL_STA_PRIM_INFEAS_CER:
                printf("Primal or dual infeasibility certificate found.\n");
                break;

            case MSK_SOL_STA_UNKNOWN:
                printf("The status of the solution could not be determined. Termination code: %d.\n", trmcode);
                break;

            default:
                printf("Other solution status.");
                break;
        }
    }
    else
    {
        printf("Error while optimizing.\n");
    }
}

if (r != MSK_RES_OK)

```

(continued from previous page)

```
{
    /* In case of an error print error code and description. */
    char symname[MSK_MAX_STR_LEN];
    char desc[MSK_MAX_STR_LEN];

    printf("An error occurred while optimizing.\n");
    MSK_getcodedesc(r,
                    symname,
                    desc);
    printf("Error %s - '%s'\n", symname, desc);
}
}
MSK_deletetask(&task);
}
MSK_deleteenv(&env);

return (r);
} /* main */
```

6.2.2 Example: Quadratic constraints

In this section we show how to solve a problem with quadratic constraints. Please note that quadratic constraints are subject to the convexity requirement (6.3).

Consider the problem:

$$\begin{aligned} & \text{minimize} && x_1^2 + 0.1x_2^2 + x_3^2 - x_1x_3 - x_2 \\ & \text{subject to} && 1 \leq x_1 + x_2 + x_3 - x_1^2 - x_2^2 - 0.1x_3^2 + 0.2x_1x_3, \\ & && x \geq 0. \end{aligned}$$

This is equivalent to

$$\begin{aligned} & \text{minimize} && \frac{1}{2}x^T Q^o x + c^T x \\ & \text{subject to} && \frac{1}{2}x^T Q^0 x + Ax \geq b, \\ & && x \geq 0, \end{aligned} \tag{6.5}$$

where

$$Q^o = \begin{bmatrix} 2 & 0 & -1 \\ 0 & 0.2 & 0 \\ -1 & 0 & 2 \end{bmatrix}, c = [0 \quad -1 \quad 0]^T, A = [1 \quad 1 \quad 1], b = 1.$$

$$Q^0 = \begin{bmatrix} -2 & 0 & 0.2 \\ 0 & -2 & 0 \\ 0.2 & 0 & -0.2 \end{bmatrix}.$$

The linear parts and quadratic objective are set up the way described in the previous tutorial.

Setting up quadratic constraints

To add quadratic terms to the constraints we use the function `MSK_putqconk`.

```
qsubi[0] = 0;   qsubj[0] = 0;   qval[0] = -2.0;
qsubi[1] = 1;   qsubj[1] = 1;   qval[1] = -2.0;
qsubi[2] = 2;   qsubj[2] = 2;   qval[2] = -0.2;
qsubi[3] = 2;   qsubj[3] = 0;   qval[3] = 0.2;

/* Put Q~0 in constraint with index 0. */

r = MSK_putqconk(task,
                  0,
```

(continues on next page)

```

4,
qsubi,
qsubj,
qval);

```

While *MSK_putqconk* adds quadratic terms to a specific constraint, it is also possible to input all quadratic terms in one chunk using the *MSK_putqcon* function.

Source code

Listing 6.3: Implementation of the quadratically constrained problem (6.5).

```

#include <stdio.h>

#include "mosek.h" /* Include the MOSEK definition file. */

#define NUMCON 1 /* Number of constraints. */
#define NUMVAR 3 /* Number of variables. */
#define NUMANZ 3 /* Number of non-zeros in A. */
#define NUMQNZ 4 /* Number of non-zeros in Q. */

static void MSKAPI printstr(void *handle,
                           const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char *argv[])
{
    MSKrescodee r;

    double c[] = {0.0, -1.0, 0.0};

    MSKboundkeye bkc[] = {MSK_BK_LO};
    double blc[] = {1.0};
    double buc[] = {+MSK_INFINITY};

    MSKboundkeye bkc[] = {MSK_BK_LO,
                          MSK_BK_LO,
                          MSK_BK_LO};
    double blx[] = {0.0,
                   0.0,
                   0.0};
    double bux[] = {+MSK_INFINITY,
                   +MSK_INFINITY,
                   +MSK_INFINITY};

    MSKint32t aptrb[] = {0, 1, 2},
               aptre[] = {1, 2, 3},
               asub[] = {0, 0, 0};
    double aval[] = {1.0, 1.0, 1.0};
    MSKint32t qsubi[NUMQNZ],
               qsubj[NUMQNZ];
    double qval[NUMQNZ];

```

(continues on next page)

```

MSKint32t    j, i;
double       xx[NUMVAR];
MSKenv_t     env;
MSKtask_t    task;

/* Create the mosek environment. */
r = MSK_makeenv(&env, NULL);

if (r == MSK_RES_OK)
{
    /* Create the optimization task. */
    r = MSK_maketask(env, NUMCON, NUMVAR, &task);

    if (r == MSK_RES_OK)
    {
        r = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

        /* Append 'NUMCON' empty constraints.
           The constraints will initially have no bounds. */
        if (r == MSK_RES_OK)
            r = MSK_appendcons(task, NUMCON);

        /* Append 'NUMVAR' variables.
           The variables will initially be fixed at zero (x=0). */
        if (r == MSK_RES_OK)
            r = MSK_appendvars(task, NUMVAR);

        /* Optionally add a constant term to the objective. */
        if (r == MSK_RES_OK)
            r = MSK_putcfix(task, 0.0);
        for (j = 0; j < NUMVAR && r == MSK_RES_OK; ++j)
        {
            /* Set the linear term c_j in the objective.*/
            if (r == MSK_RES_OK)
                r = MSK_putcj(task, j, c[j]);

            /* Set the bounds on variable j.
               blx[j] <= x_j <= bux[j] */
            if (r == MSK_RES_OK)
                r = MSK_putvarbound(task,
                                     j,           /* Index of variable.*/
                                     bkc[j],      /* Bound key.*/
                                     blx[j],       /* Numerical value of lower bound.*/
                                     bux[j]);      /* Numerical value of upper bound.*/

            /* Input column j of A */
            if (r == MSK_RES_OK)
                r = MSK_putacol(task,
                                   j,           /* Variable (column) index.*/
                                   aptre[j] - aptrb[j], /* Number of non-zeros in column j.*/
                                   asub + aptrb[j], /* Pointer to row indexes of column j.*/
                                   aval + aptrb[j]); /* Pointer to Values of column j.*/
        }

        /* Set the bounds on constraints.
           for i=1, ..., NUMCON : blc[i] <= constraint i <= buc[i] */
        for (i = 0; i < NUMCON && r == MSK_RES_OK; ++i)
            r = MSK_putconbound(task,
                                 i,           /* Index of constraint.*/
                                 bkc[i],      /* Bound key.*/

```

```

        blc[i],      /* Numerical value of lower bound.*/
        buc[i]);    /* Numerical value of upper bound.*/

if (r == MSK_RES_OK)
{
    /*
     * The lower triangular part of the  $Q^0$ 
     * matrix in the objective is specified.
     */

    qsubi[0] = 0;  qsubj[0] = 0;  qval[0] = 2.0;
    qsubi[1] = 1;  qsubj[1] = 1;  qval[1] = 0.2;
    qsubi[2] = 2;  qsubj[2] = 0;  qval[2] = -1.0;
    qsubi[3] = 2;  qsubj[3] = 2;  qval[3] = 2.0;

    /* Input the  $Q^0$  for the objective. */

    r = MSK_putqobj(task, NUMQNZ, qsubi, qsubj, qval);
}

if (r == MSK_RES_OK)
{
    /*
     * The lower triangular part of the  $Q^0$ 
     * matrix in the first constraint is specified.
     * This corresponds to adding the term
     *  $-x_1^2 - x_2^2 - 0.1 x_3^2 + 0.2 x_1 x_3$ 
     */

    qsubi[0] = 0;  qsubj[0] = 0;  qval[0] = -2.0;
    qsubi[1] = 1;  qsubj[1] = 1;  qval[1] = -2.0;
    qsubi[2] = 2;  qsubj[2] = 2;  qval[2] = -0.2;
    qsubi[3] = 2;  qsubj[3] = 0;  qval[3] = 0.2;

    /* Put  $Q^0$  in constraint with index 0. */

    r = MSK_putqconk(task,
                     0,
                     4,
                     qsubi,
                     qsubj,
                     qval);
}

if (r == MSK_RES_OK)
    r = MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MINIMIZE);

if (r == MSK_RES_OK)
{
    MSKrescodee trmcode;

    /* Run optimizer */
    r = MSK_optimizetrm(task, &trmcode);

    /* Print a summary containing information
     * about the solution for debugging purposes*/
    MSK_solutionsummary(task, MSK_STREAM_LOG);

    if (r == MSK_RES_OK)
    {
        MSKsolstae solsta;

```

```

int j;

MSK_getsolsta(task, MSK_SOL_ITR, &solsta);

switch (solsta)
{
    case MSK_SOL_STA_OPTIMAL:
        MSK_getxx(task,
                   MSK_SOL_ITR,    /* Request the interior solution. */
                   xx);

        printf("Optimal primal solution\n");
        for (j = 0; j < NUMVAR; ++j)
            printf("x[%d]: %e\n", j, xx[j]);

        break;

    case MSK_SOL_STA_DUAL_INFEAS_CER:
    case MSK_SOL_STA_PRIM_INFEAS_CER:
        printf("Primal or dual infeasibility certificate found.\n");
        break;

    case MSK_SOL_STA_UNKNOWN:
        printf("The status of the solution could not be determined. Termination code: %d.\n", trmcode);
        break;

    default:
        printf("Other solution status.");
        break;
}
else
{
    printf("Error while optimizing.\n");
}

if (r != MSK_RES_OK)
{
    /* In case of an error print error code and description. */
    char symname[MSK_MAX_STR_LEN];
    char desc[MSK_MAX_STR_LEN];

    printf("An error occurred while optimizing.\n");
    MSK_getcodedesc(r,
                   symname,
                   desc);
    printf("Error %s - '%s'\n", symname, desc);
}

MSK_deletetask(&task);
}
MSK_deleteenv(&env);

return (r);
} /* main */

```

6.3 Conic Quadratic Optimization

Conic optimization is a generalization of linear optimization, allowing constraints of the type

$$x^t \in \mathcal{K}_t,$$

where x^t is a subset of the problem variables and \mathcal{K}_t is a convex cone. Since the set \mathbb{R}^n of real numbers is also a convex cone, we can simply write a compound conic constraint $x \in \mathcal{K}$ where $\mathcal{K} = \mathcal{K}_1 \times \cdots \times \mathcal{K}_l$ is a product of smaller cones and x is the full problem variable.

MOSEK can solve conic quadratic optimization problems of the form

$$\begin{array}{ll} \text{minimize} & c^T x + c^f \\ \text{subject to} & l^c \leq Ax \leq u^c, \\ & l^x \leq x \leq u^x, \\ & x \in \mathcal{K}, \end{array}$$

where the domain restriction, $x \in \mathcal{K}$, implies that all variables are partitioned into convex cones

$$x = (x^0, x^1, \dots, x^{p-1}), \quad \text{with } x^t \in \mathcal{K}_t \subseteq \mathbb{R}^{n_t}.$$

In this tutorial we describe how to use the two types of quadratic cones defined as:

- Quadratic cone:

$$\mathcal{Q}^n = \left\{ x \in \mathbb{R}^n : x_0 \geq \sqrt{\sum_{j=1}^{n-1} x_j^2} \right\}.$$

- Rotated quadratic cone:

$$\mathcal{Q}_r^n = \left\{ x \in \mathbb{R}^n : 2x_0x_1 \geq \sum_{j=2}^{n-1} x_j^2, \quad x_0 \geq 0, \quad x_1 \geq 0 \right\}.$$

For other types of cones supported by **MOSEK** see [Sec. 6.4](#), [Sec. 6.5](#), [Sec. 6.6](#). See *MSK_appendcone* for a list and definitions of available cone types. Different cone types can appear together in one optimization problem.

For example, the following constraint:

$$(x_4, x_0, x_2) \in \mathcal{Q}^3$$

describes a convex cone in \mathbb{R}^3 given by the inequality:

$$x_4 \geq \sqrt{x_0^2 + x_2^2}.$$

Furthermore, each variable may belong to one cone at most. The constraint $x_i - x_j = 0$ would however allow x_i and x_j to belong to different cones with same effect.

6.3.1 Example CQO1

Consider the following conic quadratic problem which involves some linear constraints, a quadratic cone and a rotated quadratic cone.

$$\begin{array}{ll} \text{minimize} & x_4 + x_5 + x_6 \\ \text{subject to} & x_1 + x_2 + 2x_3 = 1, \\ & x_1, x_2, x_3 \geq 0, \\ & x_4 \geq \sqrt{x_1^2 + x_2^2}, \\ & 2x_5x_6 \geq x_3^2 \end{array} \tag{6.6}$$

Setting up the linear part

The linear parts (constraints, variables, objective) are set up using exactly the same methods as for linear problems, and we refer to [Sec. 6.1](#) for all the details. The same applies to technical aspects such as defining an optimization task, retrieving the solution and so on.

Setting up the conic constraints

A cone is defined using the function `MSK_appendcone`:

```
csub[0] = 3;
csub[1] = 0;
csub[2] = 1;

r = MSK_appendcone(task,
                   MSK_CT_QUAD,
                   0.0, /* Can be set to 0.0 */
                   3,
                   csub);
```

The first argument selects the type of quadratic cone, in this case either `MSK_CT_QUAD` for a *quadratic cone* or `MSK_CT_RQUAD` for a *rotated quadratic cone*. The second parameter is currently ignored and passing 0.0 will work.

The next argument denotes the number of variables in the cone, in this case 3, and the last argument is a list of indexes of the variables appearing in the cone.

Variants of this method are available to append multiple cones at a time.

Source code

Listing 6.4: Source code solving problem (6.6).

```
#include <stdio.h>
#include "mosek.h" /* Include the MOSEK definition file. */

static void MSKAPI printstr(void *handle,
                             const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char *argv[])
{
    MSKrescodee r;

    const MSKint32t numvar = 6,
                  numcon = 1;

    MSKboundkeye bkc[] = { MSK_BK_FX };
    double       blc[] = { 1.0 };
    double       buc[] = { 1.0 };

    MSKboundkeye bkc[] = {MSK_BK_LO,
                          MSK_BK_LO,
                          MSK_BK_LO,
                          MSK_BK_FR,
                          MSK_BK_FR,
                          MSK_BK_FR
                          };
    double       blx[] = {0.0,
                          0.0,
                          0.0,
```

(continues on next page)

```

        -MSK_INFINITY,
        -MSK_INFINITY,
        -MSK_INFINITY
    };

    double    bux[] = { +MSK_INFINITY,
                        +MSK_INFINITY,
                        +MSK_INFINITY,
                        +MSK_INFINITY,
                        +MSK_INFINITY,
                        +MSK_INFINITY
    };

    double    c[]    = {0.0,
                        0.0,
                        0.0,
                        1.0,
                        1.0,
                        1.0
    };

    MSKint32t  aptrb[] = {0, 1, 2, 3, 3, 3},
               aptre[] = {1, 2, 3, 3, 3, 3},
               asub[]  = {0, 0, 0, 0};
    double     aval[]  = {1.0, 1.0, 2.0};

    MSKint32t  i, j, csub[3];

    MSKenv_t    env  = NULL;
    MSKtask_t   task = NULL;

    /* Create the mosek environment. */
    r = MSK_makeenv(&env, NULL);

    if (r == MSK_RES_OK)
    {
        /* Create the optimization task. */
        r = MSK_maketask(env, numcon, numvar, &task);

        if (r == MSK_RES_OK)
        {
            MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

            /* Append 'numcon' empty constraints.
             The constraints will initially have no bounds. */
            if (r == MSK_RES_OK)
                r = MSK_appendcons(task, numcon);

            /* Append 'numvar' variables.
             The variables will initially be fixed at zero (x=0). */
            if (r == MSK_RES_OK)
                r = MSK_appendvars(task, numvar);

            for (j = 0; j < numvar && r == MSK_RES_OK; ++j)
            {
                /* Set the linear term c_j in the objective.*/
                if (r == MSK_RES_OK)
                    r = MSK_putcj(task, j, c[j]);

                /* Set the bounds on variable j.
                 blx[j] <= x_j <= bux[j] */
            }
        }
    }

```

(continues on next page)

```

if (r == MSK_RES_OK)
    r = MSK_putvarbound(task,
                        j,          /* Index of variable.*/
                        bkc[j],    /* Bound key.*/
                        blc[j],    /* Numerical value of lower bound.*/
                        buc[j]);   /* Numerical value of upper bound.*/

/* Input column j of A */
if (r == MSK_RES_OK)
    r = MSK_putacol(task,
                    j,          /* Variable (column) index.*/
                    aptre[j] - aptrb[j], /* Number of non-zeros in column j.*/
                    asub + aptrb[j], /* Pointer to row indexes of column j.*/
                    aval + aptrb[j]); /* Pointer to Values of column j.*/

}

/* Set the bounds on constraints.
for i=1, ..., numcon : blc[i] <= constraint i <= buc[i] */
for (i = 0; i < numcon && r == MSK_RES_OK; ++i)
    r = MSK_putconbound(task,
                        i,          /* Index of constraint.*/
                        bkc[i],    /* Bound key.*/
                        blc[i],    /* Numerical value of lower bound.*/
                        buc[i]);   /* Numerical value of upper bound.*/

if (r == MSK_RES_OK)
{
    /* Append the first cone. */
    csub[0] = 3;
    csub[1] = 0;
    csub[2] = 1;

    r = MSK_appendcone(task,
                      MSK_CT_QUAD,
                      0.0, /* Can be set to 0.0 */
                      3,
                      csub);
}

if (r == MSK_RES_OK)
{
    /* Append the second cone. */
    csub[0] = 4;
    csub[1] = 5;
    csub[2] = 2;

    r = MSK_appendcone(task,
                      MSK_CT_RQUAD,
                      0.0,
                      3,
                      csub);
}

if (r == MSK_RES_OK)
{
    MSKrescodeee trmcode;

    /* Run optimizer */
    r = MSK_optimizetrm(task, &trmcode);
}

```

```

/* Print a summary containing information
   about the solution for debugging purposes*/
MSK_solutionsummary(task, MSK_STREAM_MSG);

if (r == MSK_RES_OK)
{
    MSKsolstae solsta;

    MSK_getsolsta(task, MSK_SOL_ITR, &solsta);

    switch (solsta)
    {
        case MSK_SOL_STA_OPTIMAL:
        {
            double *xx = NULL;

            xx = calloc(numvar, sizeof(double));
            if (xx)
            {
                MSK_getxx(task,
                           MSK_SOL_ITR,    /* Request the interior solution. */
                           xx);

                printf("Optimal primal solution\n");
                for (j = 0; j < numvar; ++j)
                    printf("x[%d]: %e\n", j, xx[j]);
            }
            else
            {
                r = MSK_RES_ERR_SPACE;
            }
            free(xx);
        }
        break;
        case MSK_SOL_STA_DUAL_INFEAS_CER:
        case MSK_SOL_STA_PRIM_INFEAS_CER:
            printf("Primal or dual infeasibility certificate found.\n");
            break;
        case MSK_SOL_STA_UNKNOWN:
            printf("The status of the solution could not be determined. Termination code: %d.
↪\n", trmcode);
            break;
        default:
            printf("Other solution status.");
            break;
    }
}
else
{
    printf("Error while optimizing.\n");
}

if (r != MSK_RES_OK)
{
    /* In case of an error print error code and description. */
    char symname[MSK_MAX_STR_LEN];
    char desc[MSK_MAX_STR_LEN];

    printf("An error occurred while optimizing.\n");
}

```

```

    MSK_getcodedesc(r,
                    symname,
                    desc);
    printf("Error %s - '%s'\n", symname, desc);
}
}
/* Delete the task and the associated data. */
MSK_deletetask(&task);
}

/* Delete the environment and the associated data. */
MSK_deleteenv(&env);

return (r);
} /* main */

```

6.4 Power Cone Optimization

Conic optimization is a generalization of linear optimization, allowing constraints of the type

$$x^t \in \mathcal{K}_t,$$

where x^t is a subset of the problem variables and \mathcal{K}_t is a convex cone. Since the set \mathbb{R}^n of real numbers is also a convex cone, we can simply write a compound conic constraint $x \in \mathcal{K}$ where $\mathcal{K} = \mathcal{K}_1 \times \dots \times \mathcal{K}_l$ is a product of smaller cones and x is the full problem variable.

MOSEK can solve conic optimization problems of the form

$$\begin{aligned}
 & \text{minimize} && c^T x + c^f \\
 & \text{subject to} && l^c \leq Ax \leq u^c, \\
 & && l^x \leq x \leq u^x, \\
 & && x \in \mathcal{K},
 \end{aligned}$$

where the domain restriction, $x \in \mathcal{K}$, implies that all variables are partitioned into convex cones

$$x = (x^0, x^1, \dots, x^{p-1}), \quad \text{with } x^t \in \mathcal{K}_t \subseteq \mathbb{R}^{n_t}.$$

In this tutorial we describe how to use the power cone. The primal power cone of dimension n with parameter $0 < \alpha < 1$ is defined as:

$$\mathcal{P}_n^{\alpha, 1-\alpha} = \left\{ x \in \mathbb{R}^n : x_0^\alpha x_1^{1-\alpha} \geq \sqrt{\sum_{i=2}^{n-1} x_i^2}, \ x_0, x_1 \geq 0 \right\}.$$

In particular, the most important special case is the three-dimensional power cone family:

$$\mathcal{P}_3^{\alpha, 1-\alpha} = \{x \in \mathbb{R}^3 : x_0^\alpha x_1^{1-\alpha} \geq |x_2|, \ x_0, x_1 \geq 0\}.$$

For example, the conic constraint $(x, y, z) \in \mathcal{P}_3^{0.25, 0.75}$ is equivalent to $x^{0.25} y^{0.75} \geq |z|$, or simply $xy^3 \geq z^4$ with $x, y \geq 0$.

MOSEK also supports the dual power cone:

$$(\mathcal{P}_n^{\alpha, 1-\alpha})^* = \left\{ x \in \mathbb{R}^n : \left(\frac{x_0}{\alpha}\right)^\alpha \left(\frac{x_1}{1-\alpha}\right)^{1-\alpha} \geq \sqrt{\sum_{i=2}^{n-1} x_i^2}, \ x_0, x_1 \geq 0 \right\}.$$

For other types of cones supported by **MOSEK** see [Sec. 6.3](#), [Sec. 6.5](#), [Sec. 6.6](#). See [MSK_appendcone](#) for a list and definitions of available cone types. Different cone types can appear together in one optimization problem.

Furthermore, each variable may belong to one cone at most. The constraint $x_i - x_j = 0$ would however allow x_i and x_j to belong to different cones with same effect.

6.4.1 Example POW1

Consider the following optimization problem which involves powers of variables:

$$\begin{aligned} & \text{maximize} && x^{0.2}y^{0.8} + z^{0.4} - x \\ & \text{subject to} && x + y + \frac{1}{2}z = 2, \\ & && x, y, z \geq 0. \end{aligned} \tag{6.7}$$

With $(x, y, z) = (x_0, x_1, x_2)$ we convert it into conic form using auxiliary variables as bounds for the power expressions:

$$\begin{aligned} & \text{maximize} && x_3 + x_4 - x_0 \\ & \text{subject to} && x_0 + x_1 + \frac{1}{2}x_2 = 2, \\ & && (x_0, x_1, x_3) \in \mathcal{P}_3^{0.2, 0.8}, \\ & && (x_2, x_5, x_4) \in \mathcal{P}_3^{0.4, 0.6}, \\ & && x_5 = 1. \end{aligned} \tag{6.8}$$

Setting up the linear part

The linear parts (constraints, variables, objective) are set up using exactly the same methods as for linear problems, and we refer to [Sec. 6.1](#) for all the details. The same applies to technical aspects such as defining an optimization task, retrieving the solution and so on.

Setting up the conic constraints

A cone is defined using the function `MSK_appendcone`:

```
MSKint32t csub[2][3] = { {0, 1, 3}, {2, 5, 4} };
r = MSK_appendcone(task, MSK_CT_PPOW, 0.2, 3, csub[0]);
r = MSK_appendcone(task, MSK_CT_PPOW, 0.4, 3, csub[1]);
```

The first argument selects the type of power cone, that is `MSK_CT_PPOW`. The second argument is the cone parameter α . The remaining arguments list the variables which form the cone. Variants of this method are available to append multiple cones at a time.

The code below produces the answer of (6.7) which is

```
[ 0.06389298  0.78308564  2.30604283 ]
```

Source code

Listing 6.5: Source code solving problem (6.7).

```
#include <stdio.h>
#include "mosek.h" /* Include the MOSEK definition file. */

static void MSKAPI printstr(void *handle,
                             const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char *argv[])
{
    MSKrescodee r;

    const MSKint32t numvar = 6,
                    numcon = 1;

    MSKboundkeye btx[6];
```

(continues on next page)

```

double      blx[6], bux[6];

double      val[] = { 1.0, 1.0, -1.0 };
MSKint32t   sub[] = { 3, 4, 0 };

double      aval[] = { 1.0, 1.0, 0.5 };
MSKint32t   asub[] = { 0, 1, 2 };

MSKint32t   i, j;

MSKenv_t     env = NULL;
MSKtask_t    task = NULL;

/* Create the mosek environment. */
r = MSK_makeenv(&env, NULL);

if (r == MSK_RES_OK)
{
    /* Create the optimization task. */
    r = MSK_maketask(env, numcon, numvar, &task);

    if (r == MSK_RES_OK)
    {
        MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

        /* Append 'numcon' empty constraints.
         The constraints will initially have no bounds. */
        if (r == MSK_RES_OK)
            r = MSK_appendcons(task, numcon);

        /* Append 'numvar' variables.
         The variables will initially be fixed at zero (x=0). */
        if (r == MSK_RES_OK)
            r = MSK_appendvars(task, numvar);

        /* Set up the linear part */
        MSK_putclist(task, 3, sub, val);
        MSK_putarow(task, 0, 3, asub, aval);
        MSK_putconbound(task, 0, MSK_BK_FX, 2.0, 2.0);
        for(i=0; i<5; i++)
            bkg[i] = MSK_BK_FR, blx[i] = -MSK_INFINITY, bux[i] = MSK_INFINITY;
        bkg[5] = MSK_BK_FX, blx[5] = bux[5] = 1.0;
        MSK_putvarboundslice(task, 0, numvar, bkg, blx, bux);

        if (r == MSK_RES_OK)
        {
            /* Append two power cones. */
            MSKint32t csub[2][3] = { {0, 1, 3}, {2, 5, 4} };
            r = MSK_appendcone(task, MSK_CT_PPOW, 0.2, 3, csub[0]);
            r = MSK_appendcone(task, MSK_CT_PPOW, 0.4, 3, csub[1]);
        }

        MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE);

        if (r == MSK_RES_OK)
        {
            MSKrescodee trmcode;

            /* Run optimizer */
            r = MSK_optimizetrm(task, &trmcode);

```

```

/* Print a summary containing information
   about the solution for debugging purposes*/
MSK_solutionsummary(task, MSK_STREAM_MSG);

if (r == MSK_RES_OK)
{
    MSKsolstae solsta;

    MSK_getsolsta(task, MSK_SOL_ITR, &solsta);

    switch (solsta)
    {
        case MSK_SOL_STA_OPTIMAL:
        {
            double *xx = NULL;

            xx = calloc(numvar, sizeof(double));
            if (xx)
            {
                MSK_getxx(task,
                           MSK_SOL_ITR,    /* Request the interior solution. */
                           xx);

                printf("Optimal primal solution\n");
                for (j = 0; j < 3; ++j)
                    printf("x[%d]: %e\n", j, xx[j]);
            }
            else
            {
                r = MSK_RES_ERR_SPACE;
            }
            free(xx);
        }
        break;
        case MSK_SOL_STA_DUAL_INFEAS_CER:
        case MSK_SOL_STA_PRIM_INFEAS_CER:
            printf("Primal or dual infeasibility certificate found.\n");
            break;
        case MSK_SOL_STA_UNKNOWN:
            printf("The status of the solution could not be determined. Termination code: %d.
↪\n", trmcode);
            break;
        default:
            printf("Other solution status.");
            break;
    }
}
else
{
    printf("Error while optimizing.\n");
}
}

if (r != MSK_RES_OK)
{
    /* In case of an error print error code and description. */
    char symname[MSK_MAX_STR_LEN];
    char desc[MSK_MAX_STR_LEN];

    printf("An error occurred while optimizing.\n");
    MSK_getcodedesc(r,

```

(continues on next page)


```

        symname,
        desc);
    printf("Error %s - '%s'\n", symname, desc);
}
}
/* Delete the task and the associated data. */
MSK_deletetask(&task);
}

/* Delete the environment and the associated data. */
MSK_deleteenv(&env);

return (r);
} /* main */

```

6.5 Conic Exponential Optimization

Conic optimization is a generalization of linear optimization, allowing constraints of the type

$$x^t \in \mathcal{K}_t,$$

where x^t is a subset of the problem variables and \mathcal{K}_t is a convex cone. Since the set \mathbb{R}^n of real numbers is also a convex cone, we can simply write a compound conic constraint $x \in \mathcal{K}$ where $\mathcal{K} = \mathcal{K}_1 \times \cdots \times \mathcal{K}_l$ is a product of smaller cones and x is the full problem variable.

MOSEK can solve conic optimization problems of the form

$$\begin{aligned}
 & \text{minimize} && c^T x + c^f \\
 & \text{subject to} && l^c \leq Ax \leq u^c, \\
 & && l^x \leq x \leq u^x, \\
 & && x \in \mathcal{K},
 \end{aligned}$$

where the domain restriction, $x \in \mathcal{K}$, implies that all variables are partitioned into convex cones

$$x = (x^0, x^1, \dots, x^{p-1}), \quad \text{with } x^t \in \mathcal{K}_t \subseteq \mathbb{R}^{n_t}.$$

In this tutorial we describe how to use the primal exponential cone defined as:

$$K_{\text{exp}} = \{x \in \mathbb{R}^3 : x_0 \geq x_1 \exp(x_2/x_1), x_0, x_1 \geq 0\}.$$

MOSEK also supports the dual exponential cone:

$$K_{\text{exp}}^* = \{s \in \mathbb{R}^3 : s_0 \geq -s_2 e^{-1} \exp(s_1/s_2), s_2 \leq 0, s_0 \geq 0\}.$$

For other types of cones supported by **MOSEK** see [Sec. 6.3](#), [Sec. 6.4](#), [Sec. 6.6](#). See [MSK_appendcone](#) for a list and definitions of available cone types. Different cone types can appear together in one optimization problem.

For example, the following constraint:

$$(x_4, x_0, x_2) \in K_{\text{exp}}$$

describes a convex cone in \mathbb{R}^3 given by the inequalities:

$$x_4 \geq x_0 \exp(x_2/x_0), \quad x_0, x_4 \geq 0.$$

Furthermore, each variable may belong to one cone at most. The constraint $x_i - x_j = 0$ would however allow x_i and x_j to belong to different cones with same effect.

6.5.1 Example CEO1

Consider the following basic conic exponential problem which involves some linear constraints and an exponential inequality:

$$\begin{aligned} & \text{minimize} && x_0 + x_1 \\ & \text{subject to} && x_0 + x_1 + x_2 = 1, \\ & && x_0 \geq x_1 \exp(x_2/x_1), \\ & && x_0, x_1 \geq 0. \end{aligned} \tag{6.9}$$

The conic form of (6.9) is:

$$\begin{aligned} & \text{minimize} && x_0 + x_1 \\ & \text{subject to} && x_0 + x_1 + x_2 = 1, \\ & && (x_0, x_1, x_2) \in K_{\text{exp}}, \\ & && x \in \mathbb{R}^3. \end{aligned} \tag{6.10}$$

Setting up the linear part

The linear parts (constraints, variables, objective) are set up using exactly the same methods as for linear problems, and we refer to [Sec. 6.1](#) for all the details. The same applies to technical aspects such as defining an optimization task, retrieving the solution and so on.

Setting up the conic constraints

A cone is defined using the function `MSK_appendcone`:

```

csub[0] = 0;
csub[1] = 1;
csub[2] = 2;

r = MSK_appendcone(task,
                    MSK_CT_PEXP,
                    0.0, /* Can be set to 0.0 */
                    3,
                    csub);

```

The first argument selects the type of exponential cone, that is `MSK_CT_PEXP`. The second parameter is currently ignored and passing 0.0 will work.

The next argument denotes the number of variables in the cone, which must be 3 for the exponential cone, and the last argument is a list of indexes of the variables appearing in the cone.

Variants of this method are available to append multiple cones at a time.

Source code

Listing 6.6: Source code solving problem (6.9).

```

#include <stdio.h>
#include "mosek.h" /* Include the MOSEK definition file. */

static void MSKAPI printstr(void *handle,
                             const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char *argv[])
{
    MSKrescodee r;

```

(continues on next page)

```

const MSKint32t numvar = 3,
              numcon = 1;

MSKboundkeye bkc = MSK_BK_FX;
double      blc = 1.0;
double      buc = 1.0;

MSKboundkeye bkc[] = {MSK_BK_FR,
                      MSK_BK_FR,
                      MSK_BK_FR
                      };
double      blx[] = {-MSK_INFINITY,
                    -MSK_INFINITY,
                    -MSK_INFINITY
                    };
double      bux[] = {+MSK_INFINITY,
                    +MSK_INFINITY,
                    +MSK_INFINITY
                    };

double      c[] = {1.0,
                  1.0,
                  0.0
                  };

double      a[] = {1.0, 1.0, 1.0};
MSKint32t   asub[] = {0, 1, 2};

MSKint32t   i, j, csub[3];

MSKenv_t     env = NULL;
MSKtask_t    task = NULL;

/* Create the mosek environment. */
r = MSK_makeenv(&env, NULL);

if (r == MSK_RES_OK)
{
    /* Create the optimization task. */
    r = MSK_maketask(env, numcon, numvar, &task);

    if (r == MSK_RES_OK)
    {
        MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

        /* Append 'numcon' empty constraints.
         The constraints will initially have no bounds. */
        if (r == MSK_RES_OK)
            r = MSK_appendcons(task, numcon);

        /* Append 'numvar' variables.
         The variables will initially be fixed at zero (x=0). */
        if (r == MSK_RES_OK)
            r = MSK_appendvars(task, numvar);

        /* Set up the linear part */
        if (r == MSK_RES_OK)
            r = MSK_putcslice(task, 0, numvar, c);
        if (r == MSK_RES_OK)
            r = MSK_putarow(task, 0, numvar, asub, a);
    }
}

```

```

if (r == MSK_RES_OK)
    r = MSK_putconbound(task, 0, bkc, blc, buc);
if (r == MSK_RES_OK)
    r = MSK_putvarboundslice(task, 0, numvar, bkx, blx, bux);

if (r == MSK_RES_OK)
{
    /* Append an exponential cone. */
    csub[0] = 0;
    csub[1] = 1;
    csub[2] = 2;

    r = MSK_appendcone(task,
                        MSK_CT_PEXP,
                        0.0, /* Can be set to 0.0 */
                        3,
                        csub);
}

if (r == MSK_RES_OK)
{
    MSKrescodee trmcode;

    /* Run optimizer */
    r = MSK_optimizetrm(task, &trmcode);

    /* Print a summary containing information
       about the solution for debugging purposes*/
    MSK_solutionsummary(task, MSK_STREAM_MSG);

    if (r == MSK_RES_OK)
    {
        MSKsolstae solsta;

        MSK_getsolsta(task, MSK_SOL_ITR, &solsta);

        switch (solsta)
        {
            case MSK_SOL_STA_OPTIMAL:
            {
                double *xx = NULL;

                xx = calloc(numvar, sizeof(double));
                if (xx)
                {
                    MSK_getxx(task,
                             MSK_SOL_ITR, /* Request the interior solution. */
                             xx);

                    printf("Optimal primal solution\n");
                    for (j = 0; j < numvar; ++j)
                        printf("x[%d]: %e\n", j, xx[j]);
                }
                else
                {
                    r = MSK_RES_ERR_SPACE;
                }
                free(xx);
            }
            break;
            case MSK_SOL_STA_DUAL_INFEAS_CER:

```

```

        case MSK_SOL_STA_PRIM_INFEAS_CER:
            printf("Primal or dual infeasibility certificate found.\n");
            break;
        case MSK_SOL_STA_UNKNOWN:
            printf("The status of the solution could not be determined. Termination code: %d.
↪\n", trmcode);
            break;
        default:
            printf("Other solution status.");
            break;
    }
}
else
{
    printf("Error while optimizing.\n");
}
}

if (r != MSK_RES_OK)
{
    /* In case of an error print error code and description. */
    char symname[MSK_MAX_STR_LEN];
    char desc[MSK_MAX_STR_LEN];

    printf("An error occurred while optimizing.\n");
    MSK_getcodedesc(r,
                    symname,
                    desc);
    printf("Error %s - '%s'\n", symname, desc);
}
}
/* Delete the task and the associated data. */
MSK_deletetask(&task);
}

/* Delete the environment and the associated data. */
MSK_deleteenv(&env);

return (r);
} /* main */

```

6.6 Semidefinite Optimization

Semidefinite optimization is a generalization of conic optimization, allowing the use of matrix variables belonging to the convex cone of positive semidefinite matrices

$$\mathcal{S}_+^r = \{X \in \mathcal{S}^r : z^T X z \geq 0, \quad \forall z \in \mathbb{R}^r\},$$

where \mathcal{S}^r is the set of $r \times r$ real-valued symmetric matrices.

MOSEK can solve semidefinite optimization problems of the form

$$\begin{aligned}
 & \text{minimize} && \sum_{j=0}^{n-1} c_j x_j + \sum_{j=0}^{p-1} \langle \overline{C}_j, \overline{X}_j \rangle + c^f \\
 & \text{subject to} && l_i^c \leq \sum_{j=0}^{n-1} a_{ij} x_j + \sum_{j=0}^{p-1} \langle \overline{A}_{ij}, \overline{X}_j \rangle \leq u_i^c, \quad i = 0, \dots, m-1, \\
 & && l_j^x \leq x_j \leq u_j^x, \quad j = 0, \dots, n-1, \\
 & && x \in \mathcal{K}, \overline{X}_j \in \mathcal{S}_+^{r_j}, \quad j = 0, \dots, p-1
 \end{aligned}$$

where the problem has p symmetric positive semidefinite variables $\overline{X}_j \in \mathcal{S}_+^{r_j}$ of dimension r_j with symmetric coefficient matrices $\overline{C}_j \in \mathcal{S}^{r_j}$ and $\overline{A}_{i,j} \in \mathcal{S}^{r_j}$. We use standard notation for the matrix inner

product, i.e., for $A, B \in \mathbb{R}^{m \times n}$ we have

$$\langle A, B \rangle := \sum_{i=0}^{m-1} \sum_{j=0}^{n-1} A_{ij} B_{ij}.$$

6.6.1 Example SDO1

We consider the simple optimization problem with semidefinite and conic quadratic constraints:

$$\begin{aligned} & \text{minimize} && \left\langle \begin{bmatrix} 2 & 1 & 0 \\ 1 & 2 & 1 \\ 0 & 1 & 2 \end{bmatrix}, \bar{X} \right\rangle + x_0 \\ & \text{subject to} && \left\langle \begin{bmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 1 \end{bmatrix}, \bar{X} \right\rangle + x_0 = 1, \\ & && \left\langle \begin{bmatrix} 1 & 1 & 1 \\ 1 & 1 & 1 \\ 1 & 1 & 1 \end{bmatrix}, \bar{X} \right\rangle + x_1 + x_2 = 1/2, \\ & && x_0 \geq \sqrt{x_1^2 + x_2^2}, \quad \bar{X} \succeq 0, \end{aligned} \tag{6.11}$$

The problem description contains a 3-dimensional symmetric semidefinite variable which can be written explicitly as:

$$\bar{X} = \begin{bmatrix} \bar{X}_{00} & \bar{X}_{10} & \bar{X}_{20} \\ \bar{X}_{10} & \bar{X}_{11} & \bar{X}_{21} \\ \bar{X}_{20} & \bar{X}_{21} & \bar{X}_{22} \end{bmatrix} \in \mathcal{S}_+^3,$$

and a conic quadratic variable $(x_0, x_1, x_2) \in \mathcal{Q}^3$. The objective is to minimize

$$2(\bar{X}_{00} + \bar{X}_{10} + \bar{X}_{11} + \bar{X}_{21} + \bar{X}_{22}) + x_0,$$

subject to the two linear constraints

$$\begin{aligned} \bar{X}_{00} + \bar{X}_{11} + \bar{X}_{22} + x_0 &= 1, \\ \bar{X}_{00} + \bar{X}_{11} + \bar{X}_{22} + 2(\bar{X}_{10} + \bar{X}_{20} + \bar{X}_{21}) + x_1 + x_2 &= 1/2. \end{aligned}$$

Setting up the linear and conic part

The linear and conic parts (constraints, variables, objective, cones) are set up using the methods described in the relevant tutorials; [Sec. 6.1](#), [Sec. 6.3](#), [Sec. 6.5](#), [Sec. 6.4](#). Here we only discuss the aspects directly involving semidefinite variables.

Appending semidefinite variables

First, we need to declare the number of semidefinite variables in the problem, similarly to the number of linear variables and constraints. This is done with the function `MSK_appendbarvars`.

```
r = MSK_appendbarvars(task, NUMBARVAR, DIMBARVAR);
```

Appending coefficient matrices

Coefficient matrices \bar{C}_j and \bar{A}_{ij} are constructed as weighted combinations of sparse symmetric matrices previously appended with the function `MSK_appendsparsesymmat`.

```
r = MSK_appendsparsesymmat(task,
                             DIMBARVAR[0],
                             5,
                             barc_i,
                             barc_j,
                             barc_v,
                             &idx);
```

The arguments specify the dimension of the symmetric matrix, followed by its description in the sparse triplet format. Only lower-triangular entries should be included. The function produces a unique index of the matrix just entered in the collection of all coefficient matrices defined by the user.

After one or more symmetric matrices have been created using `MSK_appendsparsesymmat`, we can combine them to set up the objective matrix coefficient \bar{C}_j using `MSK_putbarcj`, which forms a linear combination of one or more symmetric matrices. In this example we form the objective matrix directly, i.e. as a weighted combination of a single symmetric matrix.

```
r = MSK_putbarcj(task, 0, 1, &idx, &falpha);
```

Similarly, a constraint matrix coefficient \bar{A}_{ij} is set up by the function `MSK_putbaraij`.

```
r = MSK_putbaraij(task, 0, 0, 1, &idx, &falpha);
```

Retrieving the solution

After the problem is solved, we read the solution using `MSK_getbarxj`:

```
MSK_getbarxj(task,
              MSK_SOL_ITR, /* Request the interior solution. */
              0,
              barx);
```

The function returns the half-vectorization of \bar{X}_j (the lower triangular part stacked as a column vector), where the semidefinite variable index j is passed as an argument.

Source code

Listing 6.7: Source code solving problem (6.11).

```
#include <stdio.h>

#include "mosek.h" /* Include the MOSEK definition file. */

#define NUMCON 2 /* Number of constraints. */
#define NUMVAR 3 /* Number of conic quadratic variables */
#define NUMANZ 3 /* Number of non-zeros in A */
#define NUMBARVAR 1 /* Number of semidefinite variables */

static void MSKAPI printstr(void *handle,
                           const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char *argv[])
{
    MSKrescodee r;

    MSKint32t DIMBARVAR[] = {3}; /* Dimension of semidefinite cone */
    MSKint64t LENBARVAR[] = {3 * (3 + 1) / 2}; /* Number of scalar SD variables */

    MSKboundkeye bkc[] = { MSK_BK_FX, MSK_BK_FX };
    double blc[] = { 1.0, 0.5 };
    double buc[] = { 1.0, 0.5 };

    MSKint32t barc_i[] = {0, 1, 1, 2, 2},
              barc_j[] = {0, 0, 1, 1, 2};
    double barc_v[] = {2.0, 1.0, 2.0, 1.0, 2.0};

    MSKint32t aptrb[] = {0, 1},
```

(continues on next page)

```

        aptre[] = {1, 3},
        asub[] = {0, 1, 2}; /* column subscripts of A */
double    aval[] = {1.0, 1.0, 1.0};

MSKint32t  bara_i[] = {0, 1, 2, 0, 1, 2, 1, 2, 2},
        bara_j[] = {0, 1, 2, 0, 0, 0, 1, 1, 2};
double    bara_v[] = {1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0};
MSKint32t  conesub[] = {0, 1, 2};

MSKint32t  i, j;
MSKint64t  idx;
double    falpha = 1.0;

MSKrealt   *xx;
MSKrealt   *barx;
MSKenv_t    env = NULL;
MSKtask_t   task = NULL;

/* Create the mosek environment. */
r = MSK_makeenv(&env, NULL);

if (r == MSK_RES_OK)
{
    /* Create the optimization task. */
    r = MSK_maketask(env, NUMCON, 0, &task);

    if (r == MSK_RES_OK)
    {
        MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

        /* Append 'NUMCON' empty constraints.
           The constraints will initially have no bounds. */
        if (r == MSK_RES_OK)
            r = MSK_appendcons(task, NUMCON);

        /* Append 'NUMVAR' variables.
           The variables will initially be fixed at zero (x=0). */
        if (r == MSK_RES_OK)
            r = MSK_appendvars(task, NUMVAR);

        /* Append 'NUMBARVAR' semidefinite variables. */
        if (r == MSK_RES_OK) {
            r = MSK_appendbarvars(task, NUMBARVAR, DIMBARVAR);
        }

        /* Optionally add a constant term to the objective. */
        if (r == MSK_RES_OK)
            r = MSK_putcfix(task, 0.0);

        /* Set the linear term c_j in the objective.*/
        if (r == MSK_RES_OK)
            r = MSK_putcj(task, 0, 1.0);

        for (j = 0; j < NUMVAR && r == MSK_RES_OK; ++j)
            r = MSK_putvarbound(task,
                                j,
                                MSK_BK_FR,
                                -MSK_INFINITY,
                                MSK_INFINITY);

        /* Set the linear term barc_j in the objective.*/

```



```

if (r == MSK_RES_OK)
    r = MSK_appendsparsesymmat(task,
                                DIMBARVAR[0],
                                5,
                                barc_i,
                                barc_j,
                                barc_v,
                                &idx);

if (r == MSK_RES_OK)
    r = MSK_putbarcj(task, 0, 1, &idx, &falpha);

/* Set the bounds on constraints.
   for i=1, ..., NUMCON : blc[i] <= constraint i <= buc[i] */
for (i = 0; i < NUMCON && r == MSK_RES_OK; ++i)
    r = MSK_putconbound(task,
                        i,          /* Index of constraint.*/
                        bkc[i],    /* Bound key.*/
                        blc[i],    /* Numerical value of lower bound.*/
                        buc[i]);  /* Numerical value of upper bound.*/

/* Input A row by row */
for (i = 0; i < NUMCON && r == MSK_RES_OK; ++i)
    r = MSK_putarow(task,
                    i,
                    aptre[i] - aptrb[i],
                    asub    + aptrb[i],
                    aval    + aptrb[i]);

/* Append the conic quadratic cone */
if (r == MSK_RES_OK)
    r = MSK_appendcone(task,
                      MSK_CT_QUAD,
                      0.0,
                      3,
                      conesub);

/* Add the first row of barA */
if (r == MSK_RES_OK)
    r = MSK_appendsparsesymmat(task,
                                DIMBARVAR[0],
                                3,
                                bara_i,
                                bara_j,
                                bara_v,
                                &idx);

if (r == MSK_RES_OK)
    r = MSK_putbaraij(task, 0, 0, 1, &idx, &falpha);

/* Add the second row of barA */
if (r == MSK_RES_OK)
    r = MSK_appendsparsesymmat(task,
                                DIMBARVAR[0],
                                6,
                                bara_i + 3,
                                bara_j + 3,
                                bara_v + 3,
                                &idx);

if (r == MSK_RES_OK)

```

```

r = MSK_putbaraij(task, 1, 0, 1, &idx, &falpha);

if (r == MSK_RES_OK)
{
    MSKrescodee trmcode;

    /* Run optimizer */
    r = MSK_optimizetrm(task, &trmcode);

    /* Print a summary containing information
       about the solution for debugging purposes*/
    MSK_solutionsummary(task, MSK_STREAM_MSG);

    if (r == MSK_RES_OK)
    {
        MSKsolstae solsta;

        MSK_getsolsta(task, MSK_SOL_ITR, &solsta);

        switch (solsta)
        {
            case MSK_SOL_STA_OPTIMAL:
                xx = (MSKrealt *) MSK_calloc(task, NUMVAR, sizeof(MSKrealt));
                barx = (MSKrealt *) MSK_calloc(task, LENBARVAR[0], sizeof(MSKrealt));

                MSK_getxx(task,
                        MSK_SOL_ITR,
                        xx);
                MSK_getbarxj(task,
                        MSK_SOL_ITR, /* Request the interior solution. */
                        0,
                        barx);

                printf("Optimal primal solution\n");
                for (i = 0; i < NUMVAR; ++i)
                    printf("x[%d] : % e\n", i, xx[i]);

                for (i = 0; i < LENBARVAR[0]; ++i)
                    printf("barx[%d]: % e\n", i, barx[i]);

                MSK_freetask(task, xx);
                MSK_freetask(task, barx);

                break;

            case MSK_SOL_STA_DUAL_INFEAS_CER:
            case MSK_SOL_STA_PRIM_INFEAS_CER:
                printf("Primal or dual infeasibility certificate found.\n");
                break;

            case MSK_SOL_STA_UNKNOWN:
                printf("The status of the solution could not be determined. Termination code: %d.\n", trmcode);
                break;

            default:
                printf("Other solution status.");
                break;
        }
    }
    else

```

```

    {
        printf("Error while optimizing.\n");
    }
}

if (r != MSK_RES_OK)
{
    /* In case of an error print error code and description. */
    char symname[MSK_MAX_STR_LEN];
    char desc[MSK_MAX_STR_LEN];

    printf("An error occurred while optimizing.\n");
    MSK_getcodedesc(r,
                    symname,
                    desc);
    printf("Error %s - '%s'\n", symname, desc);
}
}
/* Delete the task and the associated data. */
MSK_deletetask(&task);
}

/* Delete the environment and the associated data. */
MSK_deleteenv(&env);

return (r);
} /* main */

```

6.7 Integer Optimization

An optimization problem where one or more of the variables are constrained to integer values is called a (mixed) integer optimization problem. **MOSEK** supports integer variables in combination with linear, quadratic and quadratically constrained and conic problems (except semidefinite). See the previous tutorials for an introduction to how to model these types of problems.

6.7.1 Example MILO1

We use the example

$$\begin{aligned}
 &\text{maximize} && x_0 + 0.64x_1 \\
 &\text{subject to} && 50x_0 + 31x_1 \leq 250, \\
 & && 3x_0 - 2x_1 \geq -4, \\
 & && x_0, x_1 \geq 0 \quad \text{and integer}
 \end{aligned} \tag{6.12}$$

to demonstrate how to set up and solve a problem with integer variables. It has the structure of a linear optimization problem (see Sec. 6.1) except for integrality constraints on the variables. Therefore, only the specification of the integer constraints requires something new compared to the linear optimization problem discussed previously.

First, the integrality constraints are imposed using the function `MSK_putvartype`:

```

for (j = 0; j < numvar && r == MSK_RES_OK; ++j)
    r = MSK_putvartype(task, j, MSK_VAR_TYPE_INT);

```

Next, the example demonstrates how to set various useful parameters of the mixed-integer optimizer. See Sec. 13.4 for details.

```

/* Set max solution time */
r = MSK_putdouparam(task,
                    MSK_DPAR_MIO_MAX_TIME,
                    60.0);

```

The complete source for the example is listed Listing 6.8. Please note that when *MSK_getsolutionslice* is called, the integer solution is requested by using *MSK_SOL_ITG*. No dual solution is defined for integer optimization problems.

Listing 6.8: Source code implementing problem (6.12).

```
#include <stdio.h>
#include "mosek.h" /* Include the MOSEK definition file. */

static void MSKAPI printstr(void *handle,
                           const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, char *argv[])
{
    const MSKint32t numvar = 2,
                  numcon = 2;

    double        c[] = { 1.0, 0.64 };
    MSKboundkeye bkc[] = { MSK_BK_UP,    MSK_BK_LO };
    double        blc[] = { -MSK_INFINITY, -4.0 };
    double        buc[] = { 250.0,      MSK_INFINITY };

    MSKboundkeye bkc[] = { MSK_BK_LO,    MSK_BK_LO };
    double        blx[] = { 0.0,        0.0 };
    double        bux[] = { MSK_INFINITY, MSK_INFINITY };

    MSKint32t     aptrb[] = { 0, 2 },
                aptre[] = { 2, 4 },
                asub[] = { 0, 1, 0, 1 };
    double        aval[] = { 50.0, 3.0, 31.0, -2.0 };
    MSKint32t     i, j;

    MSKenv_t      env = NULL;
    MSKtask_t     task = NULL;
    MSKrescodee   r;

    /* Create the mosek environment. */
    r = MSK_makeenv(&env, NULL);

    /* Check if return code is ok. */
    if (r == MSK_RES_OK)
    {
        /* Create the optimization task. */
        r = MSK_maketask(env, 0, 0, &task);

        if (r == MSK_RES_OK)
            r = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

        /* Append 'numcon' empty constraints.
           The constraints will initially have no bounds. */
        if (r == MSK_RES_OK)
            r = MSK_appendcons(task, numcon);

        /* Append 'numvar' variables.
           The variables will initially be fixed at zero (x=0). */
        if (r == MSK_RES_OK)
            r = MSK_appendvars(task, numvar);
    }
}
```

(continues on next page)

```

/* Optionally add a constant term to the objective. */
if (r == MSK_RES_OK)
    r = MSK_putcfix(task, 0.0);
for (j = 0; j < numvar && r == MSK_RES_OK; ++j)
{
    /* Set the linear term c_j in the objective.*/
    if (r == MSK_RES_OK)
        r = MSK_putcj(task, j, c[j]);

    /* Set the bounds on variable j.
       blx[j] <= x_j <= bux[j] */
    if (r == MSK_RES_OK)
        r = MSK_putvarbound(task,
                               j,          /* Index of variable.*/
                               bkc[j],     /* Bound key.*/
                               blx[j],     /* Numerical value of lower bound.*/
                               bux[j]);    /* Numerical value of upper bound.*/

    /* Input column j of A */
    if (r == MSK_RES_OK)
        r = MSK_putacol(task,
                           j,              /* Variable (column) index.*/
                           aptre[j] - aptrb[j], /* Number of non-zeros in column j.*/
                           asub + aptrb[j], /* Pointer to row indexes of column j.*/
                           aval + aptrb[j]); /* Pointer to Values of column j.*/
}

/* Set the bounds on constraints.
   for i=1, ..., numcon : blc[i] <= constraint i <= buc[i] */
for (i = 0; i < numcon && r == MSK_RES_OK; ++i)
    r = MSK_putconbound(task,
                           i,              /* Index of constraint.*/
                           bkc[i],        /* Bound key.*/
                           blc[i],        /* Numerical value of lower bound.*/
                           buc[i]);       /* Numerical value of upper bound.*/

/* Specify integer variables. */
for (j = 0; j < numvar && r == MSK_RES_OK; ++j)
    r = MSK_putvartype(task, j, MSK_VAR_TYPE_INT);

if (r == MSK_RES_OK)
    r = MSK_putobjsense(task,
                          MSK_OBJECTIVE_SENSE_MAXIMIZE);

if (r == MSK_RES_OK)
    /* Set max solution time */
    r = MSK_putdouparam(task,
                          MSK_DPAR_MIO_MAX_TIME,
                          60.0);

if (r == MSK_RES_OK)
{
    MSKrescodee trmcode;

    /* Run optimizer */
    r = MSK_optimizetrm(task, &trmcode);

    /* Print a summary containing information
       about the solution for debugging purposes*/
    MSK_solutionsummary(task, MSK_STREAM_MSG);
}

```

```

if (r == MSK_RES_OK)
{
    MSKint32t j;
    MSKsolstae solsta;
    double *xx = NULL;

    MSK_getsolsta(task, MSK_SOL_ITG, &solsta);

    xx = calloc(numvar, sizeof(double));
    if (xx)
    {
        switch (solsta)
        {
            case MSK_SOL_STA_INTEGER_OPTIMAL:
                MSK_getxx(task,
                        MSK_SOL_ITG, /* Request the integer solution. */
                        xx);

                printf("Optimal solution.\n");
                for (j = 0; j < numvar; ++j)
                    printf("x[%d]: %e\n", j, xx[j]);
                break;
            case MSK_SOL_STA_PRIM_FEAS:
                /* A feasible but not necessarily optimal solution was located. */
                MSK_getxx(task, MSK_SOL_ITG, xx);

                printf("Feasible solution.\n");
                for (j = 0; j < numvar; ++j)
                    printf("x[%d]: %e\n", j, xx[j]);
                break;
            case MSK_SOL_STA_UNKNOWN:
                {
                    MSKprosta prosta;
                    MSK_getprosta(task, MSK_SOL_ITG, &prosta);
                    switch (prosta)
                    {
                        case MSK_PRO_STA_PRIM_INFEAS_OR_UNBOUNDED:
                            printf("Problem status Infeasible or unbounded\n");
                            break;
                        case MSK_PRO_STA_PRIM_INFEAS:
                            printf("Problem status Infeasible.\n");
                            break;
                        case MSK_PRO_STA_UNKNOWN:
                            printf("Problem status unknown. Termination code %d.\n", trmcode);
                            break;
                        default:
                            printf("Other problem status.");
                            break;
                    }
                }
                break;
            default:
                printf("Other solution status.");
                break;
        }
    }
    else
    {
        r = MSK_RES_ERR_SPACE;
    }
}

```

```

        free(xx);
    }
}

if (r != MSK_RES_OK)
{
    /* In case of an error print error code and description. */
    char symname[MSK_MAX_STR_LEN];
    char desc[MSK_MAX_STR_LEN];

    printf("An error occurred while optimizing.\n");
    MSK_getcodedesc(r,
                    symname,
                    desc);
    printf("Error %s - '%s'\n", symname, desc);
}

MSK_deletetask(&task);
}
MSK_deleteenv(&env);

printf("Return code: %d.\n", r);
return (r);
} /* main */

```

6.7.2 Specifying an initial solution

It is a common strategy to provide a starting feasible point (if one is known in advance) to the mixed-integer solver. This can in many cases reduce solution time.

It is not necessary to specify the whole solution. **MOSEK** will attempt to use it to speed up the computation. **MOSEK** will first try to construct a feasible solution by fixing integer variables to the values provided by the user (rounding if necessary) and optimizing over the continuous variables. The outcome of this process can be inspected via information items *MSK_IINF_MIO_CONSTRUCT_SOLUTION* and *MSK_DINF_MIO_CONSTRUCT_SOLUTION_OBJ*, and via the **Construct solution** objective entry in the log. We concentrate on a simple example below.

$$\begin{aligned}
 &\text{maximize} && 7x_0 + 10x_1 + x_2 + 5x_3 \\
 &\text{subject to} && x_0 + x_1 + x_2 + x_3 \leq 2.5 \\
 & && x_0, x_1, x_2 \in \mathbb{Z} \\
 & && x_0, x_1, x_2, x_3 \geq 0
 \end{aligned} \tag{6.13}$$

Solution values can be set using *MSK_putsolution*.

Listing 6.9: Implementation of problem (6.13) specifying an initial solution.

```

if (r == MSK_RES_OK)
{
    /* Assign values to integer variables
       (we only set a slice of xx) */
    double xxInit[] = {1.0, 1.0, 0.0};
    r = MSK_putxxslice(task, MSK_SOL_ITG, 0, 3, xxInit);
}

```

The log output from the optimizer will in this case indicate that the inputted values were used to construct an initial feasible solution:

```
Construct solution objective      : 1.950000000000e+01
```

The same information can be obtained from the API:

Listing 6.10: Retrieving information about usage of initial solution

```
MSK_getintinf(task, MSK_IINF_MIO_CONSTRUCT_SOLUTION, &constr);
MSK_getdouninf(task, MSK_DINF_MIO_CONSTRUCT_SOLUTION_OBJ, &constr_obj);
printf("Initial solution utilization: %d\nInitial solution objective: %.3f\n", constr,
↪constr_obj);
```

6.7.3 Example MICO1

Integer variables can also be used arbitrarily in conic problems (except semidefinite). We refer to the previous tutorials for how to set up a conic optimization problem. Here we present sample code that sets up a simple optimization problem:

$$\begin{aligned} &\text{minimize} && x^2 + y^2 \\ &\text{subject to} && x \geq e^y + 3.8, \\ &&& x, y \text{ integer.} \end{aligned} \tag{6.14}$$

The canonical conic formulation of (6.14) suitable for Optimizer API for C is

$$\begin{aligned} &\text{minimize} && x_0 \\ &\text{subject to} && (x_0, x_1, x_2) \in Q^3 && (x_0 \geq \sqrt{x_1^2 + x_2^2}) \\ &&& (x_3, x_4, x_5) \in K_{\text{exp}} && (x_3 \geq x_4 \exp(x_5/x_4)) \\ &&& -x_1 + x_3 = -3.8 \\ &&& x_4 = 1 \\ &&& x_2 - x_5 = 0 \\ &&& x_1, x_2 \text{ integer.} \end{aligned} \tag{6.15}$$

Listing 6.11: Implementation of problem (6.15).

```
int main(int argc, char *argv[])
{
    MSKboundkeye bkc[] = { MSK_BK_FX, MSK_BK_FX, MSK_BK_FX };
    double bc[] = { -3.8, 1, 0 };

    MSKvariabletypee var[] = { MSK_VAR_TYPE_INT, MSK_VAR_TYPE_INT };
    MSKint32t intsub[] = { 1, 2 };

    MSKint32t asubi[] = {0, 0, 1, 2, 2},
              asubj[] = {1, 3, 4, 2, 5};
    MSKrealt aval[] = {-1, 1, 1, 1, -1};
    MSKint32t i, j;

    MSKenv_t env = NULL;
    MSKtask_t task = NULL;
    MSKrescodee r, trm;

    r = MSK_makeenv(&env, NULL);

    if (r == MSK_RES_OK)
    {
        r = MSK_maketask(env, 0, 0, &task);

        if (r == MSK_RES_OK)
            r = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

        if (r == MSK_RES_OK)
            r = MSK_appendvars(task, 6);

        if (r == MSK_RES_OK)
```

(continues on next page)


```

    r = MSK_appendcons(task, 3);

    if (r == MSK_RES_OK)
        r = MSK_putvarboundsliceconst(task, 0, 6, MSK_BK_FR, -0.0, 0.0);

    /* Integrality constraints */
    if (r == MSK_RES_OK)
        r = MSK_putvartypelist(task, 2, intsub, vart);

    /* Linear part of the problem */
    if (r == MSK_RES_OK)
        r = MSK_putaijlist(task, 5, asubi, asubj, aval);
    if (r == MSK_RES_OK)
        r = MSK_putconboundslice(task, 0, 3, bkc, bc, bc);

    /* Objective */
    if (r == MSK_RES_OK)
        r = MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MINIMIZE);
    if (r == MSK_RES_OK)
        r = MSK_putcj(task, 0, 1);

    /* Conic part of the problem */
    if (r == MSK_RES_OK)
        r = MSK_appendconeseq(task, MSK_CT_QUAD, 0, 3, 0);
    if (r == MSK_RES_OK)
        r = MSK_appendconeseq(task, MSK_CT_PEXP, 0, 3, 3);

    /* Optimize the problem */
    if (r == MSK_RES_OK)
        r = MSK_optimizetrm(task, &trm);

    if (r == MSK_RES_OK)
        r = MSK_solutionsummary(task, MSK_STREAM_MSG);

    if (r == MSK_RES_OK)
    {
        MSKrealt xx[] = {0, 0};

        r = MSK_getxxslice(task, MSK_SOL_ITG, 1, 3, xx);

        if (r == MSK_RES_OK)
            printf("x = %.2f, y = %.2f\n", xx[0], xx[1]);
    }

    if (task) MSK_deletetask(&task);
}

if (env) MSK_deleteenv(&env);
return r;
}

```

Error and solution status handling were omitted for readability.

6.8 Geometric Programming

Geometric programs (GP) are a particular class of optimization problems which can be expressed in special polynomial form as positive sums of generalized monomials. More precisely, a geometric problem in canonical form is

$$\begin{aligned}
 &\text{minimize} && f_0(x) \\
 &\text{subject to} && f_i(x) \leq 1, \quad i = 1, \dots, m, \\
 & && x_j > 0, \quad j = 1, \dots, n,
 \end{aligned} \tag{6.16}$$

where each f_0, \dots, f_m is a *posynomial*, that is a function of the form

$$f(x) = \sum_k c_k x_1^{\alpha_{k1}} x_2^{\alpha_{k2}} \dots x_n^{\alpha_{kn}}$$

with arbitrary real α_{ki} and $c_k > 0$. The standard way to formulate GPs in convex form is to introduce a variable substitution

$$x_i = \exp(y_i).$$

Under this substitution all constraints in a GP can be reduced to the form

$$\log\left(\sum_k \exp(a_k^T y + b_k)\right) \leq 0 \quad (6.17)$$

involving a *log-sum-exp* bound. Moreover, constraints involving only a single monomial in x can be even more simply written as a linear inequality:

$$a_k^T y + b_k \leq 0$$

We refer to the **MOSEK Modeling Cookbook** and to [\[BKVH07\]](#) for more details on this reformulation. A geometric problem formulated in convex form can be entered into **MOSEK** with the help of exponential cones.

6.8.1 Example GP1

The following problem comes from [\[BKVH07\]](#). Consider maximizing the volume of a $h \times w \times d$ box subject to upper bounds on the area of the floor and of the walls and bounds on the ratios h/w and d/w :

$$\begin{aligned} & \text{maximize} && hwd \\ & \text{subject to} && 2(hw + hd) \leq A_{\text{wall}}, \\ & && wd \leq A_{\text{floor}}, \\ & && \alpha \leq h/w \leq \beta, \\ & && \gamma \leq d/w \leq \delta. \end{aligned} \quad (6.18)$$

The decision variables in the problem are h, w, d . We make a substitution

$$h = \exp(x), w = \exp(y), d = \exp(z)$$

after which (6.18) becomes

$$\begin{aligned} & \text{maximize} && x + y + z \\ & \text{subject to} && \log(\exp(x + y + \log(2/A_{\text{wall}})) + \exp(x + z + \log(2/A_{\text{wall}}))) \leq 0, \\ & && y + z \leq \log(A_{\text{floor}}), \\ & && \log(\alpha) \leq x - y \leq \log(\beta), \\ & && \log(\gamma) \leq z - y \leq \log(\delta). \end{aligned} \quad (6.19)$$

Next, we demonstrate how to implement a log-sum-exp constraint (6.17). It can be written as:

$$\begin{aligned} u_k &\geq \exp(a_k^T y + b_k), \quad (\text{equiv. } (u_k, 1, a_k^T y + b_k) \in K_{\text{exp}}), \\ \sum_k u_k &= 1. \end{aligned} \quad (6.20)$$

This presentation requires one extra variable u_k for each monomial appearing in the original posynomial constraint. Another fixed variable $t_k = 1$ stands for the second entry in the exponential cone.

Listing 6.12: Implementation of log-sum-exp as in (6.20).

```
// Add a single log-sum-exp constraint sum(log(exp(z_i))) <= 0
// Assume numExp variable triples are ordered as (u0,t0,z0,u1,t1,z1...)
// starting from variable with index expStart
double *val = (double*) calloc(numExp, sizeof(double));
```

(continues on next page)

(continued from previous page)

```
int      *sub = (int*) calloc(numExp, sizeof(int));
MSKconetype *ct = (MSKconetype*) calloc(numExp, sizeof(MSKconetype));
int      *len = (int*) calloc(numExp, sizeof(int));

// sum(u_i) = 1 as constraint number c, u_i unbounded
for(i = 0; i < numExp; i++)
    { sub[i] = expStart + 3*i; val[i] = 1.0; }
if (r == MSK_RES_OK)
    r = MSK_putarow(task, c, numExp, sub, val);
if (r == MSK_RES_OK)
    r = MSK_putconbound(task, c, MSK_BK_FX, 1.0, 1.0);
if (r == MSK_RES_OK)
    r = MSK_putvarboundlistconst(task, numExp, sub, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY);

// z_i unbounded
for(i = 0; i < numExp; i++) sub[i] = expStart + 3*i + 2;
if (r == MSK_RES_OK)
    r = MSK_putvarboundlistconst(task, numExp, sub, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY);

// t_i = 1
for(i = 0; i < numExp; i++) sub[i] = expStart + 3*i + 1;
if (r == MSK_RES_OK)
    r = MSK_putvarboundlistconst(task, numExp, sub, MSK_BK_FX, 1, 1);

// Every triple is in an exponential cone
for(i = 0; i < numExp; i++)
    { ct[i] = MSK_CT_PEXP; val[i] = 0.0; len[i] = 3; }
if (r == MSK_RES_OK)
    r = MSK_appendconeseq(task, numExp, ct, val, len, expStart);

free(val); free(sub); free(ct); free(len);
```

We can now use this function to assemble all constraints in the model. The linear part of the problem is entered as in Sec. 6.1.

Listing 6.13: Source code solving problem (6.19).

```
int max_volume_box(double Aw, double Af,
                  double alpha, double beta, double gamma, double delta,
                  double hwd[])
{
    // Basic dimensions of our problem
    const int numvar = 3; // Variables in original problem
    const int numLinCon = 3; // Linear constraints in original problem
    const int numExp = 2; // Number of exp-terms in the log-sum-exp constraint

    // Linear part of the problem
    const double cval[] = {1, 1, 1};
    const int asubi[] = {0, 0, 1, 1, 2, 2};
    const int asubj[] = {1, 2, 0, 1, 2, 1};
    const int alen = 6;
    const double aval[] = {1.0, 1.0, 1.0, -1.0, 1.0, -1.0};
    const MSKboundkey bkc[] = {MSK_BK_UP, MSK_BK_RA, MSK_BK_RA};
    const double blc[] = {-MSK_INFINITY, log(alpha), log(gamma)};
    const double buc[] = {log(Af), log(beta), log(delta)};

    // Linear part setting up slack variables
    // for the linear expressions appearing inside exps
    // x_5 - x - y = log(2/Awall)
    // x_8 - x - z = log(2/Awall)
    // The slack indexes are convenient for defining exponential cones, see later
```

(continues on next page)

```

const int      a2subi[] = {3, 3, 3, 4, 4, 4};
const int      a2subj[] = {5, 0, 1, 8, 0, 2};
const int      a2len   = 6;
const double   a2val[] = {1.0, -1.0, -1.0, 1.0, -1.0, -1.0};
const MSKboundkey b2kc[] = {MSK_BK_FX, MSK_BK_FX};
const double   b2luc[] = {log(2/Aw), log(2/Aw)};

MSKenv_t       env = NULL;
MSKtask_t      task = NULL;
MSKrescodee    r, trmcode;
MSKsolstae     solsta;
MSKint32t      i;
double         *xyz = (double*) calloc(numvar, sizeof(double));

r = MSK_makeenv(&env, NULL);

if (r == MSK_RES_OK)
    r = MSK_maketask(env, 0, 0, &task);

if (r == MSK_RES_OK)
    r = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

if (r == MSK_RES_OK)
    r = MSK_appendvars(task, numvar + 3*numExp);

if (r == MSK_RES_OK)
    r = MSK_appendcons(task, numLinCon + numExp + 1);

// Objective is the sum of three first variables
if (r == MSK_RES_OK)
    r = MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE);
if (r == MSK_RES_OK)
    r = MSK_putcslice(task, 0, numvar, cval);
if (r == MSK_RES_OK)
    r = MSK_putvarboundsliceconst(task, 0, numvar, MSK_BK_FR, -MSK_INFINITY, +MSK_INFINITY);

// Add the three linear constraints
if (r == MSK_RES_OK)
    r = MSK_putaijlist(task, alen, asubi, asubj, aval);
if (r == MSK_RES_OK)
    r = MSK_putconboundslice(task, 0, numvar, bkc, blc, buc);

// Add linear constraints for the expressions appearing in exp(...)
if (r == MSK_RES_OK)
    r = MSK_putaijlist(task, a2len, a2subi, a2subj, a2val);
if (r == MSK_RES_OK)
    r = MSK_putconboundslice(task, numLinCon, numLinCon+numExp, b2kc, b2luc, b2luc);

{
    int c = numLinCon + numExp;
    int expStart = numvar;
    // Add a single log-sum-exp constraint  $\sum(\log(\exp(z_i))) \leq 0$ 
    // Assume numExp variable triples are ordered as (u0,t0,z0,u1,t1,z1...)
    // starting from variable with index expStart
    double *val = (double*) calloc(numExp, sizeof(double));
    int *sub = (int*) calloc(numExp, sizeof(int));
    MSKconetypee *ct = (MSKconetypee*) calloc(numExp, sizeof(MSKconetypee));
    int *len = (int*) calloc(numExp, sizeof(int));

    //  $\sum(u_i) = 1$  as constraint number c,  $u_i$  unbounded
    for(i = 0; i < numExp; i++)

```

(continued from previous page)

```
    { sub[i] = expStart + 3*i; val[i] = 1.0; }
    if (r == MSK_RES_OK)
        r = MSK_putarow(task, c, numExp, sub, val);
    if (r == MSK_RES_OK)
        r = MSK_putconbound(task, c, MSK_BK_FX, 1.0, 1.0);
    if (r == MSK_RES_OK)
        r = MSK_putvarboundlistconst(task, numExp, sub, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY);

    // z_i unbounded
    for(i = 0; i < numExp; i++) sub[i] = expStart + 3*i + 2;
    if (r == MSK_RES_OK)
        r = MSK_putvarboundlistconst(task, numExp, sub, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY);

    // t_i = 1
    for(i = 0; i < numExp; i++) sub[i] = expStart + 3*i + 1;
    if (r == MSK_RES_OK)
        r = MSK_putvarboundlistconst(task, numExp, sub, MSK_BK_FX, 1, 1);

    // Every triple is in an exponential cone
    for(i = 0; i < numExp; i++)
        { ct[i] = MSK_CT_PEXP; val[i] = 0.0; len[i] = 3; }
    if (r == MSK_RES_OK)
        r = MSK_appendconesseq(task, numExp, ct, val, len, expStart);

    free(val); free(sub); free(ct); free(len);
}

// Solve and map to original h, w, d
if (r == MSK_RES_OK)
    r = MSK_optimizetrm(task, &trmcode);

if (r == MSK_RES_OK)
    MSK_getsolsta(task, MSK_SOL_ITR, &solsta);

if (solsta == MSK_SOL_STA_OPTIMAL)
{
    if (r == MSK_RES_OK)
        r = MSK_getxxslice(task, MSK_SOL_ITR, 0, numvar, xyz);
    for(i = 0; i < numvar; i++) hwd[i] = exp(xyz[i]);
}
else
{
    printf("Solution not optimal, termination code %d.\n", trmcode);
    r = trmcode;
}

free(xyz);
return r;
}
```

Given sample data we obtain the solution h, w, d as follows:

Listing 6.14: Sample data for problem (6.18).

```
int main()
{
    const double Aw    = 200.0;
    const double Af    = 50.0;
    const double alpha = 2.0;
    const double beta  = 10.0;
    const double gamma = 2.0;
```

(continues on next page)

```

const double delta = 10.0;
MSKrescodee r;
double      hwd[3];

r = max_volume_box(Aw, Af, alpha, beta, gamma, delta, hwd);

printf("Response code: %d\n", r);
if (r == MSK_RES_OK)
    printf("Solution h=%.4f w=%.4f d=%.4f\n", hwd[0], hwd[1], hwd[2]);

return r;
}

```

6.9 Library of basic functions

This section contains a library of small models of basic functions frequently appearing in optimization models. It is essentially an implementation of the mathematical models from the [MOSEK Modeling Cookbook](#) using Optimizer API for C. These short code snippets can be seen as illustrative examples, can be copy-pasted to other code, and can even be directly called when assembling optimization models as we show in [Sec. 6.9.6](#) (although this may be more suitable for prototyping; also note that additional variables and constraints will be introduced and there is no error checking).

6.9.1 Variable and constraint management

Append variables

Adds a number of new variables. Returns the index of the first variable in the sequence.

Listing 6.15: New variables.

```

int msk_newvar(MSKtask_t task, int num) { // free
    int i, v;
    MSK_getnumvar(task, &v);
    MSK_appendvars(task, num);
    for(i=0; i<num; i++)
        MSK_putvarbound(task, v+i, MSK_BK_FR, -inf, inf);
    return v;
}

int msk_newvar_fx(MSKtask_t task, int num, double val) { // fixed
    int i, v;
    MSK_getnumvar(task, &v);
    MSK_appendvars(task, num);
    for(i=0; i<num; i++)
        MSK_putvarbound(task, v+i, MSK_BK_FX, val, val);
    return v;
}

int msk_newvar_bin(MSKtask_t task, int num) { // binary
    int i, v;
    MSK_getnumvar(task, &v);
    MSK_appendvars(task, num);
    for(i=0; i<num; i++) {
        MSK_putvarbound(task, v+i, MSK_BK_RA, 0.0, 1.0);
        MSK_putvartype(task, v+i, MSK_VAR_TYPE_INT);
    }
    return v;
}

```

Variable duplication

Declares equality of two variables, or returns an index of a new duplicate of an existing variable.

Listing 6.16: Duplicate variables.

```
// x = y
void msk_equal(MSKtask_t task, int x, int y) {
    int c;
    c = msk_newcon(task, 1);
    MSK_putaij(task, c, x, 1.0);
    MSK_putaij(task, c, y, -1.0);
    MSK_putconbound(task, c, MSK_BK_FX, 0.0, 0.0);
}
int msk_dup(MSKtask_t task, int x) {
    int y;
    y = msk_newvar(task, 1);
    msk_equal(task, x, y);
    return y;
}
```

Append constraints

Adds a number of new constraints. Returns the index of the first constraint in the sequence.

Listing 6.17: New constraints.

```
int msk_newcon(MSKtask_t task, int num) {
    int c;
    MSK_getnumcon(task, &c);
    MSK_appendcons(task, num);
    return c;
}
```

6.9.2 Linear operations

Absolute value

$$t \geq |x|$$

Listing 6.18: Absolute value.

```
// t >= |x|
void msk_abs(MSKtask_t task, int t, int x) {
    int c;
    c = msk_newcon(task, 2);
    MSK_putaij(task, c, t, 1.0);
    MSK_putaij(task, c, x, 1.0);
    MSK_putconbound(task, c, MSK_BK_LO, 0.0, inf);
    MSK_putaij(task, c+1, t, 1.0);
    MSK_putaij(task, c+1, x, -1.0);
    MSK_putconbound(task, c+1, MSK_BK_LO, 0.0, inf);
}
```

1-norm

$$t \geq \sum_i |x_i|$$

Listing 6.19: 1-norm.

```
// t >= sum( |x_i| ), x is a list of variables
void msk_norm1(MSKtask_t task, int t, int n, int* x) {
    int i, c, u;
    u = msk_newvar(task, n);
```

(continues on next page)

(continued from previous page)

```
for(i=0; i<n; i++) msk_abs(task, u+i, x[i]);
c = msk_newcon(task, 1);
for(i=0; i<n; i++) MSK_putaij(task, c, u+i, -1.0);
MSK_putaij(task, c, t, 1.0);
MSK_putconbound(task, c, MSK_BK_LO, 0.0, inf);
}
```

6.9.3 Quadratic and power operations

Square

$$t \geq x^2$$

Listing 6.20: Square.

```
// t >= x^2
void msk_sq(MSKtask_t task, int t, int x) {
    int submem[3];
    submem[0] = msk_newvar_fx(task, 1, 0.5), submem[1] = t, submem[2] = x;
    MSK_appendcone(task, MSK_CT_RQUAD, 0.0, 3, submem);
}
```

2-norm

$$t \geq \sqrt{\sum_i x_i^2}$$

Listing 6.21: 2-norm.

```
// t >= sqrt(x_1^2 + ... + x_n^2) where x is a list of variables
void msk_norm2(MSKtask_t task, int t, int n, int* x) {
    int* submem;
    int i;
    submem = (int*) MSK_calloc(task, n+1, sizeof(int));
    submem[0] = t;
    for(i=0; i<n; i++) submem[i+1] = x[i];
    MSK_appendcone(task, MSK_CT_QUAD, 0.0, n+1, submem);
    MSK_freetask(task, (void*)submem);
}
```

Powers

$$t \geq |x|^p, p > 1$$

Listing 6.22: Power.

```
// t >= |x|^p (where p>1)
void msk_pow(MSKtask_t task, int t, int x, double p) {
    int submem[3];
    submem[0] = t, submem[1] = msk_newvar_fx(task, 1, 1.0), submem[2] = x;
    MSK_appendcone(task, MSK_CT_PPOW, 1.0/p, 3, submem);
}
```

$$t \geq 1/x^p, x > 0, p > 0$$

Listing 6.23: Power reciprocal.

```
// t >= 1/x^p, x>0 (where p>0)
void msk_pow_inv(MSKtask_t task, int t, int x, double p) {
    int submem[3];
    submem[0] = t, submem[1] = x, submem[2] = msk_newvar_fx(task, 1, 1.0);
}
```

(continues on next page)


```
MSK_appendcone(task, MSK_CT_PPOW, 1.0/(1.0+p), 3, submem);
}
```

p-norm

$$t \geq (\sum_i |x_i|^p)^{1/p}, p > 1$$

Listing 6.24: p -norm.

```
// t >= ||x||_p (where p>1), x is a list of variables
void msk_pnorm(MSKtask_t task, int t, int n, int* x, double p) {
    int i, r, c, submem[3];
    r = msk_newvar(task, n);
    for(i=0; i<n; i++) {
        submem[0] = t, submem[1] = r+i, submem[2] = x[i];
        MSK_appendcone(task, MSK_CT_PPOW, 1.0-1.0/p, 3, submem);
    }
    c = msk_newcon(task, 1);
    for(i=0; i<n; i++)
        MSK_putaij(task, c, r+i, -1.0);
    MSK_putaij(task, c, t, 1.0);
    MSK_putconbound(task, c, MSK_BK_FX, 0.0, 0.0);
}
```

Geometric mean

$$t \leq (x_1 \cdots x_n)^{1/n}, x_i > 0$$

Listing 6.25: Geometric mean.

```
// |t| <= (x_1...x_n)^(1/n), x_i>=0, x is a list of variables of Length >= 1
void msk_geo_mean(MSKtask_t task, int t, int n, int* x) {
    if (n==1) msk_abs(task, x[0], t);
    else {
        int t2, submem[3];
        t2 = msk_newvar(task, 1);
        submem[0] = t2, submem[1] = x[n-1], submem[2] = t;
        MSK_appendcone(task, MSK_CT_PPOW, 1.0-1.0/n, 3, submem);
        msk_geo_mean(task, msk_dup(task, t2), n-1, x);
    }
}
```

6.9.4 Exponentials and logarithms

log

$$t \leq \log x, x > 0$$

Listing 6.26: Logarithm.

```
// t <= log(x), x>=0
void msk_log(MSKtask_t task, int t, int x) {
    int submem[3];
    submem[0] = x, submem[1] = msk_newvar_fx(task, 1, 1.0), submem[2] = t;
    MSK_appendcone(task, MSK_CT_PEXP, 0.0, 3, submem);
}
```

exp

$$t \geq e^x$$

Listing 6.27: Exponential.

```
// t >= exp(x)
void msk_exp(MSKtask_t task, int t, int x) {
    int submem[3];
    submem[0] = t, submem[1] = msk_newvar_fx(task, 1, 1.0), submem[2] = x;
    MSK_appendcone(task, MSK_CT_PEXP, 0.0, 3, submem);
}
```

Entropy

$$t \geq x \log x, x > 0$$

Listing 6.28: Entropy.

```
// t >= x * log(x), x>=0
void msk_ent(MSKtask_t task, int t, int x) {
    int v, c, submem[3];
    v = msk_newvar(task, 1);
    c = msk_newcon(task, 1);
    MSK_putaij(task, c, v, 1.0);
    MSK_putaij(task, c, t, 1.0);
    MSK_putconbound(task, c, MSK_BK_FX, 0.0, 0.0);
    submem[0] = msk_newvar_fx(task, 1, 1.0), submem[1] = x, submem[2] = v;
    MSK_appendcone(task, MSK_CT_PEXP, 0.0, 3, submem);
}
```

Relative entropy

$$t \geq x \log x/y, x, y > 0$$

Listing 6.29: Relative entropy.

```
// t >= x * log(x/y), x,y>=0
void msk_relent(MSKtask_t task, int t, int x, int y) {
    int v, c, submem[3];
    v = msk_newvar(task, 1);
    c = msk_newcon(task, 1);
    MSK_putaij(task, c, v, 1.0);
    MSK_putaij(task, c, t, 1.0);
    MSK_putconbound(task, c, MSK_BK_FX, 0.0, 0.0);
    submem[0] = y, submem[1] = x, submem[2] = v;
    MSK_appendcone(task, MSK_CT_PEXP, 0.0, 3, submem);
}
```

Log-sum-exp

$$\log \sum_i e^{x_i} \leq t$$

Listing 6.30: Log-sum-exp.

```
// log( sum_i(exp(x_i)) ) <= t, where x is a list of variables
void msk_logsumexp(MSKtask_t task, int t, int n, int* x) {
    int z, u, c, s, i;
    u = msk_newvar(task, n);
    z = msk_newvar(task, n);
    for(i=0; i<n; i++) msk_exp(task, u+i, z+i);
    c = msk_newcon(task, n);
    for(i=0; i<n; i++) {
        MSK_putaij(task, c+i, x[i], 1.0);
    }
}
```

(continues on next page)

(continued from previous page)

```
MSK_putaij(task, c+i, t, -1.0);
MSK_putaij(task, c+i, z+i, -1.0);
MSK_putconbound(task, c+i, MSK_BK_FX, 0.0, 0.0);
}
s = msk_newcon(task, 1);
for(i=0; i<n; i++) MSK_putaij(task, s, u+i, 1.0);
MSK_putconbound(task, s, MSK_BK_UP, -inf, 1.0);
}
```

6.9.5 Integer Modeling

Semicontinuous variable

$$x \in \{0\} \cup [a, b], b > a > 0$$

Listing 6.31: Semicontinuous variable.

```
// x = 0 or a <= x <= b
void msk_semicontinuous(MSKtask_t task, int x, double a, double b) {
    int u, c;
    u = msk_newvar_bin(task, 1);
    c = msk_newcon(task, 2);
    MSK_putaij(task, c, x, 1.0);
    MSK_putaij(task, c, u, -a);
    MSK_putconbound(task, c, MSK_BK_LO, 0.0, inf);
    MSK_putaij(task, c+1, x, 1.0);
    MSK_putaij(task, c+1, u, -b);
    MSK_putconbound(task, c+1, MSK_BK_UP, -inf, 0.0);
}
```

Indicator variable

$x \neq 0 \implies t = 1$. We assume x is a priori normalized so $|x_i| \leq 1$.

Listing 6.32: Indicator variable.

```
// x!=0 implies t=1. Assumes that |x|<=1 in advance.
int msk_indicator(MSKtask_t task, int x) {
    int t;
    t = msk_newvar_bin(task, 1);
    msk_abs(task, t, x);
    return t;
}
```

Logical OR

At least one of the conditions is true.

Listing 6.33: Logical OR.

```
// x OR y, where x, y are binary
void msk_logic_or(MSKtask_t task, int x, int y) {
    int c;
    c = msk_newcon(task, 1);
    MSK_putaij(task, c, x, 1.0);
    MSK_putaij(task, c, y, 1.0);
    MSK_putconbound(task, c, MSK_BK_LO, 1.0, inf);
}
// x_1 OR ... OR x_n, where x is sequence of variables
void msk_logic_or_vect(MSKtask_t task, int n, int* x) {
```

(continues on next page)

(continued from previous page)

```
int c, i;
c = msk_newcon(task, 1);
for(i=0; i<n; i++) MSK_putaij(task, c, x[i], 1.0);
MSK_putconbound(task, c, MSK_BK_LO, 1.0, inf);
}
```

Logical NAND

At most one of the conditions is true (also known as SOS1).

Listing 6.34: Logical NAND.

```
// at most one of x_1,...,x_n, where x is a binary vector (SOS1 constraint)
void msk_logic_sos1(MSKtask_t task, int n, int* x) {
    int c, i;
    c = msk_newcon(task, 1);
    for(i=0; i<n; i++) MSK_putaij(task, c, x[i], 1.0);
    MSK_putconbound(task, c, MSK_BK_UP, -inf, 1.0);
}
// NOT(x AND y), where x, y are binary
void msk_logic_nand(MSKtask_t task, int x, int y) {
    int c;
    c = msk_newcon(task, 1);
    MSK_putaij(task, c, x, 1.0);
    MSK_putaij(task, c, y, 1.0);
    MSK_putconbound(task, c, MSK_BK_UP, -inf, 1.0);
}
```

Cardinality bound

At most k of the continuous variables are nonzero. We assume x is a priori normalized so $|x_i| \leq 1$.

Listing 6.35: Cardinality bound.

```
// At most k of entries in x are nonzero, assuming in advance that |x_i|<=1.
void msk_card(MSKtask_t task, int n, int* x, int k) {
    int t, i, c;
    t = msk_newvar_bin(task, n);
    for(i=0; i<n; i++) msk_abs(task, t+i, x[i]);
    c = msk_newcon(task, 1);
    for(i=0; i<n; i++) MSK_putaij(task, c, t+i, 1.0);
    MSK_putconbound(task, c, MSK_BK_UP, -inf, k);
}
```

6.9.6 Model assembly example

We now demonstrate how to quickly build a simple optimization model for the problem

$$\begin{aligned} &\text{maximize} && -\sqrt{x^2 + y^2} + \log y - x^{1.5}, \\ &\text{subject to} && x \geq y + 3, \end{aligned} \tag{6.21}$$

or equivalently

$$\begin{aligned} &\text{maximize} && -t_0 + t_1 - t_2, \\ &\text{subject to} && x \geq y + 3, \\ & && t_0 \geq \sqrt{x^2 + y^2}, \\ & && t_1 \leq \log y, \\ & && t_2 \geq x^{1.5}. \end{aligned}$$

Listing 6.36: Modeling (6.21).

```
MSK_makeemptytask(env, &task);

x = msk_newvar(task, 1);
y = msk_newvar(task, 1);
t = msk_newvar(task, 3);

c = msk_newcon(task, 1);
MSK_putaij(task, c, x, 1.0);
MSK_putaij(task, c, y, -1.0);
MSK_putconbound(task, c, MSK_BK_LO, 3.0, inf);

sub[0] = x, sub[1] = y;
msk_norm2(task, t+0, 2, sub);
msk_log (task, t+1, msk_dup(task, y));
msk_pow (task, t+2, msk_dup(task, x), 1.5);

sub[0] = t, sub[1] = t+1, sub[2] = t+2;
cj[0] = -1.0, cj[1] = 1.0, cj[2] = -1.0;
MSK_putclist(task, 3, sub, cj);
MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE);
```

6.10 Problem Modification and Reoptimization

Often one might want to solve not just a single optimization problem, but a sequence of problems, each differing only slightly from the previous one. This section demonstrates how to modify and re-optimize an existing problem. The example we study is a simple production planning model.

Problem modifications regarding variables, cones, objective function and constraints can be grouped in categories:

- add/remove,
- coefficient modifications,
- bounds modifications.

Especially removing variables and constraints can be costly. Special care must be taken with respect to constraints and variable indexes that may be invalidated.

Depending on the type of modification, **MOSEK** may be able to optimize the modified problem more efficiently exploiting the information and internal state from the previous execution. After optimization, the solution is always stored internally, and is available before next optimization. The former optimal solution may be still feasible, but no longer optimal; or it may remain optimal if the modification of the objective function was small. This special case is discussed in [Sec. 14.3](#).

In general, **MOSEK** exploits dual information and availability of an optimal basis from the previous execution. The simplex optimizer is well suited for exploiting an existing primal or dual feasible solution. Restarting capabilities for interior-point methods are still not as reliable and effective as those for the simplex algorithm. More information can be found in Chapter 10 of the book [\[Chv83\]](#).

Parameter settings (see [Sec. 7.4](#)) can also be changed between optimizations.

6.10.1 Example: Production Planning

A company manufactures three types of products. Suppose the stages of manufacturing can be split into three parts: Assembly, Polishing and Packing. In the table below we show the time required for each stage as well as the profit associated with each product.

Product no.	Assembly (minutes)	Polishing (minutes)	Packing (minutes)	Profit (\$)
0	2	3	2	1.50
1	4	2	3	2.50
2	3	3	2	3.00

With the current resources available, the company has 100,000 minutes of assembly time, 50,000 minutes of polishing time and 60,000 minutes of packing time available per year. We want to know how many items of each product the company should produce each year in order to maximize profit?

Denoting the number of items of each type by x_0, x_1 and x_2 , this problem can be formulated as a linear optimization problem:

$$\begin{aligned} & \text{maximize} && 1.5x_0 + 2.5x_1 + 3.0x_2 \\ & \text{subject to} && 2x_0 + 4x_1 + 3x_2 \leq 100000, \\ & && 3x_0 + 2x_1 + 3x_2 \leq 50000, \\ & && 2x_0 + 3x_1 + 2x_2 \leq 60000, \end{aligned} \tag{6.22}$$

and

$$x_0, x_1, x_2 \geq 0.$$

Code in [Listing 6.37](#) loads and solves this problem.

Listing 6.37: Setting up and solving problem (6.22)

```
MSKint32t      numvar = 3,
               numcon = 3;
MSKint32t      i, j;
double         c[]  = {1.5, 2.5, 3.0};
MSKint32t      ptrb[] = {0, 3, 6},
               ptre[] = {3, 6, 9},
               asub[] = { 0, 1, 2,
                        0, 1, 2,
                        0, 1, 2
                        };

double         aval[] = { 2.0, 3.0, 2.0,
                        4.0, 2.0, 3.0,
                        3.0, 3.0, 2.0
                        };

MSKboundkeye   bkc[]  = {MSK_BK_UP, MSK_BK_UP, MSK_BK_UP   };
double         blc[]  = { -MSK_INFINITY, -MSK_INFINITY, -MSK_INFINITY};
double         buc[]  = {100000, 50000, 60000};

MSKboundkeye   bkc[]  = {MSK_BK_LO,   MSK_BK_LO,   MSK_BK_LO};
double         blx[]  = {0.0,         0.0,         0.0,};
double         bux[]  = { +MSK_INFINITY, +MSK_INFINITY, +MSK_INFINITY};

double         *xx = NULL;
MSKenv_t       env;
MSKtask_t      task;
MSKint32t      varidx, conidx;
MSKrescodee    r,lr;

/* Create the mosek environment. */
r = MSK_makeenv(&env, DEBUG ? "" : NULL);

if (r == MSK_RES_OK)
{
    /* Create the optimization task. */
    r = MSK_maketask(env, numcon, numvar, &task);

    /* Append the constraints. */
    if (r == MSK_RES_OK)
        r = MSK_appendcons(task, numcon);

    /* Append the variables. */
```

(continues on next page)

```

if (r == MSK_RES_OK)
    r = MSK_appendvars(task, numvar);

/* Put C. */
if (r == MSK_RES_OK)
    r = MSK_putcfix(task, 0.0);

if (r == MSK_RES_OK)
    for (j = 0; j < numvar; ++j)
        r = MSK_putcj(task, j, c[j]);

/* Put constraint bounds. */
if (r == MSK_RES_OK)
    for (i = 0; i < numcon; ++i)
        r = MSK_putconbound(task, i, bkc[i], blc[i], buc[i]);

/* Put variable bounds. */
if (r == MSK_RES_OK)
    for (j = 0; j < numvar; ++j)
        r = MSK_putvarbound(task, j, bkc[j], blc[j], buc[j]);

/* Put A. */
if (r == MSK_RES_OK)
    if (numcon > 0)
        for (j = 0; j < numvar; ++j)
            r = MSK_putacol(task,
                             j,
                             ptre[j] - ptrb[j],
                             asub + ptrb[j],
                             aval + ptrb[j]);

if (r == MSK_RES_OK)
    r = MSK_putobjsense(task,
                        MSK_OBJECTIVE_SENSE_MAXIMIZE);

if (r == MSK_RES_OK)
    r = MSK_optimizetrm(task, NULL);

if (r == MSK_RES_OK)
{
    xx = calloc(numvar, sizeof(double));
    if (!xx)
        r = MSK_RES_ERR_SPACE;
}

if (r == MSK_RES_OK)
    r = MSK_getxx(task,
                  MSK_SOL_BAS,      /* Basic solution. */
                  xx);

```

6.10.2 Changing the Linear Constraint Matrix

Suppose we want to change the time required for assembly of product 0 to 3 minutes. This corresponds to setting $a_{0,0} = 3$, which is done by calling the function *MSK_putaij* as shown below.

```

if (r == MSK_RES_OK)
    r = MSK_putaij(task, 0, 0, 3.0);

```

The problem now has the form:

$$\begin{aligned}
 & \text{maximize} && 1.5x_0 &+& 2.5x_1 &+& 3.0x_2 \\
 & \text{subject to} && 3x_0 &+& 4x_1 &+& 3x_2 &\leq 100000, \\
 & && 3x_0 &+& 2x_1 &+& 3x_2 &\leq 50000, \\
 & && 2x_0 &+& 3x_1 &+& 2x_2 &\leq 60000,
 \end{aligned} \tag{6.23}$$

and

$$x_0, x_1, x_2 \geq 0.$$

After this operation we can reoptimize the problem.

6.10.3 Appending Variables

We now want to add a new product with the following data:

Product no.	Assembly (minutes)	Polishing (minutes)	Packing (minutes)	Profit (\$)
3	4	0	1	1.00

This corresponds to creating a new variable x_3 , appending a new column to the A matrix and setting a new term in the objective. We do this in [Listing 6.38](#)

Listing 6.38: How to add a new variable (column)

```

/***** Add a new variable *****/
/* Get index of new variable, this should be 3 */
if (r == MSK_RES_OK)
    r = MSK_getnumvar(task, &varidx);
/* Append a new variable x_3 to the problem */
if (r == MSK_RES_OK)
{
    r = MSK_appendvars(task, 1);
    numvar++;
}
/* Set bounds on new variable */
if (r == MSK_RES_OK)
    r = MSK_putvarbound(task,
                        varidx,
                        MSK_BK_LO,
                        0,
                        +MSK_INFINITY);

/* Change objective */
if (r == MSK_RES_OK)
    r = MSK_putcj(task, varidx, 1.0);

/* Put new values in the A matrix */
if (r == MSK_RES_OK)
{
    MSKint32t acolsub[] = {0, 2};
    double    acolval[] = {4.0, 1.0};

    r = MSK_putacol(task,
                    varidx, /* column index */
                    2, /* num nz in column */
                    acolsub,
                    acolval);
}

```


After this operation the new problem is:

$$\begin{array}{llllllll}
\text{maximize} & 1.5x_0 & + & 2.5x_1 & + & 3.0x_2 & + & 1.0x_3 \\
\text{subject to} & 3x_0 & + & 4x_1 & + & 3x_2 & + & 4x_3 & \leq & 100000, \\
& 3x_0 & + & 2x_1 & + & 3x_2 & & & \leq & 50000, \\
& 2x_0 & + & 3x_1 & + & 2x_2 & + & 1x_3 & \leq & 60000,
\end{array} \tag{6.24}$$

and

$$x_0, x_1, x_2, x_3 \geq 0.$$

6.10.4 Appending Constraints

Now suppose we want to add a new stage to the production process called *Quality control* for which 30000 minutes are available. The time requirement for this stage is shown below:

Product no.	Quality control (minutes)
0	1
1	2
2	1
3	1

This corresponds to adding the constraint

$$x_0 + 2x_1 + x_2 + x_3 \leq 30000$$

to the problem. This is done as follows.

Listing 6.39: Adding a new constraint.

```

/* ***** Add a new constraint ***** */
/* Get index of new constraint*/
if (r == MSK_RES_OK)
    r = MSK_getnumcon(task, &conidx);

/* Append a new constraint */
if (r == MSK_RES_OK)
{
    r = MSK_appendcons(task, 1);
    numcon++;
}

/* Set bounds on new constraint */
if (r == MSK_RES_OK)
    r = MSK_putconbound(task,
                        conidx,
                        MSK_BK_UP,
                        -MSK_INFINITY,
                        30000);

/* Put new values in the A matrix */
if (r == MSK_RES_OK)
{
    MSKint32t arowsub[] = {0, 1, 2, 3 };
    double arowval[] = {1.0, 2.0, 1.0, 1.0};

    r = MSK_putarow(task,
                    conidx, /* row index */
                    4, /* num nz in row*/
                    arowsub,
                    arowval);
}

```

Again, we can continue with re-optimizing the modified problem.

6.10.5 Changing bounds

One typical reoptimization scenario is to change bounds. Suppose for instance that we must operate with limited time resources, and we must change the upper bounds in the problem as follows:

Operation	Time available (before)	Time available (new)
Assembly	100000	80000
Polishing	50000	40000
Packing	60000	50000
Quality control	30000	22000

That means we would like to solve the problem:

$$\begin{aligned}
 &\text{maximize} && 1.5x_0 &+& 2.5x_1 &+& 3.0x_2 &+& 1.0x_3 \\
 &\text{subject to} && 3x_0 &+& 4x_1 &+& 3x_2 &+& 4x_3 &\leq 80000, \\
 & && 3x_0 &+& 2x_1 &+& 3x_2 && &\leq 40000, \\
 & && 2x_0 &+& 3x_1 &+& 2x_2 &+& 1x_3 &\leq 50000, \\
 & && x_0 &+& 2x_1 &+& x_2 &+& x_3 &\leq 22000.
 \end{aligned} \tag{6.25}$$

In this case all we need to do is redefine the upper bound vector for the constraints, as shown in the next listing.

Listing 6.40: Change constraint bounds.

```

/* ***** Change constraint bounds ***** */
if (r == MSK_RES_OK)
{
    MSKboundkey newbkc[] = { MSK_BK_UP, MSK_BK_UP, MSK_BK_UP, MSK_BK_UP };
    double newblc[] = { -MSK_INFINITY, -MSK_INFINITY, -MSK_INFINITY, -MSK_INFINITY };
    double newbuc[] = { 80000, 40000, 50000, 22000 };

    r = MSK_putconboundslice(task, 0, numcon, newbkc, newblc, newbuc);
}

```

Again, we can continue with re-optimizing the modified problem.

6.10.6 Advanced hot-start

If the optimizer used the data from the previous run to hot-start the optimizer for reoptimization, this will be indicated in the log:

```
Optimizer - hotstart : yes
```

When performing re-optimizations, instead of removing a basic variable it may be more efficient to fix the variable at zero and then remove it when the problem is re-optimized and it has left the basis. This makes it easier for **MOSEK** to restart the simplex optimizer.

6.11 Parallel optimization

In this section we demonstrate the simplest possible multi-threading setup to run multiple **MOSEK** optimizations in parallel. All tasks must be created using the same **MOSEK** environment. One license token checked out by the environment will be shared by the tasks.

We first define a simple method that runs a number of optimization tasks in parallel, using the standard multi-threading setup available in the language.

Listing 6.41: Parallel optimization of a list of tasks. (C++).

```

/** Runs a single task */
void runTask(int num,
             MSKtask_t task,
             MSKrescodee *res,

```

(continues on next page)

```

        MSKrescodee *trm)
{
    *res = MSK_optimizetrm(task, trm);
}

/** Takes a list of tasks and optimizes then in parallel. The
    response code and termination code from each optimization is
    stored in ``res`` and ``trm``.
    */
void paropt(int          n,
            MSKtask_t    *tasks,
            MSKrescodee *res,
            MSKrescodee *trm)
{
    int i;
    std::thread * jobs = new std::thread[n];

    // Initialize
    for(i = 0; i < n; ++i) {
        res[i] = trm[i] = MSK_RES_ERR_UNKNOWN;
        jobs[i] = std::thread(runTask, i, tasks[i], &(res[i]), &(trm[i]));
    }

    // Join all threads
    for(i = 0; i < n; ++i) jobs[i].join();
    delete[] jobs;
}

```

It remains to call the method with a few different tasks. When optimizing many task in parallel it usually makes sense to solve each task using one thread to avoid additional multitasking overhead. When all tasks complete we access the solutions in the standard way.

Listing 6.42: Calling the parallel optimizer (C++).

```

/** Example of how to use ``paropt``.
    Optimizes tasks whose names were read from command line.
    */
int main(int argc, char **argv)
{
    MSKenv_t env;
    int n = argc - 1;
    MSKtask_t *tasks = new MSKtask_t[n];
    MSKrescodee *res = new MSKrescodee[n];
    MSKrescodee *trm = new MSKrescodee[n];

    MSK_makeenv(&env, NULL);

    for (int i = 0; i < n; i++) {
        MSK_makeemptytask(env, &(tasks[i]));
        MSK_readdata(tasks[i], argv[i+1]);
        // Each task will be single-threaded
        MSK_putintparam(tasks[i], MSK_IPAR_INTPNT_MULTI_THREAD, MSK_OFF);
    }

    paropt(n, tasks, res, trm);

    for(int i = 0; i < n; i++) {
        double obj, tm;
        MSK_getdouinf(tasks[i], MSK_DINF_INTPNT_PRIMAL_OBJ, &obj);
        MSK_getdouinf(tasks[i], MSK_DINF_OPTIMIZER_TIME, &tm);
    }
}

```

(continued from previous page)

```
printf("Task %d res %d trm %d obj_val %.5f time %.5f\n",
      i,
      res[i],
      trm[i],
      obj,
      tm);
}

for(int i = 0; i < n; i++)
    MSK_deletetask(&(amp;tasks[i]));
delete[] tasks;
delete[] res;
delete[] trm;
MSK_deleteenv(&env);
return 0;
}
```

Another, slightly more advanced application of the parallel optimizer is presented in [Sec. 11.3](#). For a more in-depth treatment see the following sections:

- *Case studies* for more advanced and complicated optimization examples.
- *Problem Formulation and Solutions* for formal mathematical formulations of problems **MOSEK** can solve, dual problems and infeasibility certificates.

Chapter 7

Solver Interaction Tutorials

In this section we cover the interaction with the solver.

7.1 Accessing the solution

This section contains important information about the status of the solver and the status of the solution, which must be checked in order to properly interpret the results of the optimization.

7.1.1 Solver termination

The optimizer provides two status codes relevant for error handling:

- **Response code** of type *MSKrescodee*. It indicates if any unexpected error (such as an out of memory error, licensing error etc.) has occurred. The expected value for a successful optimization is *MSK_RES_OK*.
- **Termination code**: It provides information about why the optimizer terminated, for instance if a predefined time limit has been reached. These are not errors, but ordinary events that can be expected (depending on parameter settings and the type of optimizer used).

To obtain both codes separately call the function *MSK_optimizetrm* to optimize the problem. When using the simplified *MSK_optimize* the response code or termination code most relevant for the user will be returned.

If a runtime error causes the program to crash during optimization, the first debugging step is to enable logging and check the log output. See [Sec. 7.3](#).

If the optimization completes successfully, the next step is to check the solution status, as explained below.

7.1.2 Available solutions

MOSEK uses three kinds of optimizers and provides three types of solutions:

- **basic solution** from the simplex optimizer,
- **interior-point solution** from the interior-point optimizer,
- **integer solution** from the mixed-integer optimizer.

Under standard parameters settings the following solutions will be available for various problem types:

Table 7.1: Types of solutions available from **MOSEK**

	Simplex optimizer	Interior-point optimizer	Mixed-integer optimizer
Linear problem	<i>MSK_SOL_BAS</i>	<i>MSK_SOL_ITR</i>	
Nonlinear continuous problem		<i>MSK_SOL_ITR</i>	
Problem with integer variables			<i>MSK_SOL_ITG</i>

For linear problems the user can force a specific optimizer choice making only one of the two solutions available. For example, if the user disables basis identification, then only the interior point solution will be available for a linear problem. Numerical issues may cause one of the solutions to be unknown even if another one is feasible.

Not all components of a solution are always available. For example, there is no dual solution for integer problems and no dual conic variables from the simplex optimizer.

The user will always need to specify which solution should be accessed.

7.1.3 Problem and solution status

Assuming that the optimization terminated without errors, the next important step is to check the problem and solution status. There is one for every type of solution, as explained above.

Problem status

Problem status (*MSKprosta*) determines whether the problem is certified as feasible. Its values can roughly be divided into the following broad categories:

- **feasible** — the problem is feasible. For continuous problems and when the solver is run with default parameters, the feasibility status should ideally be *MSK_PRO_STA_PRIM_AND_DUAL_FEAS*.
- **primal/dual infeasible** — the problem is infeasible or unbounded or a combination of those. The exact problem status will indicate the type of infeasibility.
- **unknown** — the solver was unable to reach a conclusion, most likely due to numerical issues.

Solution status

Solution status (*MSKsolsta*) provides the information about what the solution values actually contain. The most important broad categories of values are:

- **optimal** (*MSK_SOL_STA_OPTIMAL*) — the solution values are feasible and optimal.
- **certificate** — the solution is in fact a certificate of infeasibility (primal or dual, depending on the solution).
- **unknown/undefined** — the solver could not solve the problem or this type of solution is not available for a given problem.

Problem and solution status for each solution can be retrieved with *MSK_getprosta* and *MSK_getsolsta*, respectively.

The solution status determines the action to be taken. For example, in some cases a suboptimal solution may still be valuable and deserve attention. It is the user's responsibility to check the status and quality of the solution.

Typical status reports

Here are the most typical optimization outcomes described in terms of the problem and solution statuses. Note that these do not cover all possible situations that can occur.

Table 7.2: Continuous problems (solution status for interior-point and basic solution)

Outcome	Problem status	Solution status
Optimal	<i>MSK_PRO_STA_PRIM_AND_DUAL_FEAS</i>	<i>MSK_SOL_STA_OPTIMAL</i>
Primal infeasible	<i>MSK_PRO_STA_PRIM_INFEAS</i>	<i>MSK_SOL_STA_PRIM_INFEAS_CER</i>
Dual infeasible (unbounded)	<i>MSK_PRO_STA_DUAL_INFEAS</i>	<i>MSK_SOL_STA_DUAL_INFEAS_CER</i>
Uncertain (stall, numerical issues, etc.)	<i>MSK_PRO_STA_UNKNOWN</i>	<i>MSK_SOL_STA_UNKNOWN</i>

Table 7.3: Integer problems (solution status for integer solution, others undefined)

Outcome	Problem status	Solution status
Integer optimal	<i>MSK_PRO_STA_PRIM_FEAS</i>	<i>MSK_SOL_STA_INTEGER_OPTIMAL</i>
Infeasible	<i>MSK_PRO_STA_PRIM_INFEAS</i>	<i>MSK_SOL_STA_UNKNOWN</i>
Integer feasible point	<i>MSK_PRO_STA_PRIM_FEAS</i>	<i>MSK_SOL_STA_PRIM_FEAS</i>
No conclusion	<i>MSK_PRO_STA_UNKNOWN</i>	<i>MSK_SOL_STA_UNKNOWN</i>

7.1.4 Retrieving solution values

After the meaning and quality of the solution (or certificate) have been established, we can query for the actual numerical values. They can be accessed using:

- *MSK_getprimalobj*, *MSK_getdualobj* — the primal and dual objective value.
- *MSK_getxx* — solution values for the variables.
- *MSK_getsolution* — a full solution with primal and dual values

and many more specialized methods, see the *API reference*.

7.1.5 Source code example

Below is a source code example with a simple framework for assessing and retrieving the solution to a conic optimization problem.

Listing 7.1: Sample framework for checking optimization result.

```
#include <stdio.h>
#include "mosek.h"

/* Log handler */
void MSKAPI printlog(void *ptr,
                    const char s[])
{
    printf("%s", s);
}

int main(int argc, char const *argv[])
{
    MSKenv_t    env;
    MSKtask_t   task;
    MSKrescodee r;
    char        symname[MSK_MAX_STR_LEN];
    char        desc[MSK_MAX_STR_LEN];
    int         i, numvar;
    double      *xx = NULL;
    const char  *filename;

    if (argc >= 2) filename = argv[1];
    else          filename = "../data/cqo1.mps";

    // Create the environment
    r = MSK_makeenv(&env, NULL);

    if (r == MSK_RES_OK)
    {
        // Create the task
        r = MSK_makeemptytask(env, &task);

        // (Optionally) attach the log handler to receive log information
    }
}
```

(continues on next page)

```

// if ( r == MSK_RES_OK ) MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printlog);

// (Optionally) uncomment this line to most likely see solution status Unknown
// MSK_putintparam(task, MSK_IPAR_INTPNT_MAX_ITERATIONS, 1);

// In this example we read an optimization problem from a file
r = MSK_readdata(task, filename);

if (r == MSK_RES_OK)
{
    MSKrescodee trmcode;
    MSKsolstae solsta;

    // Do the optimization, and exit in case of error
    r = MSK_optimizetrm(task, &trmcode);

    if (r != MSK_RES_OK) {
        MSK_getcodedesc(r, symname, desc);
        printf("Error during optimization: %s %s\n", symname, desc);
        exit(r);
    }

    MSK_solutionsummary(task, MSK_STREAM_LOG);

    /* Expected result: The solution status of the interior-point solution is optimal. */

    if (MSK_RES_OK == MSK_getsolsta(task, MSK_SOL_ITR, &solsta))
    {
        switch (solsta)
        {
            case MSK_SOL_STA_OPTIMAL:
                printf("An optimal interior-point solution is located.\n");

                /* Read and print the variable values in the solution */
                MSK_getnumvar(task, &numvar);
                xx = calloc(numvar, sizeof(double));
                MSK_getxx(task, MSK_SOL_ITR, xx);
                for (i = 0; i < numvar; i++)
                    printf("xx[%d] = %.4lf\n", i, xx[i]);
                free(xx);
                break;

            case MSK_SOL_STA_DUAL_INFEAS_CER:
                printf("Dual infeasibility certificate found.\n");
                break;

            case MSK_SOL_STA_PRIM_INFEAS_CER:
                printf("Primal infeasibility certificate found.\n");
                break;

            case MSK_SOL_STA_UNKNOWN:
                /* The solutions status is unknown. The termination code
                   indicating why the optimizer terminated prematurely. */
                printf("The solution status is unknown.\n");
                /* No-error cause of termination e.g. an iteration limit is reached. */
                MSK_getcodedesc(trmcode, symname, desc);
                printf("Termination code: %s %s\n", symname, desc);
                break;

            default:
                MSK_solstatostr(task, solsta, desc);
        }
    }
}

```


(continued from previous page)

```
        printf("An unexpected solution status %s with code %d is obtained.\n", desc, solsta);
        break;
    }
}
else
    printf("Could not obtain the solution status for the requested solution.\n");
}
else {
    MSK_getcodedesc(r, symname, desc);
    printf("Optimization was not started because of error %s(%d): %s\n", symname, r, desc);
}

MSK_deletetask(&task);
}

MSK_deleteenv(&env);
return r;
}
```

7.2 Errors and exceptions

Response codes

Almost every function in Optimizer API for C returns a **response code**, which is an integer (implemented as the enum *MSKrescodee*), informing if the requested operation was performed correctly, and if not, what error occurred. The expected response, indicating successful execution, is always *MSK_RES_OK*. It is a good idea to check the response code every time to avoid silent fails such as for instance:

- referencing a nonexistent variable (for example with too large index),
- defining an invalid value for a parameter,
- accessing an undefined solution,
- repeating a variable name, etc.

The one case where it is *extremely important* to check the response code is during optimization, when *MSK_optimizetrm* is invoked. We will say more about this in [Sec. 7.1](#).

A numerical response code can be converted into a human-readable description using *MSK_getcodedesc*. A full list of response codes, error, warning and termination codes can be found in the *API reference*. For example, the following code

```
res = MSK_putdoupam(task, MSK_DPAR_INTPNT_CO_TOL_REL_GAP, -1.0e-7);
if (res != MSK_RES_OK) {
    MSK_getcodedesc(res, symb, str);
    printf("Error %s(%d): %s\n", symb, res, str);
}
```

will produce as output:

```
Error MSK_RES_ERR_PARAM_IS_TOO_SMALL(1216): A parameter value is too small.
```

Optimizer errors and warnings

The optimizer may also produce warning messages. They indicate non-critical but important events, that will not prevent solver execution, but may be an indication that something in the optimization problem might be improved. Warning messages are normally printed to a log stream (see [Sec. 7.3](#)). A typical warning is, for example:

MOSEK warning 53: A numerically large upper bound value 6.6e+09 is specified for constraint
↪ 'C69200' (46020).

Warnings can also be suppressed by setting the `MSK_IPAR_MAX_NUM_WARNINGS` parameter to zero, if they are well-understood.

The user can also register a dedicated callback function to handle all errors and warnings. This is done with `MSK_putresponsefunc`.

Error and solution status handling example

Below is a source code example with a simple framework for handling major errors when assessing and retrieving the solution to a conic optimization problem.

Listing 7.2: Sample framework for checking optimization result.

```
#include <stdio.h>
#include "mosek.h"

/* Log handler */
void MSKAPI printlog(void *ptr,
                    const char s[])
{
    printf("%s", s);
}

int main(int argc, char const *argv[])
{
    MSKenv_t    env;
    MSKtask_t   task;
    MSKrescodee r;
    char        symname[MSK_MAX_STR_LEN];
    char        desc[MSK_MAX_STR_LEN];
    int         i, numvar;
    double      *xx = NULL;
    const char  *filename;

    if (argc >= 2) filename = argv[1];
    else          filename = "../data/cqo1.mps";

    // Create the environment
    r = MSK_makeenv(&env, NULL);

    if (r == MSK_RES_OK)
    {
        // Create the task
        r = MSK_makeemptytask(env, &task);

        // (Optionally) attach the log handler to receive log information
        // if ( r == MSK_RES_OK ) MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printlog);

        // (Optionally) uncomment this line to most likely see solution status Unknown
        // MSK_putintparam(task, MSK_IPAR_INTPNT_MAX_ITERATIONS, 1);

        // In this example we read an optimization problem from a file
        r = MSK_readdata(task, filename);

        if (r == MSK_RES_OK)
        {
            MSKrescodee trmcode;
            MSKsolstae  solsta;

            // Do the optimization, and exit in case of error
```

(continues on next page)

```

r = MSK_optimizetrm(task, &trmcode);

if (r != MSK_RES_OK) {
    MSK_getcodedesc(r, symname, desc);
    printf("Error during optimization: %s %s\n", symname, desc);
    exit(r);
}

MSK_solutionsummary(task, MSK_STREAM_LOG);

/* Expected result: The solution status of the interior-point solution is optimal. */

if (MSK_RES_OK == MSK_getsolsta(task, MSK_SOL_ITR, &solsta))
{
    switch (solsta)
    {
        case MSK_SOL_STA_OPTIMAL:
            printf("An optimal interior-point solution is located.\n");

            /* Read and print the variable values in the solution */
            MSK_getnumvar(task, &numvar);
            xx = calloc(numvar, sizeof(double));
            MSK_getxx(task, MSK_SOL_ITR, xx);
            for (i = 0; i < numvar; i++)
                printf("xx[%d] = %.4lf\n", i, xx[i]);
            free(xx);
            break;

        case MSK_SOL_STA_DUAL_INFEAS_CER:
            printf("Dual infeasibility certificate found.\n");
            break;

        case MSK_SOL_STA_PRIM_INFEAS_CER:
            printf("Primal infeasibility certificate found.\n");
            break;

        case MSK_SOL_STA_UNKNOWN:
            /* The solutions status is unknown. The termination code
               indicating why the optimizer terminated prematurely. */
            printf("The solution status is unknown.\n");
            /* No-error cause of termination e.g. an iteration limit is reached. */
            MSK_getcodedesc(trmcode, symname, desc);
            printf("Termination code: %s %s\n", symname, desc);
            break;

        default:
            MSK_solstatostr(task, solsta, desc);
            printf("An unexpected solution status %s with code %d is obtained.\n", desc,
↪solsta);
            break;
    }
}
else
    printf("Could not obtain the solution status for the requested solution.\n");
}
else {
    MSK_getcodedesc(r, symname, desc);
    printf("Optimization was not started because of error %s(%d): %s\n", symname, r, desc);
}

MSK_deletetask(&task);

```

```

}

MSK_deleteenv(&env);
return r;
}

```

7.3 Input/Output

The logging and I/O features are provided mainly by the **MOSEK** task and to some extent by the **MOSEK** environment objects.

7.3.1 Stream logging

By default the solver runs silently and does not produce any output to the console or otherwise. However, the log output can be redirected to a user-defined output stream or stream callback function. The log output is analogous to the one produced by the command-line version of **MOSEK**.

The log messages are partitioned in three streams:

- messages, *MSK_STREAM_MSG*
- warnings, *MSK_STREAM_WRN*
- errors, *MSK_STREAM_ERR*

These streams are aggregated in the *MSK_STREAM_LOG* stream. A stream handler can be defined for each stream separately.

A stream handler is simply a user-defined function of type *MSKstreamfunc* that accepts a string, for example:

```

static void MSKAPI printstr(void *handle,
                           const char *str)
{
    printf("%s", str);
    fflush(stdout);
}

```

It is attached to a stream as follows:

```
MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);
```

The stream can be detached by calling

```
MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, NULL);
```

A log stream can also be redirected to a file:

```
MSK_linkfiletotaskstream(task, MSK_STREAM_LOG, "mosek.log", 0);
```

After optimization is completed an additional short summary of the solution and optimization process can be printed to any stream using the method *MSK_solutionsummary*.

7.3.2 Log verbosity

The logging verbosity can be controlled by setting the relevant parameters, as for instance

- *MSK_IPAR_LOG*,
- *MSK_IPAR_LOG_INTPNT*,
- *MSK_IPAR_LOG_MIO*,
- *MSK_IPAR_LOG_CUT_SECOND_OPT*,

- `MSK_IPAR_LOG_SIM`, and
- `MSK_IPAR_LOG_SIM_MINOR`.

Each parameter controls the output level of a specific functionality or algorithm. The main switch is `MSK_IPAR_LOG` which affect the whole output. The actual log level for a specific functionality is determined as the minimum between `MSK_IPAR_LOG` and the relevant parameter. For instance, the log level for the output produce by the interior-point algorithm is tuned by the `MSK_IPAR_LOG_INTPNT`; the actual log level is defined by the minimum between `MSK_IPAR_LOG` and `MSK_IPAR_LOG_INTPNT`.

Tuning the solver verbosity may require adjusting several parameters. It must be noticed that verbose logging is supposed to be of interest during debugging and tuning. When output is no more of interest, the user can easily disable it globally with `MSK_IPAR_LOG`. Larger values of `MSK_IPAR_LOG` do not necessarily result in increased output.

By default **MOSEK** will reduce the amount of log information after the first optimization on a given problem. To get full log output on subsequent re-optimizations set `MSK_IPAR_LOG_CUT_SECOND_OPT` to zero.

7.3.3 Saving a problem to a file

An optimization problem can be dumped to a file using the method `MSK_writedata`. The file format will be determined from the extension of the filename. Supported formats are listed in [Sec. 16](#) together with a table of problem types supported by each.

For instance the problem can be written to an OPF file with

```
MSK_writedata(task, "data.opf");
```

All formats can be compressed with `gzip` by appending the `.gz` extension, for example

```
MSK_writedata(task, "data.task.gz");
```

Some remarks:

- Unnamed variables are given generic names. It is therefore recommended to use meaningful variable names if the problem file is meant to be human-readable.
- The `task` format is **MOSEK**'s native file format which contains all the problem data as well as solver settings.

7.3.4 Reading a problem from a file

A problem saved in any of the supported file formats can be read directly into a task using `MSK_readdata`. The task must be created in advance. Afterwards the problem can be optimized, modified, etc. If the file contained solutions, then are also imported, but the status of any solution will be set to `MSK_SOL_STA_UNKNOWN` (solutions can also be read separately using `MSK_readsolution`). If the file contains parameters, they will be set accordingly.

```
res = MSK_maketask(env, 0,0, &task);
if (res == MSK_RES_OK)
    res = MSK_readdata(task, "file.task.gz");
if (res == MSK_RES_OK)
    res = MSK_optimize(task);
```

7.4 Setting solver parameters

MOSEK comes with a large number of parameters that allows the user to tune the behavior of the optimizer. The typical settings which can be changed with solver parameters include:

- choice of the optimizer for linear problems,
- choice of primal/dual solver,
- turning presolve on/off,

- turning heuristics in the mixed-integer optimizer on/off,
- level of multi-threading,
- feasibility tolerances,
- solver termination criteria,
- behaviour of the license manager,

and more. All parameters have default settings which will be suitable for most typical users. The API reference contains:

- *Full list of parameters*
- *List of parameters grouped by topic*

Setting parameters

Each parameter is identified by a unique name. There are three types of parameters depending on the values they take:

- Integer parameters. They take either simple integer values or values from an enumeration provided for readability and compatibility of the code. Set with *MSK_putintparam*.
- Double (floating point) parameters. Set with *MSK_putdoupparam*.
- String parameters. Set with *MSK_putstrparam*.

There are also parameter setting functions which operate fully on symbolic strings containing generic command-line style names of parameters and their values. See the example below. The optimizer will try to convert the given argument to the exact expected type, and will error if that fails.

If an incorrect value is provided then the parameter is left unchanged.

For example, the following piece of code sets up parameters which choose and tune the interior point optimizer before solving a problem.

Listing 7.3: Parameter setting example.

```
// Set log level (integer parameter)
res = MSK_putintparam(task, MSK_IPAR_LOG, 1);
// Select interior-point optimizer... (integer parameter)
res = MSK_putintparam(task, MSK_IPAR_OPTIMIZER, MSK_OPTIMIZER_INTPNT);
// ... without basis identification (integer parameter)
res = MSK_putintparam(task, MSK_IPAR_INTPNT_BASIS, MSK_BI_NEVER);
// Set relative gap tolerance (double parameter)
res = MSK_putdoupparam(task, MSK_DPAR_INTPNT_CO_TOL_REL_GAP, 1.0e-7);

// The same using explicit string names
res = MSK_putparam(task, "MSK_DPAR_INTPNT_CO_TOL_REL_GAP", "1.0e-7");
res = MSK_putnadoupparam(task, "MSK_DPAR_INTPNT_CO_TOL_REL_GAP", 1.0e-7);

// Incorrect value
res = MSK_putdoupparam(task, MSK_DPAR_INTPNT_CO_TOL_REL_GAP, -1.0);
if (res != MSK_RES_OK)
    printf("Wrong parameter value\n");
```

Reading parameter values

The functions *MSK_getintparam*, *MSK_getdoupparam*, *MSK_getstrparam* can be used to inspect the current value of a parameter, for example:

```
res = MSK_getdoupparam(task, MSK_DPAR_INTPNT_CO_TOL_REL_GAP, &param);
printf("Current value for parameter MSK_DPAR_INTPNT_CO_TOL_REL_GAP = %e\n", param);
```

7.5 Retrieving information items

After the optimization the user has access to the solution as well as to a report containing a large amount of additional *information items*. For example, one can obtain information about:

- **timing**: total optimization time, time spent in various optimizer subroutines, number of iterations, etc.
- **solution quality**: feasibility measures, solution norms, constraint and bound violations, etc.
- **problem structure**: counts of variables of different types, constraints, nonzeros, etc.
- **integer optimizer**: integrality gap, objective bound, number of cuts, etc.

and more. Information items are numerical values of integer, long integer or double type. The full list can be found in the API reference:

- *Double*
- *Integer*
- *Long*

Certain information items make sense, and are made available, also *during* the optimization process. They can be accessed from a callback function, see [Sec. 7.6](#) for details.

Remark

For efficiency reasons, not all information items are automatically computed after optimization. To force all information items to be updated use the parameter `MSK_IPAR_AUTO_UPDATE_SOL_INFO`.

Retrieving the values

Values of information items are fetched using one of the methods

- `MSK_getdouinf` for a double information item,
- `MSK_gettintinf` for an integer information item,
- `MSK_getlintinf` for a long integer information item.

Each information item is identified by a unique name. The example below reads two pieces of data from the solver: total optimization time and the number of interior-point iterations.

Listing 7.4: Information items example.

```
res = MSK_getdouinf(task, MSK_DINF_OPTIMIZER_TIME, &tm);
res = MSK_gettintinf(task, MSK_IINF_INTPNT_ITER, &iter);

printf("Time: %f\nIterations: %d\n", tm, iter);
```

7.6 Progress and data callback

Callbacks are a very useful mechanism that allow the caller to track the progress of the **MOSEK** optimizer. A callback function provided by the user is regularly called during the optimization and can be used to

- obtain a customized log of the solver execution,
- collect information for debugging purposes or
- ask the solver to terminate.

Warning

The callback functions *must not* invoke any functions of the solver, environment or task. Otherwise the state of the solver and its outcome are undefined. The only exception is the possibility to retrieve an integer solution, see below.

Retrieving mixed-integer solutions

If the mixed-integer optimizer is used, the callback will take place, in particular, every time an improved integer solution is found. In that case it is possible to retrieve the current values of the best integer solution from within the callback function. It can be useful for implementing complex termination criteria for integer optimization. The example in [Listing 7.5](#) shows how to do it by handling the callback code `MSK_CALLBACK_NEW_INT_MIO`.

7.6.1 Data callback

In the data callback **MOSEK** passes a callback code and values of all information items to a user-defined function. The callback function is called, in particular, at the beginning of each iteration of the interior-point optimizer. For the simplex optimizers `MSK_IPAR_LOG_SIM_FREQ` controls how frequently the call-back is called.

The callback is set by calling the function `MSK_putcallbackfunc` and providing a handle to a user-defined function `MSKcallbackfunc`.

Non-zero return value of the callback function indicates that the optimizer should be terminated.

7.6.2 Working example: Data callback

The following example defines a data callback function that prints out some of the information items. It interrupts the solver after a certain time limit.

Listing 7.5: An example of a data callback function.

```
static int MSKAPI usercallback(MSKtask_t      task,
                               MSKuserhandle_t handle,
                               MSKcallbackcode caller,
                               const MSKrealt * douinf,
                               const MSKint32t * intinf,
                               const MSKint64t * lintinf)
{
    cbdata_t data = (cbdata_t) handle;
    double maxtime = data->maxtime;
    MSKrescode r;

    switch (caller)
    {
    case MSK_CALLBACK_BEGIN_INTPNT:
        printf("Starting interior-point optimizer\n");
        break;
    case MSK_CALLBACK_INTPNT:
        printf("Iterations: %-3d Time: %6.2f(%.2f) ",
              intinf[MSK_IINF_INTPNT_ITER],
              douinf[MSK_DINF_OPTIMIZER_TIME],
              douinf[MSK_DINF_INTPNT_TIME]);

        printf("Primal obj.: %-18.6e Dual obj.: %-18.6e\n",
              douinf[MSK_DINF_INTPNT_PRIMAL_OBJ],
              douinf[MSK_DINF_INTPNT_DUAL_OBJ]);
        break;
    case MSK_CALLBACK_END_INTPNT:
        printf("Interior-point optimizer finished.\n");
        break;
    case MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX:
```

(continues on next page)

(continued from previous page)

```
    printf("Primal simplex optimizer started.\n");
    break;
case MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX:
    printf("Iterations: %-3d ",
           intinf[MSK_IINF_SIM_PRIMAL_ITER]);
    printf(" Elapsed time: %6.2f(%.2f)\n",
           douinf[MSK_DINF_OPTIMIZER_TIME],
           douinf[MSK_DINF_SIM_TIME]);
    printf("Obj.: %-.18.6e\n",
           douinf[MSK_DINF_SIM_OBJ]);
    break;
case MSK_CALLBACK_END_PRIMAL_SIMPLEX:
    printf("Primal simplex optimizer finished.\n");
    break;
case MSK_CALLBACK_BEGIN_DUAL_SIMPLEX:
    printf("Dual simplex optimizer started.\n");
    break;
case MSK_CALLBACK_UPDATE_DUAL_SIMPLEX:
    printf("Iterations: %-3d ", intinf[MSK_IINF_SIM_DUAL_ITER]);
    printf(" Elapsed time: %6.2f(%.2f)\n",
           douinf[MSK_DINF_OPTIMIZER_TIME],
           douinf[MSK_DINF_SIM_TIME]);
    printf("Obj.: %-.18.6e\n", douinf[MSK_DINF_SIM_OBJ]);
    break;
case MSK_CALLBACK_END_DUAL_SIMPLEX:
    printf("Dual simplex optimizer finished.\n");
    break;
case MSK_CALLBACK_NEW_INT_MIO:
    printf("New integer solution has been located.\n");

    r = MSK_getxx(task, MSK_SOL_ITG, data->xx);
    if (r == MSK_RES_OK) {
        int i;
        printf("xx = ");
        for (i = 0; i < data->numvars; i++) printf("%lf ", data->xx[i]);
        printf("\nObj.: %f\n", douinf[MSK_DINF_MIO_OBJ_INT]);
    }
    default:
        break;
}

if (douinf[MSK_DINF_OPTIMIZER_TIME] >= maxtime)
{
    /* mosek is spending too much time.
       Terminate it. */
    return (1);
}

return (0);
} /* usercallback */
```

Assuming that we have defined a task `task` and a time limit `maxtime`, the callback function is attached as follows:

Listing 7.6: Attaching the data callback function to the model.

```
data.maxtime = 0.05;
MSK_getnumvar(task, &data.numvars);
data.xx = MSK_callocenv(env, data.numvars, sizeof(double));

MSK_putcallbackfunc(task,
```

(continues on next page)

```

        usercallback,
        (void *) &data);

```

7.7 MOSEK OptServer

MOSEK provides an easy way to offload optimization problem to a remote server in both *synchronous* or *asynchronous* mode. This section describes related functionalities from the client side, i.e. sending optimization tasks to the remote server and retrieving solutions.

Setting up and configuring the remote server is described in a separate manual for the OptServer.

7.7.1 Synchronous Remote Optimization

In synchronous mode the client sends an optimization problem to the server and blocks, waiting for the optimization to end. Once the result has been received, the program can continue. This is the simplest mode and requires very few modifications to existing code: instead of *MSK_optimize* the user must invoke *MSK_optimizermt* with the host and port where the server is running and listening as additional arguments. The rest of the code remains untouched.

Note that it is impossible to recover the job in case of a broken connection.

Source code example

Listing 7.7: Using the OptServer in synchronous mode.

```

#include "mosek.h"

static void MSKAPI printstr(void *handle, const char str[])
{
    printf("%s", str);
}

int main(int argc, const char * argv[])
{
    MSKenv_t    env = NULL;
    MSKtask_t   task = NULL;
    MSKrescodee res = MSK_RES_OK;
    MSKrescodee trm = MSK_RES_OK;

    if (argc <= 3)
    {
        printf("Missing argument, syntax is:\n");
        printf("  opt_server_sync inputfile host port\n");
    }
    else
    {
        // Create the mosek environment.
        // The `NULL' arguments here, are used to specify customized
        // memory allocators and a memory debug file. These can
        // safely be ignored for now.
        res = MSK_makeenv(&env, NULL);

        // Create a task object linked with the environment env.
        // We create it with 0 variables and 0 constraints initially,
        // since we do not know the size of the problem.
        if (res == MSK_RES_OK)
            res = MSK_maketask(env, 0, 0, &task);

        // Direct the task log stream to a user specified function

```

(continues on next page)

(continued from previous page)

```
if (res == MSK_RES_OK)
    res = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

// We assume that a problem file was given as the first command
// line argument (received in `argv')
if (res == MSK_RES_OK)
    res = MSK_readdata(task, argv[1]);

// Solve the problem remotely
if (res == MSK_RES_OK)
    res = MSK_optimizermt(task, argv[2], argv[3], &trm);

// Print a summary of the solution.
if (res == MSK_RES_OK)
    res = MSK_solutionsummary(task, MSK_STREAM_LOG);

// If an output file was specified, write a solution
if (res == MSK_RES_OK && argc >= 3)
{
    // We define the output format to be OPF, and tell MOSEK to
    // leave out parameters and problem data from the output file.
    MSK_putintparam(task, MSK_IPAR_OPF_WRITE_SOLUTIONS, MSK_ON);
    MSK_putintparam(task, MSK_IPAR_OPF_WRITE_HINTS, MSK_OFF);
    MSK_putintparam(task, MSK_IPAR_OPF_WRITE_PARAMETERS, MSK_OFF);
    MSK_putintparam(task, MSK_IPAR_OPF_WRITE_PROBLEM, MSK_OFF);

    res = MSK_writedata(task, argv[2]);
}

// Delete task and environment
MSK_deletetask(&task);
MSK_deleteenv(&env);
}
return res;
}
```

7.7.2 Asynchronous Remote Optimization

In asynchronous mode the client sends a job to the remote server and the execution of the client code continues. In particular, it is the client's responsibility to periodically check the optimization status and, when ready, fetch the results. The client can also interrupt optimization. The most relevant methods are:

- *MSK_asyncoptimize* : Offload the optimization task to a solver server.
- *MSK_asyncpoll* : Request information about the status of the remote job.
- *MSK_asyncgetresult* : Request the results from a completed remote job.
- *MSK_asyncstop* : Terminate a remote job.

Source code example

In the example below the program enters in a polling loop that regularly checks whether the result of the optimization is available.

Listing 7.8: Using the OptServer in asynchronous mode.

```
#include "mosek.h"
#ifdef _WIN32
#include "windows.h"
```

(continues on next page)

```

# else
#include "unistd.h"
#endif

static void MSKAPI printstr(void *handle, const char str[])
{
    printf("%s", str);
}

int main(int argc, char * argv[])
{
    char token[33];

    int      numpolls = 10;
    int      i = 0;

    MSKboolean_t respavailable;

    MSKenv_t   env   = NULL;
    MSKtask_t  task  = NULL;

    MSKrescodee res   = MSK_RES_OK;
    MSKrescodee trm;
    MSKrescodee resp;

    const char * filename = "../data/25fv47.mps";
    const char * host      = "karise";
    const char * port      = "30080";

    if (argc < 5)
    {
        fprintf(stderr, "Syntax: opt_server_async filename host port numpolls\n");
        return 0;
    }

    if (argc > 1) filename = argv[1];
    if (argc > 2) host      = argv[2];
    if (argc > 3) port      = argv[3];
    if (argc > 4) numpolls = atoi(argv[4]);

    res = MSK_makeenv(&env, NULL);

    if (res == MSK_RES_OK)
        res = MSK_maketask(env, 0, 0, &task);
    if (res == MSK_RES_OK)
        res = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

    if (res == MSK_RES_OK)
        res = MSK_readdata(task, filename);

    res = MSK_asyncoptimize(task,
                             host,
                             port,
                             token);
    MSK_deletetask(&task);
    printf("token = %s\n", token);

    if (res == MSK_RES_OK)
        res = MSK_maketask(env, 0, 0, &task);

```

```

if (res == MSK_RES_OK)
    res = MSK_readdata(task, filename);

if (res == MSK_RES_OK)
    res = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

for (i = 0; i < numpolls && res == MSK_RES_OK ; i++)
{
    #if __linux__
        sleep(1);
    #elif defined(_WIN32)
        Sleep(1000);
    #endif

    printf("poll %d\n ", i);

    res = MSK_asyncpoll(task,
                        host,
                        port,
                        token,
                        &respavailable,
                        &resp,
                        &trm);

    puts("polling done");

    if (respavailable)
    {
        puts("solution available!");

        res = MSK_asyncgetresult(task,
                                host,
                                port,
                                token,
                                &respavailable,
                                &resp,
                                &trm);

        MSK_solutionsummary(task, MSK_STREAM_LOG);
        break;
    }
}

if (i == numpolls)
{
    printf("max num polls reached, stopping %s", host);
    MSK_asyncstop(task, host, port, token);
}

MSK_deletetask(&task);
MSK_deleteenv(&env);

printf("%s:%d: Result = %d\n", __FILE__, __LINE__, res); fflush(stdout);

return res;
}

```

Chapter 8

Debugging Tutorials

This collection of tutorials contains basic techniques for debugging optimization problems using tools available in **MOSEK**: optimizer log, solution summary, infeasibility report, command-line tools. It is intended as a first line of technical help for issues such as: Why do I get solution status *unknown* and how can I fix it? Why is my model infeasible while it shouldn't be? Should I change some parameters? Can the model solve faster? etc.

The major steps when debugging a model are always:

- Enable log output. See [Sec. 7.3.1](#) for how to do it. In the simplest case:

Create a log handler function:

```
static void MSKAPI printstr(void      *handle,
                             const char *str)
{
    printf("%s", str);
    fflush(stdout);
}
```

attach it to the log stream:

```
MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);
```

and include solution summary after the call to `optimize`:

```
res = MSK_optimize(task);
MSK_solutionsummary(task, MSK_STREAM_LOG);
```

- Run the optimization and analyze the log output, see [Sec. 8.1](#). In particular:
 - check if the problem setup (number of constraints/variables etc.) matches your expectation.
 - check solution summary and solution status.
- Dump the problem to disk if necessary to continue analysis. See [Sec. 7.3.3](#).
 - use a human-readable text format, such as `*.opf` if you want to check the problem structure by hand. Assign names to variables and constraints to make them easier to identify.

```
MSK_writedata(task, "data.opf");
```

- use the **MOSEK** native format `*.task.gz` when submitting a bug report or support question.

```
MSK_writedata(task, "data.task.gz");
```

- Fix problem setup, improve the model, locate infeasibility or adjust parameters, depending on the diagnosis.

See the following sections for details.

8.1 Understanding optimizer log

The optimizer produces a log which splits roughly into four sections:

1. summary of the input data,
2. presolve and other pre-optimize problem setup stages,
3. actual optimizer iterations,
4. solution summary.

In this tutorial we show how to analyze the most important parts of the log when initially debugging a model: input data (1) and solution summary (4). For the iterations log (3) see [Sec. 13.3.4](#) or [Sec. 13.4.8](#).

8.1.1 Input data

If **MOSEK** behaves very far from expectations it may be due to errors in problem setup. The log file will begin with a summary of the structure of the problem, which looks for instance like:

```
Problem
  Name           :
  Objective sense : max
  Type           : CONIC (conic optimization problem)
  Constraints     : 20413
  Cones          : 2508
  Scalar variables : 20414
  Matrix variables : 0
  Integer variables : 0
```

This can be consulted to eliminate simple errors: wrong objective sense, wrong number of variables etc. Note that Fusion, and third-party modeling tools can introduce additional variables and constraints to the model. In the remaining **MOSEK** APIs the problem dimensions should match exactly what the user specified.

If this is not sufficient a bit more information can be obtained by dumping the problem to a file (see [Sec. 8](#)) and using the `anapro` option of any of the command line tools. It can also be done directly with the function `MSK_analyzeproblem`. This will produce a longer summary similar to:

```
** Variables
scalar: 20414      integer: 0      matrix: 0
low: 2082         up: 5014        ranged: 0      free: 12892    fixed: 426

** Constraints
all: 20413
low: 10028        up: 0          ranged: 0      free: 0        fixed: 10385

** Cones
QUAD: 1           dims: 2865: 1
RQUAD: 2507       dims: 3: 2507

** Problem data (numerics)
|c|              nnz: 10028      min=2.09e-05   max=1.00e+00
|A|              nnz: 597023     min=1.17e-10   max=1.00e+00
blx              fin: 2508       min=-3.60e+09   max=2.75e+05
bux              fin: 5440       min=0.00e+00   max=2.94e+08
blc              fin: 20413     min=-7.61e+05   max=7.61e+05
buc              fin: 10385     min=-5.00e-01   max=0.00e+00
```

Again, this can be used to detect simple errors, such as:

- Wrong type of cone was used or it has wrong dimension.
- The bounds for variables or constraints are incorrect or incomplete. Check if you defined bound keys for all variables. A variable for which no bound was defined is by default fixed at 0.

- The model is otherwise incomplete.
- Suspicious values of coefficients.
- For various data sizes the model does not scale as expected.

Finally saving the problem in a human-friendly text format such as LP or OPF (see [Sec. 8](#)) and analyzing it by hand can reveal if the model is correct.

Warnings and errors

At this stage the user can encounter warnings which should not be ignored, unless they are well-understood. They can also serve as hints as to numerical issues with the problem data. A typical warning of this kind is

```
MOSEK warning 53: A numerically large upper bound value 2.9e+08 is specified for variable
↪ 'absh[107]' (2613).
```

Warnings do not stop the problem setup. If, on the other hand, an error occurs then the model will become invalid. The user should make sure to test for errors/exceptions from all API calls that set up the problem and validate the data. See [Sec. 7.2](#) for more details.

8.1.2 Solution summary

The last item in the log is the solution summary. In the Optimizer API it is only printed by invoking the function `MSK_solutionsummary`.

Continuous problem

Optimal solution

A typical solution summary for a continuous (linear, conic, quadratic) problem looks like:

```
Problem status : PRIMAL_AND_DUAL_FEASIBLE
Solution status : OPTIMAL
Primal.  obj: 8.7560516107e+01    nrm: 1e+02    Viol.  con: 3e-12    var: 0e+00    cones: 3e-11
Dual.    obj: 8.7560521345e+01    nrm: 1e+00    Viol.  con: 5e-09    var: 9e-11    cones: 0e+00
```

It contains the following elements:

- Problem and solution status. For details see [Sec. 7.1.3](#).
- A summary of the primal solution: objective value, infinity norm of the solution vector \mathbf{x} , maximal violations of constraints, variable bounds and cones. The violation of a linear constraint such as $a^T x \leq b$ is $\max(a^T x - b, 0)$. The violation of a conic constraint $x \in \mathcal{K}$ is the distance $\text{dist}(x, \mathcal{K})$.
- The same for the dual solution.

The features of the solution summary which characterize a very good and accurate solution and a well-posed model are:

- **Status:** The solution status is `OPTIMAL`.
- **Duality gap:** The primal and dual objective values are (almost) identical, which proves the solution is (almost) optimal.
- **Norms:** Ideally the norms of the solution and the objective values should not be too large. This of course depends on the input data, but a huge solution norm can be an indicator of issues with the scaling, conditioning and/or well-posedness of the model. It may also indicate that the problem is borderline between feasibility and infeasibility and sensitive to small perturbations in this respect.
- **Violations:** The violations are close to zero, which proves the solution is (almost) feasible. Observe that due to rounding errors it can be expected that the violations are proportional to the norm (`nrm:`) of the solution. It is rarely the case that violations are exactly zero.

Solution status UNKNOWN

A typical example with solution status UNKNOWN due to numerical problems will look like:

Problem status : UNKNOWN						
Solution status : UNKNOWN						
Primal.	obj:	1.3821656824e+01	nrm:	1e+01	Viol.	con: 2e-03 var: 0e+00 cones: 0e+00
Dual.	obj:	3.0119004098e-01	nrm:	5e+07	Viol.	con: 4e-16 var: 1e-01 cones: 0e+00

Note that:

- The primal and dual objective are very different.
- The dual solution has very large norm.
- There are considerable violations so the solution is likely far from feasible.

Follow the hints in [Sec. 8.2](#) to resolve the issue.

Solution status UNKNOWN with a potentially useful solution

Solution status UNKNOWN does not necessarily mean that the solution is completely useless. It only means that the solver was unable to make any more progress due to numerical difficulties, and it was not able to reach the accuracy required by the termination criteria (see [Sec. 13.3.2](#)). Consider for instance:

Problem status : UNKNOWN						
Solution status : UNKNOWN						
Primal.	obj:	3.4531019648e+04	nrm:	1e+05	Viol.	con: 7e-02 var: 0e+00 cones: 0e+00
Dual.	obj:	3.4529720645e+04	nrm:	8e+03	Viol.	con: 1e-04 var: 2e-04 cones: 0e+00

Such a solution may still be useful, and it is always up to the user to decide. It may be a good enough approximation of the optimal point. For example, the large constraint violation may be due to the fact that one constraint contained a huge coefficient.

Infeasibility certificate

A primal infeasibility certificate is stored in the dual variables:

Problem status : PRIMAL_INFEASIBLE						
Solution status : PRIMAL_INFEASIBLE_CER						
Dual.	obj:	2.9238975853e+02	nrm:	6e+02	Viol.	con: 0e+00 var: 1e-11 cones: 0e+00

It is a Farkas-type certificate as described in [Sec. 12.2.2](#). In particular, for a good certificate:

- The dual objective is positive for a minimization problem, negative for a maximization problem. Ideally it is well bounded away from zero.
- The norm is not too big and the violations are small (as for a solution).

If the model was not expected to be infeasible, the likely cause is an error in the problem formulation. Use the hints in [Sec. 8.1.1](#) and [Sec. 8.3](#) to locate the issue.

Just like a solution, the infeasibility certificate can be of better or worse quality. The infeasibility certificate above is very solid. However, there can be less clear-cut cases, such as for example:

Problem status : PRIMAL_INFEASIBLE						
Solution status : PRIMAL_INFEASIBLE_CER						
Dual.	obj:	1.6378689238e-06	nrm:	6e+05	Viol.	con: 7e-03 var: 2e-04 cones: 0e+00

This infeasibility certificate is more dubious because the dual objective is positive, but barely so in comparison with the large violations. It also has rather large norm. This is more likely an indication that the problem is borderline between feasibility and infeasibility or simply ill-posed and sensitive to tiny variations in input data. See [Sec. 8.3](#) and [Sec. 8.2](#).

The same remarks apply to dual infeasibility (i.e. unboundedness) certificates. Here the primal objective should be negative a minimization problem and positive for a maximization problem.

8.1.3 Mixed-integer problem

Optimal integer solution

For a mixed-integer problem there is no dual solution and a typical optimal solution report will look as follows:

Problem status : PRIMAL_FEASIBLE						
Solution status : INTEGER_OPTIMAL						
Primal.	obj:	6.0111122960e+06	nrm:	1e+03	Viol.	con: 2e-13 var: 2e-14 itg: 5e-15

The interpretation of all elements is as for a continuous problem. The additional field `itg` denotes the maximum violation of an integer variable from being an exact integer.

Feasible integer solution

If the solver found an integer solution but did not prove optimality, for instance because of a time limit, the solution status will be `PRIMAL_FEASIBLE`:

Problem status : PRIMAL_FEASIBLE						
Solution status : PRIMAL_FEASIBLE						
Primal.	obj:	6.0114607792e+06	nrm:	1e+03	Viol.	con: 2e-13 var: 2e-13 itg: 4e-15

In this case it is valuable to go back to the optimizer summary to see how good the best solution is:

31	35	1	0	6.0114607792e+06	6.0078960892e+06	0.06	4.1
Objective of best integer solution : 6.011460779193e+06							
Best objective bound : 6.007896089225e+06							

In this case the best integer solution found has objective value `6.011460779193e+06`, the best proved lower bound is `6.007896089225e+06` and so the solution is guaranteed to be within 0.06% from optimum. The same data can be obtained as information items through an API. See also [Sec. 13.4](#) for more details.

Infeasible problem

If the problem is declared infeasible the summary is simply

Problem status : PRIMAL_INFEASIBLE						
Solution status : UNKNOWN						
Primal.	obj:	0.0000000000e+00	nrm:	0e+00	Viol.	con: 0e+00 var: 0e+00 itg: 0e+00

If infeasibility was not expected, consult [Sec. 8.3](#).

8.2 Addressing numerical issues

The suggestions in this section should help diagnose and solve issues with numerical instability, in particular `UNKNOWN` solution status or solutions with large violations. Since numerically stable models tend to solve faster, following these hints can also dramatically shorten solution times.

We always recommend that issues of this kind are addressed by reformulating or rescaling the model, since it is the modeler who has the best insight into the structure of the problem and can fix the cause of the issue.

8.2.1 Formulating problems

Scaling

Make sure that all the data in the problem are of comparable orders of magnitude. This applies especially to the linear constraint matrix. Use [Sec. 8.1.1](#) if necessary. For example a report such as

A	nnz: 597023	min=1.17e-6	max=2.21e+5
---	-------------	-------------	-------------

means that the ratio of largest to smallest elements in **A** is 10^{11} . In this case the user should rescale or reformulate the model to avoid such spread which makes it difficult for **MOSEK** to scale the problem internally. In many cases it may be possible to change the units, i.e. express the model in terms of rescaled variables (for instance work with millions of dollars instead of dollars, etc.).

Similarly, if the objective contains very different coefficients, say

$$\text{maximize } 10^{10}x + y$$

then it is likely to lead to inaccuracies. The objective will be dominated by the contribution from x and y will become insignificant.

Removing huge bounds

Never use a very large number as replacement for ∞ . Instead define the variable or constraint as unbounded from below/above. Similarly, avoid artificial huge bounds if you expect they will not become tight in the optimal solution.

Avoiding linear dependencies

As much as possible try to avoid linear dependencies and near-linear dependencies in the model. See [Example 8.3](#).

Avoiding ill-posedness

Avoid continuous models which are ill-posed: the solution space is degenerate, for example consists of a single point (technically, the Slater condition is not satisfied). In general, this refers to problems which are borderline between feasible and infeasible. See [Example 8.1](#).

Scaling the expected solution

Try to formulate the problem in such a way that the expected solution (both primal and dual) is not very large. Consult the solution summary [Sec. 8.1.2](#) to check the objective values or solution norms.

8.2.2 Further suggestions

Here are other simple suggestions that can help locate the cause of the issues. They can also be used as hints for how to tune the optimizer if fixing the root causes of the issue is not possible.

- Remove the objective and solve the feasibility problem. This can reveal issues with the objective.
- Change the objective or change the objective sense from minimization to maximization (if applicable). If the two objective values are almost identical, this may indicate that the feasible set is very small, possibly degenerate.
- Perturb the data, for instance bounds, very slightly, and compare the results.
- For linear problems: solve the problem using a different optimizer by setting the parameter `MSK_IPAR_OPTIMIZER` and compare the results.
- Force the optimizer to solve the primal/dual versions of the problem by setting the parameter `MSK_IPAR_INTPNT_SOLVE_FORM` or `MSK_IPAR_SIM_SOLVE_FORM`. **MOSEK** has a heuristic to decide whether to dualize, but for some problems the guess is wrong an explicit choice may give better results.
- Solve the problem without presolve or some of its parts by setting the parameter `MSK_IPAR_PRESOLVE_USE`, see [Sec. 13.1](#).
- Use different numbers of threads (`MSK_IPAR_NUM_THREADS`) and compare the results. Very different results indicate numerical issues resulting from round-off errors.

If the problem was dumped to a file, experimenting with various parameters is facilitated with the **MOSEK** Command Line Tool or **MOSEK** Python Console [Sec. 8.4](#).

8.2.3 Typical pitfalls

Example 8.1 (Ill-posedness). A toy example of this situation is the feasibility problem

$$(x - 1)^2 \leq 1, (x + 1)^2 \leq 1$$

whose only solution is $x = 0$ and moreover replacing any 1 on the right hand side by $1 - \varepsilon$ makes the problem infeasible and replacing it by $1 + \varepsilon$ yields a problem whose solution set is an interval (fully-dimensional). This is an example of ill-posedness.

Example 8.2 (Huge solution). If the norm of the expected solution is very large it may lead to numerical issues or infeasibility. For example the problem

$$(10^{-4}, x, 10^3) \in \mathcal{Q}_r^3$$

may be declared infeasible because the expected solution must satisfy $x \geq 5 \cdot 10^9$.

Example 8.3 (Near linear dependency). Consider the following problem:

$$\begin{array}{llllll} \text{minimize} & & & & & \\ \text{subject to} & x_1 & + & x_2 & & = 1, \\ & & & & x_3 & + & x_4 & = 1, \\ & - & x_1 & & - & x_3 & & = -1 + \varepsilon, \\ & & - & x_2 & & - & x_4 & = -1, \\ & x_1, & & x_2, & x_3, & & x_4 & \geq 0. \end{array}$$

If we add the equalities together we obtain:

$$0 = \varepsilon$$

which is infeasible for any $\varepsilon \neq 0$. Here infeasibility is caused by a linear dependency in the constraint matrix coupled with a precision error represented by the ε . Indeed if a problem contains linear dependencies then the problem is either infeasible or contains redundant constraints. In the above case any of the equality constraints can be removed while not changing the set of feasible solutions. To summarize linear dependencies in the constraints can give rise to infeasible problems and therefore it is better to avoid them.

Example 8.4 (Presolving very tight bounds). Next consider the problem

$$\begin{array}{llll} \text{minimize} & & & \\ \text{subject to} & x_1 - 0.01x_2 & = & 0, \\ & x_2 - 0.01x_3 & = & 0, \\ & x_3 - 0.01x_4 & = & 0, \\ & x_1 & \geq & -10^{-9}, \\ & x_1 & \leq & 10^{-9}, \\ & x_4 & \geq & 10^{-4}. \end{array}$$

Now the **MOSEK** presolve will, for the sake of efficiency, fix variables (and constraints) that have tight bounds where tightness is controlled by the parameter `MSK_DPAR_PREOLVE_TOL_X`. Since the bounds

$$-10^{-9} \leq x_1 \leq 10^{-9}$$

are tight, presolve will set $x_1 = 0$. It easy to see that this implies $x_4 = 0$, which leads to the incorrect conclusion that the problem is infeasible. However a tiny change of the value 10^{-9} makes the problem

feasible. In general it is recommended to avoid ill-posed problems, but if that is not possible then one solution is to reduce parameters such as `MSK_DPAR_PRESOLVE_TOL_X` to say 10^{-10} . This will at least make sure that presolve does not make the undesired reduction.

8.3 Debugging infeasibility

This section contains hints for debugging problems that are unexpectedly infeasible. It is always a good idea to remove the objective, i.e. only solve a feasibility problem when debugging such issues.

8.3.1 Numerical issues

Infeasible problem status may be just an artifact of numerical issues appearing when the problem is badly-scaled, barely feasible or otherwise ill-conditioned so that it is unstable under small perturbations of the data or round-off errors. This may be visible in the solution summary if the infeasibility certificate has poor quality. See [Sec. 8.1.2](#) for how to diagnose that and [Sec. 8.2](#) for possible hints. [Sec. 8.2.3](#) contains examples of situations which may lead to infeasibility for numerical reasons.

We refer to [Sec. 8.2](#) for further information on dealing with those sort of issues. For the rest of this section we concentrate on the case when the solution summary leaves little doubt that the problem solved by the optimizer actually is infeasible.

8.3.2 Locating primal infeasibility

As an example of a primal infeasible problem consider minimizing the cost of transportation between a number of production plants and stores: Each plant produces a fixed number of goods, and each store has a fixed demand that must be met. Supply, demand and cost of transportation per unit are given in [Fig. 8.1](#).




Fig. 8.1: Supply, demand and cost of transportation.

The problem represented in [Fig. 8.1](#) is infeasible, since the total demand

$$2300 = 1100 + 200 + 500 + 500$$

exceeds the total supply

$$2200 = 200 + 1000 + 1000$$

If we denote the number of transported goods from plant i to store j by x_{ij} , the problem can be

formulated as the LP:

$$\begin{aligned}
& \text{minimize} && x_{11} + 2x_{12} + 5x_{23} + 2x_{24} + x_{31} + 2x_{33} + x_{34} \\
& \text{subject to} && s_0 : x_{11} + x_{12} \leq 200, \\
& && s_1 : x_{23} + x_{24} \leq 1000, \\
& && s_2 : x_{31} + x_{33} + x_{34} \leq 1000, \\
& && d_1 : x_{11} + x_{31} = 1100, \\
& && d_2 : x_{12} = 200, \\
& && d_3 : x_{23} + x_{33} = 500, \\
& && d_4 : x_{24} + x_{34} = 500, \\
& && x_{ij} \geq 0.
\end{aligned} \tag{8.1}$$

Solving problem (8.1) using **MOSEK** will result in an infeasibility status. The infeasibility certificate is contained in the dual variables and can be accessed from an API. The variables and constraints with nonzero solution values form an infeasible subproblem, which frequently is very small. See [Sec. 12.1.2](#) or [Sec. 12.2.2](#) for detailed specifications of infeasibility certificates.

A short infeasibility report can also be printed to the log stream. It can be turned on by setting the parameter `MSK_IPAR_INFEAS_REPORT_AUTO` to `MSK_ON`. This causes **MOSEK** to print a report on variables and constraints which are involved in infeasibility in the above sense, i.e. have nonzero values in the certificate. The parameter `MSK_IPAR_INFEAS_REPORT_LEVEL` controls the amount of information presented in the infeasibility report. The default value is 1. For the above example the report is

MOSEK PRIMAL INFEASIBILITY REPORT.

Problem status: The problem is primal infeasible

The following constraints are involved in the primal infeasibility.

Index	Name	Lower bound	Upper bound	Dual lower	Dual upper
0	s0	NONE	2.000000e+002	0.000000e+000	1.000000e+000
2	s2	NONE	1.000000e+003	0.000000e+000	1.000000e+000
3	d1	1.100000e+003	1.100000e+003	1.000000e+000	0.000000e+000
4	d2	2.000000e+002	2.000000e+002	1.000000e+000	0.000000e+000

The following bound constraints are involved in the infeasibility.

Index	Name	Lower bound	Upper bound	Dual lower	Dual upper
8	x33	0.000000e+000	NONE	1.000000e+000	0.000000e+000
10	x34	0.000000e+000	NONE	1.000000e+000	0.000000e+000

The infeasibility report is divided into two sections corresponding to constraints and variables. It is a selection of those lines from the problem solution which are important in understanding primal infeasibility. In this case the constraints s0, s2, d1, d2 and variables x33, x34 are of importance because of nonzero dual values. The columns **Dual lower** and **Dual upper** contain the values of dual variables s_l^c , s_u^c , s_l^x and s_u^x in the primal infeasibility certificate (see [Sec. 12.1.2](#)).

In our example the certificate means that an appropriate linear combination of constraints s0, s1 with coefficient $s_u^c = 1$, constraints d1 and d2 with coefficient $s_u^c - s_l^c = 0 - 1 = -1$ and lower bounds on x33 and x34 with coefficient $-s_l^x = -1$ gives a contradiction. Indeed, the combination of the four involved constraints is $x_{33} + x_{34} \leq -100$ (as indicated in the introduction, the difference between supply and demand).

It is also possible to extract the infeasible subproblem with the command-line tool. For an infeasible problem called `infeas.lp` the command:

```
mosek -d MSK_IPAR_INFEAS_REPORT_AUTO MSK_ON infeas.lp -info rinfeas.lp
```

will produce the file `rinfeas.bas.inf.lp` which contains the infeasible subproblem. Because of its size it may be easier to work with than the original problem file.

Returning to the transportation example, we discover that removing the fifth constraint $x_{12} = 200$ makes the problem feasible. Almost all undesired infeasibilities should be fixable at the modeling stage.

8.3.3 Locating dual infeasibility

A problem may also be *dual infeasible*. In this case the primal problem is usually unbounded, meaning that feasible solutions exists such that the objective tends towards infinity. For example, consider the problem

$$\begin{aligned} & \text{maximize} && 200y_1 + 1000y_2 + 1000y_3 + 1100y_4 + 200y_5 + 500y_6 + 500y_7 \\ & \text{subject to} && y_1 + y_4 \leq 1, \quad y_1 + y_5 \leq 2, \quad y_2 + y_6 \leq 5, \quad y_2 + y_7 \leq 2, \\ & && y_3 + y_4 \leq 1, \quad y_3 + y_6 \leq 2, \quad y_3 + y_7 \leq 1 \\ & && y_1, y_2, y_3 \leq 0 \end{aligned}$$

which is dual to (8.1) (and therefore is dual infeasible). The dual infeasibility report may look as follows:

MOSEK DUAL INFEASIBILITY REPORT.					
Problem status: The problem is dual infeasible					
The following constraints are involved in the infeasibility.					
Index	Name	Activity	Objective	Lower bound	Upper bound
5	x33	-1.000000e+00		NONE	2.000000e+00
6	x34	-1.000000e+00		NONE	1.000000e+00
The following variables are involved in the infeasibility.					
Index	Name	Activity	Objective	Lower bound	Upper bound
0	y1	-1.000000e+00	2.000000e+02	NONE	0.000000e+00
2	y3	-1.000000e+00	1.000000e+03	NONE	0.000000e+00
3	y4	1.000000e+00	1.100000e+03	NONE	NONE
4	y5	1.000000e+00	2.000000e+02	NONE	NONE
Interior-point solution summary					
Problem status : DUAL_INFEASIBLE					
Solution status : DUAL_INFEASIBLE_CER					
Primal. obj: 1.0000000000e+02 nrm: 1e+00 Viol. con: 0e+00 var: 0e+00					

In the report we see that the variables y_1 , y_3 , y_4 , y_5 and two constraints contribute to infeasibility with non-zero values in the Activity column. Therefore

$$(y_1, \dots, y_7) = (-1, 0, -1, 1, 1, 0, 0)$$

is the dual infeasibility certificate as in Sec. 12.1.2. This just means, that along the ray

$$(0, 0, 0, 0, 0, 0, 0) + t(y_1, \dots, y_7) = (-t, 0, -t, t, t, 0, 0), \quad t > 0,$$

which belongs to the feasible set, the objective value $100t$ can be arbitrarily large, i.e. the problem is unbounded.

In the example problem we could

- Add a lower bound on y_3 . This will directly invalidate the certificate of dual infeasibility.
- Increase the objective coefficient of y_3 . Changing the coefficients sufficiently will invalidate the inequality $c^T y^* > 0$ and thus the certificate.

8.3.4 Suggestions

Primal infeasibility

When trying to understand what causes the unexpected primal infeasible status use the following hints:

- Remove the objective function. This does not change the infeasibility status but simplifies the problem, eliminating any possibility of issues related to the objective function.

- Remove cones, semidefinite variables and integer constraints. Solve only the linear part of the problem. Typical simple modeling errors will lead to infeasibility already at this stage.
- Consider whether your problem has some obvious necessary conditions for feasibility and examine if these are satisfied, e.g. total supply should be greater than or equal to total demand.
- Verify that coefficients and bounds are reasonably sized in your problem.
- See if there are any obvious contradictions, for instance a variable is bounded both in the variables and constraints section, and the bounds are contradictory.
- Consider replacing suspicious equality constraints by inequalities. For instance, instead of $x_{12} = 200$ see what happens for $x_{12} \geq 200$ or $x_{12} \leq 200$.
- Relax bounds of the suspicious constraints or variables.
- For integer problems, remove integrality constraints on some/all variables and see if the problem solves.
- Remember that variables without explicitly initialized bounds are fixed at zero.
- Form an **elastic model**: allow to violate constraints at a cost. Introduce slack variables and add them to the objective as penalty. For instance, suppose we have a constraint

$$\begin{array}{ll}\text{minimize} & c^T x, \\ \text{subject to} & a^T x \leq b.\end{array}$$

which might be causing infeasibility. Then create a new variable y and form the problem which contains:

$$\begin{array}{ll}\text{minimize} & c^T x + y, \\ \text{subject to} & a^T x \leq b + y.\end{array}$$

Solving this problem will reveal by how much the constraint needs to be relaxed in order to become feasible. This is equivalent to inspecting the infeasibility certificate but may be more intuitive.

- If you think you have a feasible solution or its part, fix all or some of the variables to those values. Presolve will propagate them through the model and potentially reveal more localized sources of infeasibility.
- Dump the problem in OPF or LP format and verify that the problem that was passed to the optimizer corresponds to the problem expressed in the high-level modeling language, if any such was used.

Dual infeasibility

When trying to understand what causes the unexpected dual infeasible status use the following hints:

- Verify that the objective coefficients are reasonably sized.
- Check if no bounds and constraints are missing, for example if all variables that should be nonnegative have been declared as such etc.
- Strengthen bounds of the suspicious constraints or variables.
- Remember that constraints without explicitly initialized bounds are free (no bound).
- Form an series of models with decreasing bounds on the objective, that is, instead of objective

$$\text{minimize } c^T x$$

solve the problem with an additional constraint such as

$$c^T x = -10^5$$

and inspect the solution to figure out the mechanism behind arbitrarily decreasing objective values. This is equivalent to inspecting the infeasibility certificate but may be more intuitive.

- Dump the problem in OPF or LP format and verify that the problem that was passed to the optimizer corresponds to the problem expressed in the high-level modeling language, if any such was used.

Please note that modifying the problem to invalidate the reported certificate does *not* imply that the problem becomes feasible — the reason for infeasibility may simply *move*, resulting a problem that is still infeasible, but for a different reason. More often, the reported certificate can be used to give a hint about errors or inconsistencies in the model that produced the problem.

8.4 Python Console

The **MOSEK** Python Console is an alternative to the **MOSEK** Command Line Tool. It can be used for interactive loading, solving and debugging optimization problems stored in files, for example **MOSEK** task files. It facilitates debugging techniques described in [Sec. 8](#).

8.4.1 Usage

The tool requires Python 2 or 3. The **MOSEK** interface for Python must be installed following the installation instructions for Python API or Python Fusion API. In the basic case it should be sufficient to execute the script

```
python setup.py install --user
```

in the directory containing the **MOSEK** Python module.

The Python Console is contained in the file `mosekconsole.py` in the folder with **MOSEK** binaries. It can be copied to an arbitrary location. The file is also available for [download here](#) (`mosekconsole.py`).

To run the console in interactive mode use

```
python mosekconsole.py
```

To run the console in batch mode provide a semicolon-separated list of commands as the second argument of the script, for example:

```
python mosekconsole.py "read data.task.gz; solve form=dual; writesol data"
```

The script is written using the **MOSEK** Python API and can be extended by the user if more specific functionality is required. We refer to the documentation of the Python API.

8.4.2 Examples

To read a problem from `data.task.gz`, solve it, and write solutions to `data.sol`, `data.bas` or `data.itg`:

```
read data.task.gz; solve; writesol data
```

To convert between file formats:

```
read data.task.gz; write data.mps
```

To set a parameter before solving:

```
read data.task.gz; param INTPNT_CO_TOL_DFEAS 1e-9; solve"
```

To list parameter values related to the mixed-integer optimizer in the task file:

```
read data.task.gz; param MIO
```

To print a summary of problem structure:

```
read data.task.gz; anapro
```

To solve a problem forcing the dual and switching off presolve:

```
read data.task.gz; solve form=dual presolve=no
```

To write an infeasible subproblem to a file for debugging purposes:

```
read data.task.gz; solve; infsub; write inf.opf
```

8.4.3 Full list of commands

Below is a brief description of all the available commands. Detailed information about a specific command `cmd` and its options can be obtained with

```
help cmd
```

Table 8.1: List of commands of the MOSEK Python Console.
:header: “Command”, “Description” :widths: 20,80

<code>help [command]</code>	Print list of commands or info about a specific command
<code>log filename</code>	Save the session to a file
<code>intro</code>	Print MOSEK splashscreen
<code>testlic</code>	Test the license system
<code>read filename</code>	Load problem from file
<code>reread</code>	Reload last problem file
<code>solve [options]</code>	Solve current problem
<code>write filename</code>	Write current problem to file
<code>param [name [value]]</code>	Set a parameter or get parameter values
<code>paramdef</code>	Set all parameters to default values
<code>info [name]</code>	Get an information item
<code>anapro</code>	Analyze problem data
<code>hist</code>	Plot a histogram of problem data
<code>histsol</code>	Plot a histogram of the solutions
<code>spy</code>	Plot the sparsity pattern of the A matrix
<code>anasol</code>	Analyze solutions
<code>removeitg</code>	Remove integrality constraints
<code>infsub</code>	Replace current problem with its infeasible subproblem
<code>writesol basename</code>	Write solution(s) to file(s) with given basename
<code>delsol</code>	Remove all solutions from the task
<code>exit</code>	Leave

Chapter 9

Advanced Numerical Tutorials

9.1 Solving Linear Systems Involving the Basis Matrix

A linear optimization problem always has an optimal solution which is also a basic solution. In an optimal basic solution there are exactly m basic variables where m is the number of rows in the constraint matrix A . Define

$$B \in \mathbb{R}^{m \times m}$$

as a matrix consisting of the columns of A corresponding to the basic variables. The basis matrix B is always non-singular, i.e.

$$\det(B) \neq 0$$

or, equivalently, B^{-1} exists. This implies that the linear systems

$$B\bar{x} = w \tag{9.1}$$

and

$$B^T \bar{x} = w \tag{9.2}$$

each have a unique solution for all w .

MOSEK provides functions for solving the linear systems (9.1) and (9.2) for an arbitrary w .

In the next sections we will show how to use **MOSEK** to

- *identify the solution basis,*
- *solve arbitrary linear systems.*

9.1.1 Basis identification

To use the solutions to (9.1) and (9.2) it is important to know how the basis matrix B is constructed.

Internally **MOSEK** employs the linear optimization problem

$$\begin{array}{ll} \text{maximize} & c^T x \\ \text{subject to} & Ax - x^c = 0, \\ & l^x \leq x \leq u^x, \\ & l^c \leq x^c \leq u^c. \end{array} \tag{9.3}$$

where

$$x^c \in \mathbb{R}^m \text{ and } x \in \mathbb{R}^n.$$

The basis matrix is constructed of m columns taken from

$$\begin{bmatrix} A & -I \end{bmatrix}.$$

If variable x_j is a basis variable, then the j -th column of A , denoted $a_{:,j}$, will appear in B . Similarly, if x_i^c is a basis variable, then the i -th column of $-I$ will appear in the basis. The ordering of the basis variables and therefore the ordering of the columns of B is arbitrary. The ordering of the basis variables may be retrieved by calling the function `MSK_initbasissolve`. This function initializes data structures for later use and returns the indexes of the basic variables in the array `basis`. The interpretation of the `basis` is as follows. If we have

$$\text{basis}[i] < \text{numcon}$$

then the i -th basis variable is

$$x_{\text{basis}[i]}^c.$$

Moreover, the i -th column in B will be the i -th column of $-I$. On the other hand if

$$\text{basis}[i] \geq \text{numcon},$$

then the i -th basis variable is the variable

$$x_{\text{basis}[i] - \text{numcon}}$$

and the i -th column of B is the column

$$A_{:,(\text{basis}[i] - \text{numcon})}.$$

For instance if `basis[0] = 4` and `numcon = 5`, then since `basis[0] < numcon`, the first basis variable is x_4^c . Therefore, the first column of B is the fourth column of $-I$. Similarly, if `basis[1] = 7`, then the second variable in the basis is $x_{\text{basis}[1] - \text{numcon}} = x_2$. Hence, the second column of B is identical to $a_{:,2}$.

An example

Consider the linear optimization problem:

$$\begin{aligned} & \text{minimize} && x_0 + x_1 \\ & \text{subject to} && x_0 + 2x_1 \leq 2, \\ & && x_0 + x_1 \leq 6, \\ & && x_0, x_1 \geq 0. \end{aligned} \tag{9.4}$$

Suppose a call to `MSK_initbasissolve` returns an array `basis` so that

```
basis[0] = 1,
basis[1] = 2.
```

Then the basis variables are x_1^c and x_0 and the corresponding basis matrix B is

$$\begin{bmatrix} 0 & 1 \\ -1 & 1 \end{bmatrix}.$$

Please note the ordering of the columns in B .

Listing 9.1: A program showing how to identify the basis.

```
#include "mosek.h"

static void MSKAPI printstr(void *handle,
                             const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char *argv[])
```

(continues on next page)

```

{
    MSKenv_t      env;
    MSKtask_t     task;
    MSKint32t     numcon = 2, numvar = 2;
    double        c[]  = {1.0, 1.0};
    MSKint32t     ptrb[] = {0, 2},
                  ptre[] = {2, 3};
    MSKint32t     asub[] = {0, 1, 0, 1};
    double        aval[] = {1.0, 1.0, 2.0, 1.0};
    MSKboundkeye  bkc[]  = { MSK_BK_UP, MSK_BK_UP };
    double        blc[]  = { -MSK_INFINITY, -MSK_INFINITY };
    double        buc[]  = {2.0, 6.0};

    MSKboundkeye  bkc[]  = { MSK_BK_LO, MSK_BK_LO };
    double        blx[]  = {0.0, 0.0};
    double        bux[]  = { +MSK_INFINITY, +MSK_INFINITY};
    MSKrescodee   r      = MSK_RES_OK;
    MSKint32t     i, nz;
    double        w[]    = {2.0, 6.0};
    MSKint32t     sub[]  = {0, 1};
    MSKint32t     *basis;

    if (r == MSK_RES_OK)
        r = MSK_makeenv(&env, NULL);

    if (r == MSK_RES_OK)
        r = MSK_makeemptytask(env, &task);

    if (r == MSK_RES_OK)
        MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

    if (r == MSK_RES_OK)
        r = MSK_inputdata(task, numcon, numvar, numcon, numvar,
                          c, 0.0,
                          ptrb, ptre, asub, aval, bkc, blc, buc, bkc, blx, bux);

    if (r == MSK_RES_OK)
        r = MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE);

    if (r == MSK_RES_OK)
        r = MSK_optimizetrm(task, NULL);

    if (r == MSK_RES_OK)
        basis = MSK_calloc(task, numcon, sizeof(MSKint32t));

    if (r == MSK_RES_OK)
        r = MSK_initbasissolve(task, basis);

    /* List basis variables corresponding to columns of B */
    for (i = 0; i < numcon && r == MSK_RES_OK; ++i)
    {
        printf("basis[%d] = %d\n", i, basis[i]);
        if (basis[sub[i]] < numcon)
            printf("Basis variable no %d is x%d.\n", i, basis[i]);
        else
            printf("Basis variable no %d is x%d.\n", i, basis[i] - numcon);
    }

    nz = 2;
    /* solve Bx = w */
    /* sub contains index of non-zeros in w.

```

(continues on next page)

```

    On return w contains the solution x and sub
    the index of the non-zeros in x.
*/
if (r == MSK_RES_OK)
    r = MSK_solvewithbasis(task, 0, &nz, sub, w);

if (r == MSK_RES_OK)
{
    printf("\nSolution to Bx = w:\n\n");

    /* Print solution and b. */

    for (i = 0; i < nz; ++i)
    {
        if (basis[sub[i]] < numcon)
            printf("xc%d = %e\n", basis[sub[i]] , w[sub[i]]);
        else
            printf("x%d = %e\n", basis[sub[i]] - numcon , w[sub[i]]);
    }
}

/* Solve B^T y = w */
nz      = 1;    /* Only one element in sub is nonzero. */
sub[0] = 1;     /* Only w[1] is nonzero. */
w[0]    = 0.0;
w[1]    = 1.0;

if (r == MSK_RES_OK)
    r = MSK_solvewithbasis(task, 1, &nz, sub, w);

if (r == MSK_RES_OK)
{
    printf("\nSolution to B^T y = w:\n\n");
    /* Print solution and y. */
    for (i = 0; i < nz; ++i)
        printf("y%d = %e\n", sub[i], w[sub[i]]);
}

return (r);
}/* main */

```

In the example above the linear system is solved using the optimal basis for (9.4) and the original right-hand side of the problem. Thus the solution to the linear system is the optimal solution to the problem. When running the example program the following output is produced.

```

basis[0] = 1
Basis variable no 0 is xc1.
basis[1] = 2
Basis variable no 1 is x0.

Solution to Bx = b:

x0 = 2.000000e+00
xc1 = -4.000000e+00

Solution to B^Tx = c:

x1 = -1.000000e+00
x0 = 1.000000e+00

```

Please note that the ordering of the basis variables is

$$\begin{bmatrix} x_1^c \\ x_0 \end{bmatrix}$$

and thus the basis is given by:

$$B = \begin{bmatrix} 0 & 1 \\ -1 & 1 \end{bmatrix}$$

It can be verified that

$$\begin{bmatrix} x_1^c \\ x_0 \end{bmatrix} = \begin{bmatrix} -4 \\ 2 \end{bmatrix}$$

is a solution to

$$\begin{bmatrix} 0 & 1 \\ -1 & 1 \end{bmatrix} \begin{bmatrix} x_1^c \\ x_0 \end{bmatrix} = \begin{bmatrix} 2 \\ 6 \end{bmatrix}.$$

9.1.2 Solving arbitrary linear systems

MOSEK can be used to solve an arbitrary (rectangular) linear system

$$Ax = b$$

using the `MSK_solvewithbasis` function without optimizing the problem as in the previous example. This is done by setting up an A matrix in the task, setting all variables to basic and calling the `MSK_solvewithbasis` function with the b vector as input. The solution is returned by the function.

An example

Below we demonstrate how to solve the linear system

$$\begin{bmatrix} 0 & 1 \\ -1 & 1 \end{bmatrix} \begin{bmatrix} x_0 \\ x_1 \end{bmatrix} = \begin{bmatrix} b_1 \\ b_2 \end{bmatrix} \quad (9.5)$$

with two inputs $b = (1, -2)$ and $b = (7, 0)$.

```
#include "mosek.h"

static void MSKAPI printstr(void *handle,
                           const char str[])
{
    printf("%s", str);
} /* printstr */

static MSKrescodee setup(MSKtask_t task,
                        double *aval,
                        MSKint32t *asub,
                        MSKint32t *ptrb,
                        MSKint32t *ptre,
                        MSKint32t numvar,
                        MSKint32t *basis)
{
    MSKint32t i, j;
    MSKrescodee r = MSK_RES_OK;
    MSKstakeye *skx = NULL, *skc = NULL;

    skx = (MSKstakeye *) calloc(numvar, sizeof(MSKstakeye));
```

(continues on next page)

```

if (skx == NULL && numvar)
    r = MSK_RES_ERR_SPACE;

skc = (MSKstakeye *) calloc(numvar, sizeof(MSKstakeye));
if (skc == NULL && numvar)
    r = MSK_RES_ERR_SPACE;

for (i = 0; i < numvar && r == MSK_RES_OK; ++i)
{
    skx[i] = MSK_SK_BAS;
    skc[i] = MSK_SK_FIX;
}

/* Create a coefficient matrix and right hand
   side with the data from the linear system */
if (r == MSK_RES_OK)
    r = MSK_appendvars(task, numvar);

if (r == MSK_RES_OK)
    r = MSK_appendcons(task, numvar);

for (i = 0; i < numvar && r == MSK_RES_OK; ++i)
    r = MSK_putacol(task, i, ptre[i] - ptrb[i], asub + ptrb[i], aval + ptrb[i]);

for (i = 0; i < numvar && r == MSK_RES_OK; ++i)
    r = MSK_putconbound(task, i, MSK_BK_FX, 0, 0);

for (i = 0; i < numvar && r == MSK_RES_OK; ++i)
    r = MSK_putvarbound(task, i, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY);

/* Allocate space for the solution and set status to unknown */
if (r == MSK_RES_OK)
    r = MSK_deletesolution(task, MSK_SOL_BAS);

/* Setup status keys. That is all that is needed. */
if (r == MSK_RES_OK)
    r = MSK_putskcslice(task, MSK_SOL_BAS, 0, numvar, skc);

if (r == MSK_RES_OK)
    r = MSK_putskxslice(task, MSK_SOL_BAS, 0, numvar, skx);

if (r == MSK_RES_OK)
    r = MSK_initbasissolve(task, basis);

free(skx);
free(skc);

return (r);
}

#define NUMCON 2
#define NUMVAR 2

int main(int argc, const char *argv[])
{
    const MSKint32t numvar = NUMCON,
                  numcon = NUMVAR;    /* we must have numvar == numcon */
    MSKenv_t      env;
    MSKtask_t     task;

```



```

MSKrescodee      r = MSK_RES_OK;
MSKint32t        i, nz;
double           aval[] = { -1.0, 1.0, 1.0};
MSKint32t        asub[] = {1, 0, 1};
MSKint32t        ptrb[] = {0, 1};
MSKint32t        ptre[] = {1, 3};
MSKint32t        bsub[NUMCON];
double           b[NUMCON];
MSKint32t        *basis = NULL;

if (r == MSK_RES_OK)
    r = MSK_makeenv(&env, NULL);

if (r == MSK_RES_OK)
    r = MSK_makeemptytask(env, &task);

if (r == MSK_RES_OK)
    MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

basis = (MSKint32t *) calloc(numcon, sizeof(MSKint32t));
if (basis == NULL && numvar)
    r = MSK_RES_ERR_SPACE;

/* setup: Put A matrix and factor A.
   Call this function only once for a given task. */
if (r == MSK_RES_OK)
    r = setup(task,
              aval,
              asub,
              ptrb,
              ptre,
              numvar,
              basis
              );

/* now solve rhs */
b[0] = 1;
b[1] = -2;
bsub[0] = 0;
bsub[1] = 1;
nz = 2;

if (r == MSK_RES_OK)
    r = MSK_solvewithbasis(task, 0, &nz, bsub, b);

if (r == MSK_RES_OK)
{
    printf("\nSolution to Bx = b:\n\n");
    /* Print solution and show correspondents
       to original variables in the problem */
    for (i = 0; i < nz; ++i)
    {
        if (basis[bsub[i]] < numcon)
            printf("This should never happen\n");
        else
            printf("x%d = %e\n", basis[bsub[i]] - numcon, b[bsub[i]]);
    }
}

b[0] = 7;
bsub[0] = 0;

```

```

nz = 1;

if (r == MSK_RES_OK)
    r = MSK_solvewithbasis(task, 0, &nz, bsub, b);

if (r == MSK_RES_OK)
{
    printf("\nSolution to Bx = b:\n\n");
    /* Print solution and show correspondents
       to original variables in the problem */
    for (i = 0; i < nz; ++i)
    {
        if (basis[bsub[i]] < numcon)
            printf("This should never happen\n");
        else
            printf("x%d = %e\n", basis[bsub[i]] - numcon, b[bsub[i]]);
    }
}

free(basis);
return r;
}

```

The most important step in the above example is the definition of the basic solution, where we define the status key for each variable. The actual values of the variables are not important and can be selected arbitrarily, so we set them to zero. All variables corresponding to columns in the linear system we want to solve are set to basic and the slack variables for the constraints, which are all non-basic, are set to their bound.

The program produces the output:

```

Solution to Bx = b:

x1 = 1
x0 = 3

Solution to Bx = b:

x1 = 7
x0 = 7

```

9.2 Calling BLAS/LAPACK Routines from MOSEK

Sometimes users need to perform linear algebra operations that involve dense matrices and vectors. Also **MOSEK** extensively uses high-performance linear algebra routines from the BLAS and LAPACK packages and some of these routines are included in the package shipped to the users.

The **MOSEK** versions of BLAS/LAPACK routines:

- use **MOSEK** data types and return value conventions,
- preserve the BLAS/LAPACK naming convention.

Therefore the user can leverage on efficient linear algebra routines, with a simplified interface, with no need for additional packages.

List of available routines

Table 9.1: BLAS routines available.

BLAS Name	MOSEK function	Math Expression
AXPY	<i>MSK_axpy</i>	$y = \alpha x + y$
DOT	<i>MSK_dot</i>	$x^T y$
GEMV	<i>MSK_gemv</i>	$y = \alpha Ax + \beta y$
GEMM	<i>MSK_gemm</i>	$C = \alpha AB + \beta C$
SYRK	<i>MSK_syrk</i>	$C = \alpha AA^T + \beta C$

Table 9.2: LAPACK routines available.

LAPACK Name	MOSEK function	Description
POTRF	<i>MSK_potrf</i>	Cholesky factorization of a semidefinite symmetric matrix
SYEVD	<i>MSK_syevd</i>	Eigenvalues and eigenvectors of a symmetric matrix
SYEIG	<i>MSK_syeig</i>	Eigenvalues of a symmetric matrix

Source code examples

In Listing 9.2 we provide a simple working example. It has no practical meaning except showing how to organize the input and call the methods.

Listing 9.2: Calling BLAS and LAPACK routines from Optimizer API for C.

```
#include "mosek.h"
void print_matrix(MSKrealt* x, MSKint32t r, MSKint32t c)
{
    MSKint32t i, j;
    for (i = 0; i < r; i++)
    {
        for (j = 0; j < c; j++)
            printf("%f ", x[j * r + i]);

        printf("\n");
    }
}

int main(int argc, char* argv[])
{
    MSKrescodee r = MSK_RES_OK;
    MSKenv_t env = NULL;

    const MSKint32t n = 3, m = 2, k = 3;

    MSKrealt alpha = 2.0, beta = 0.5;
    MSKrealt x[] = {1.0, 1.0, 1.0};
    MSKrealt y[] = {1.0, 2.0, 3.0};
    MSKrealt z[] = {1.0, 1.0};
    MSKrealt A[] = {1.0, 1.0, 2.0, 2.0, 3.0, 3.0};
    MSKrealt B[] = {1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0};
    MSKrealt C[] = {1.0, 2.0, 3.0, 4.0, 5.0, 6.0};
    MSKrealt D[] = {1.0, 1.0, 1.0, 1.0};
    MSKrealt Q[] = {1.0, 0.0, 0.0, 2.0};
    MSKrealt v[] = {0.0, 0.0, 0.0};

    MSKrealt xy;
```

(continues on next page)

```

/* BLAS routines*/
r = MSK_makeenv(&env, NULL);
printf("n=%d m=%d k=%d\n", m, n, k);
printf("alpha=%f\n", alpha);
printf("beta=%f\n", beta);

r = MSK_dot(env, n, x, y, &xy);
printf("dot results= %f r=%d\n", xy, r);

print_matrix(x, 1, n);
print_matrix(y, 1, n);

r = MSK_axpy(env, n, alpha, x, y);
puts("axpy results is");
print_matrix(y, 1, n);

r = MSK_gemv(env, MSK_TRANSPOSE_NO, m, n, alpha, A, x, beta, z);
printf("gemv results is (r=%d) \n", r);
print_matrix(z, 1, m);

r = MSK_gemm(env, MSK_TRANSPOSE_NO, MSK_TRANSPOSE_NO, m, n, k, alpha, A, B, beta, C);
printf("gemm results is (r=%d) \n", r);
print_matrix(C, m, n);

r = MSK_syrk(env, MSK_UPLO_LO, MSK_TRANSPOSE_NO, m, k, 1., A, beta, D);
printf("syrk results is (r=%d) \n", r);
print_matrix(D, m, m);

/* LAPACK routines*/

r = MSK_potrf(env, MSK_UPLO_LO, m, Q);
printf("potrf results is (r=%d) \n", r);
print_matrix(Q, m, m);

r = MSK_syevig(env, MSK_UPLO_LO, m, Q, v);
printf("syevig results is (r=%d) \n", r);
print_matrix(v, 1, m);

r = MSK_syevd(env, MSK_UPLO_LO, m, Q, v);
printf("syevd results is (r=%d) \n", r);
print_matrix(v, 1, m);
print_matrix(Q, m, m);

/* Delete the environment and the associated data. */
MSK_deleteenv(&env);

return r;
}

```

9.3 Computing a Sparse Cholesky Factorization

Given a positive semidefinite symmetric (PSD) matrix

$$A \in \mathbb{R}^{n \times n}$$

it is well known there exists a matrix L such that

$$A = LL^T.$$

If the matrix L is lower triangular then it is called a *Cholesky factorization*. Given A is positive definite (nonsingular) then L is also nonsingular. A Cholesky factorization is useful for many reasons:

- A system of linear equations $Ax = b$ can be solved by first solving the lower triangular system $Ly = b$ followed by the upper triangular system $L^T x = y$.
- A quadratic term $x^T Ax$ in a constraint or objective can be replaced with $y^T y$ for $y = L^T x$, potentially leading to a more robust formulation (see [And13]).

Therefore, **MOSEK** provides a function that can compute a Cholesky factorization of a PSD matrix. In addition a function for solving linear systems with a nonsingular lower or upper triangular matrix is available.

In practice A may be very large with n is in the range of millions. However, then A is typically sparse which means that most of the elements in A are zero, and sparsity can be exploited to reduce the cost of computing the Cholesky factorization. The computational savings depend on the positions of zeros in A . For example, below a matrix A is given together with a Cholesky factor up to 5 digits of accuracy:

$$A = \begin{bmatrix} 4 & 1 & 1 & 1 \\ 1 & 1 & 0 & 0 \\ 1 & 0 & 1 & 0 \\ 1 & 0 & 0 & 1 \end{bmatrix}, \quad L = \begin{bmatrix} 2.0000 & 0 & 0 & 0 \\ 0.5000 & 0.8660 & 0 & 0 \\ 0.5000 & -0.2887 & 0.8165 & 0 \\ 0.5000 & -0.2887 & -0.4082 & 0.7071 \end{bmatrix}. \quad (9.6)$$

However, if we symmetrically permute the rows and columns of A using a permutation matrix P

$$P = \begin{bmatrix} 0 & 1 & 0 & 0 \\ 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \\ 1 & 0 & 0 & 0 \end{bmatrix}, \quad A' = PAP^T = \begin{bmatrix} 1 & 0 & 0 & 1 \\ 0 & 1 & 0 & 1 \\ 0 & 0 & 1 & 1 \\ 1 & 1 & 1 & 4 \end{bmatrix},$$

then the Cholesky factorization of $A' = L' L'^T$ is

$$L' = \begin{bmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 1 & 0 \\ 1 & 1 & 1 & 1 \end{bmatrix}$$

which is sparser than L .

Computing a permutation matrix that leads to the sparsest Cholesky factorization or the minimal amount of work is NP-hard. Good permutations can be chosen by using heuristics, such as the minimum degree heuristic and variants. The function `MSK_computesparscholesky` provided by **MOSEK** for computing a Cholesky factorization has a build in permutation aka. reordering heuristic. The following code illustrates the use of `MSK_computesparscholesky` and `MSK_sparsetriangularsolvedense`.

Listing 9.3: How to use the sparse Cholesky factorization routine available in **MOSEK**.

```
r = MSK_computesparscholesky(env,
    0,          /* Disable multithreading */
    1,          /* Apply a reordering heuristic */
    1.0e-14,    /* Singularity tolerance */
    n, anzc, aptrc, asubc, avalc,
    &perm, &diag, &lnzc, &lptrc, &lensubnval, &lsubc, &lvalc);

if (r == MSK_RES_OK)
{
    MSKint32t i, j;
    MSKrealt *x;
    printspars(n, perm, diag, lnzc, lptrc, lensubnval, lsubc, lvalc);

    x = MSK_callocenv(env, n, sizeof(MSKrealt));
    if (x)
    {
```

(continues on next page)

(continued from previous page)

```
/* Permuted b is stored as x. */
for (i = 0; i < n; ++i) x[i] = b[perm[i]];

/* Compute inv(L)*x. */
r = MSK_sparsetriangularsolvedense(env, MSK_TRANSPOSE_NO, n,
                                   lnzc, lptrc, lensubnval, lsubc, lvalc, x);

if (r == MSK_RES_OK) {
    /* Compute inv(L^T)*x. */
    r = MSK_sparsetriangularsolvedense(env, MSK_TRANSPOSE_YES, n,
                                       lnzc, lptrc, lensubnval, lsubc, lvalc, x);

    printf("\nSolution A x = b, x = [ ");
    for (i = 0; i < n; i++)
        for (j = 0; j < n; j++) if (perm[j] == i) printf("%.2f ", x[j]);
    printf("]\n");
}

MSK_freeenv(env, x);
}
else
    printf("Out of space while creating x.\n");
}
else
    printf("Cholesky computation failed: %d\n", (int) r);
```

We can set up the data to recreate the matrix A from (9.6):

```
const MSKint32t n      = 4;          // Data from the example in the text
//Observe that anzc, aptrc, asubc and avalc only specify the lower triangular part.
const MSKint32t anzc[] = {4, 1, 1, 1},
               asubc[] = {0, 1, 2, 3, 1, 2, 3};
const MSKint64t aptrc[] = {0, 4, 5, 6};
const MSKrealt  avalc[] = {4.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0},
               b[]      = {13.0, 3.0, 4.0, 5.0};
MSKint32t      *perm = NULL, *lnzc = NULL, *lsubc = NULL;
MSKint64t      lensubnval, *lptrc = NULL;
MSKrealt      *diag = NULL, *lvalc = NULL;
```

and we obtain the following output:

```
Example with positive definite A.
P = [ 3 2 0 1 ]
diag(D) = [ 0.00 0.00 0.00 0.00 ]
L=
1.00 0.00 0.00 0.00
0.00 1.00 0.00 0.00
1.00 1.00 1.41 0.00
0.00 0.00 0.71 0.71

Solution A x = b, x = [ 1.00 2.00 3.00 4.00 ]
```

The output indicates that with the permutation matrix

$$P = \begin{bmatrix} 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \\ 0 & 1 & 0 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix}$$

there is a Cholesky factorization $PAP^T = LL^T$, where

$$L = \begin{bmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 1 & 1 & 1.4142 & 0 \\ 0 & 0 & 0.7071 & 0.7071 \end{bmatrix}$$

The remaining part of the code solves the linear system $Ax = b$ for $b = [13, 3, 4, 5]^T$. The solution is reported to be $x = [1, 2, 3, 4]^T$, which is correct.

The second example shows what happens when we compute a sparse Cholesky factorization of a singular matrix. In this example A is a rank 1 matrix

$$A = \begin{bmatrix} 1 & 1 & 1 \\ 1 & 1 & 1 \\ 1 & 1 & 1 \end{bmatrix} = \begin{bmatrix} 1 \\ 1 \\ 1 \end{bmatrix} \begin{bmatrix} 1 & 1 & 1 \end{bmatrix}^T \quad (9.7)$$

```
const MSKint32t n      = 3;
const MSKint32t anzc[] = {3, 2, 1},
               asubc[] = {0, 1, 2, 1, 2, 2};
const MSKint64t aptrc[] = {0, 3, 5};
const MSKrealt  avalc[] = {1.0, 1.0, 1.0, 1.0, 1.0, 1.0};
MSKint32t      *perm = NULL, *lnzc = NULL, *lsubc = NULL;
MSKint64t      lensubnval, *lptrc = NULL;
MSKrealt      *diag = NULL, *lvalc = NULL;
```

Now we get the output

```
P = [ 0 2 1 ]
diag(D) = [ 0.00e+00 1.00e-14 1.00e-14 ]
L=
1.00e+00 0.00e+00 0.00e+00
1.00e+00 1.00e-07 0.00e+00
1.00e+00 0.00e+00 1.00e-07
```

which indicates the decomposition

$$PAP^T = LL^T - D$$

where

$$P = \begin{bmatrix} 1 & 0 & 0 \\ 0 & 0 & 1 \\ 0 & 1 & 0 \end{bmatrix}, \quad L = \begin{bmatrix} 1 & 0 & 0 \\ 1 & 10^{-7} & 0 \\ 1 & 0 & 10^{-7} \end{bmatrix}, \quad D = \begin{bmatrix} 1 & 0 & 0 \\ 0 & 10^{-14} & 0 \\ 0 & 0 & 10^{-14} \end{bmatrix}.$$

Since A is only positive semidefinite, but not of full rank, some of diagonal elements of A are boosted to make it truly positive definite. The amount of boosting is passed as an argument to `MSK_computesparsesholesky`, in this case 10^{-14} . Note that

$$PAP^T = LL^T - D$$

where D is a small matrix so the computed Cholesky factorization is exact of slightly perturbed A . In general this is the best we can hope for in finite precision and when A is singular or close to being singular.

We will end this section by a word of caution. Computing a Cholesky factorization of a matrix that is not of full rank and that is not sufficiently well conditioned may lead to incorrect results i.e. a matrix that is indefinite may declared positive semidefinite and vice versa.

9.4 Converting a quadratically constrained problem to conic form

MOSEK employs the following form of quadratic problems:

$$\begin{aligned} & \text{minimize} && \frac{1}{2}x^T Q^o x + c^T x + c^f \\ & \text{subject to} && \begin{aligned} l_k^c &\leq \frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{k,j} x_j &\leq u_k^c, & k = 0, \dots, m-1, \\ l_j^x &\leq x_j &\leq u_j^x, & j = 0, \dots, n-1. \end{aligned} \end{aligned} \quad (9.8)$$

A conic quadratic constraint has the form

$$x \in \mathcal{Q}^n$$

in its most basic form where

$$\mathcal{Q}^n = \left\{ x \in \mathbb{R}^n : x_1 \geq \sqrt{\sum_{j=2}^n x_j^2} \right\}.$$

A quadratic problem such as (9.8), if convex, can be reformulated in conic form. This is in fact the reformulation **MOSEK** performs internally. It has many advantages:

- elegant duality theory for conic problems,
- reporting accurate dual information for quadratic inequalities is hard and/or computational expensive,
- it certifies that the original quadratic problem is indeed convex,
- modeling directly in conic form usually leads to a better model [And13] i.e. a faster solution time and better numerical properties.

In addition, there are more types of conic constraints that can be combined with a quadratic cone, for example semidefinite cones.

MOSEK offers a function that performs the conversion from quadratic to conic quadratic form explicitly. Note that the reformulation is not unique. The approach followed by **MOSEK** is to introduce additional variables, linear constraints and quadratic cones to obtain a larger but equivalent problem in which the original variables are preserved.

In particular:

- all variables and constraints are kept in the problem,
- each quadratic constraint and quadratic terms in the objective generate one rotated quadratic cone,
- each quadratic constraint will contain no coefficients and upper/lower bounds will be set to $\infty, -\infty$ respectively.

This allows the user to recover the original variable and constraint values, as well as their dual values, with no conversion or additional effort.

Note: `MSK_toconic` modifies the input task in-place: this means that if the reformulation is not possible, i.e. the problem is not conic representable, the state of the task is in general undefined. The user should consider cloning the original task.

9.4.1 Quadratic Constraint Reformulation

Let us assume we want to convert the following quadratic constraint

$$l \leq \frac{1}{2}x^T Qx + \sum_{j=0}^{n-1} a_j x_j \leq u$$

to conic form. We first check whether $l = -\infty$ or $u = \infty$, otherwise either the constraint can be dropped, or the constraint is not convex. Thus let us consider the case

$$\frac{1}{2}x^T Qx + \sum_{j=0}^{n-1} a_j^T x_j \leq u. \tag{9.9}$$

Introducing an additional variable w such that

$$w = u - \sum_{j=0}^{n-1} a_j^T x_j \tag{9.10}$$

we obtain the equivalent form

$$\begin{aligned} \frac{1}{2}x^T Qx &\leq w, \\ u - \sum_{j=0}^{n-1} a_j^T x_j &= w. \end{aligned}$$

If Q is positive semidefinite, then there exists a matrix F such that

$$Q = FF^T \quad (9.11)$$

and therefore we can write

$$\begin{aligned} \|Fx\|^2 &\leq 2w, \\ u - \sum_{j=0}^{n-1} a_j^T x_j &= w. \end{aligned}$$

Introducing an additional variable $z = 1$, and setting $y = Fx$ we obtain the conic formulation

$$\begin{aligned} (w, z, y) &\in \mathcal{Q}_r, \\ z &= 1 \\ y &= Fx \\ w &= u - a^T x. \end{aligned} \quad (9.12)$$

Summarizing, for each quadratic constraint involving t variables, **MOSEK** introduces

1. a rotated quadratic cone of dimension $t + 2$,
2. two additional variables for the cone roots,
3. t additional variables to map the remaining part of the cone,
4. t linear constraints.

A quadratic term in the objective is reformulated in a similar fashion. We refer to [And13] for a more thorough discussion.

Example

Next we consider a simple problem with quadratic objective function:

$$\begin{aligned} \text{minimize} \quad & \frac{1}{2}(13x_0^2 + 17x_1^2 + 12x_2^2 + 24x_0x_1 + 12x_1x_2 - 4x_0x_2) - 22x_0 - 14.5x_1 + 12x_2 + 1 \\ \text{subject to} \quad & -1 \leq x_0, x_1, x_2 \leq 1 \end{aligned}$$

We can specify it in the human-readable OPF format.

```
[comment]
An example of small QO problem from Boyd and Vandenberghe, "Convex Optimization", page 189 ex_
↪4.3
The solution is (1,0.5,-1)
[/comment]

[variables]
x0 x1 x2
[/variables]

[objective min]
0.5 (13 x0^2 + 17 x1^2 + 12 x2^2 + 24 x0 * x1 + 12 x1 * x2 - 4 x0 * x2 ) - 22 x0 - 14.5 x1 +
↪12 x2 + 1
[/objective]

[bounds]
[b] -1 <= * <= 1 [/b]
[/bounds]
```

The objective function is convex, the minimum is attained for $x^* = (1, 0.5, -1)$. The conversion will introduce first a variable x_3 in the objective function such that $x_3 \geq 1/2x^T Q x$ and then convert the latter directly in conic form. The converted problem follows:

$$\begin{aligned} \text{minimize} \quad & -22x_0 - 14.5x_1 + 12x_2 + x_3 + 1 \\ \text{subject to} \quad & 3.61x_0 + 3.33x_1 - 0.55x_2 - x_6 = 0 \\ & +2.29x_1 + 3.42x_2 - x_7 = 0 \\ & 0.81x_1 - x_8 = 0 \\ & -x_3 + x_4 = 0 \\ & x_5 = 1 \\ & (x_4, x_5, x_6, x_7, x_8) \in \mathcal{Q}_\nabla \\ & -1 \leq x_0, x_1, x_2 \leq 1 \end{aligned}$$

The model generated by *MSK_toconic* is

```
[comment]
  Written by MOSEK version 8.1.0.19
  Date 21-08-17
  Time 10:53:36
[/comment]

[hints]
  [hint NUMVAR] 9 [/hint]
  [hint NUMCON] 4 [/hint]
  [hint NUMANZ] 11 [/hint]
  [hint NUMQNZ] 0 [/hint]
  [hint NUMCONE] 1 [/hint]
[/hints]

[variables disallow_new_variables]
  x0000_x0 x0001_x1 x0002_x2 x0003 x0004
  x0005 x0006 x0007 x0008
[/variables]

[objective minimize]
  - 2.2e+01 x0000_x0 - 1.45e+01 x0001_x1 + 1.2e+01 x0002_x2 + x0003
  + 1e+00
[/objective]

[constraints]
  [con c0000] 3.605551275463989e+00 x0000_x0 - 5.547001962252291e-01 x0002_x2 + 3.
  ↪ 328201177351375e+00 x0001_x1 - x0006 = 0e+00 [/con]
  [con c0001] 3.419401657060442e+00 x0002_x2 + 2.294598480395823e+00 x0001_x1 - x0007 = 0e+00 ↪
  ↪ [/con]
  [con c0002] 8.111071056538127e-01 x0001_x1 - x0008 = 0e+00 [/con]
  [con c0003] - x0003 + x0004 = 0e+00 [/con]
[/constraints]

[bounds]
  [b] -1e+00      <= x0000_x0,x0001_x1,x0002_x2 <= 1e+00 [/b]
  [b]              x0003,x0004 free [/b]
  [b]              x0005 = 1e+00 [/b]
  [b]              x0006,x0007,x0008 free [/b]
  [cone rquad k0000] x0004, x0005, x0006, x0007, x0008 [/cone]
[/bounds]
```

We can clearly see that constraints c0000, c0001 and c0002 represent the original linear constraints as in (9.11), while c0003 corresponds to (9.10). The cone roots are x0005 and x0004.

Chapter 10

Technical guidelines

This section contains some more in-depth technical guidelines for Optimizer API for C, not strictly necessary for basic use of **MOSEK**.

10.1 Memory management and garbage collection

Users who experience memory leaks, especially:

- memory usage not decreasing after the solver terminates,
- memory usage increasing when solving a sequence of problems,

should make sure that the memory used by the task is released when the task is no longer needed. This is done with the method `MSK_deletetask`. The same applies to the environment when it is no longer needed.

```
MSK_deletetask(&task);  
MSK_deleteenv(&env);
```

10.2 Names

All elements of an optimization problem in **MOSEK** (objective, constraints, variables, etc.) can be given names. Assigning meaningful names to variables and constraints makes it much easier to understand and debug optimization problems dumped to a file. On the other hand, note that assigning names can substantially increase setup time, so it should be avoided in time-critical applications.

Names of various elements of the problem can be set and retrieved using various functions listed in the **Names** section of [Sec. 15.2](#).

10.3 Multithreading

Thread safety

Sharing a task between threads is safe, as long as it is not accessed from more than one thread at a time. Multiple tasks can be created and used in parallel without any problems.

Parallelization

The interior-point and mixed-integer optimizers in **MOSEK** are parallelized. By default **MOSEK** will automatically select the number of threads. However, the maximum number of threads allowed can be changed by setting the parameter `MSK_IPAR_NUM_THREADS` and related parameters. This should never exceed the number of cores. See [Sec. 13](#) and [Sec. 13.4](#) for more details.

The speed-up obtained when using multiple threads is highly problem and hardware dependent. We recommend experimenting with various thread numbers to determine the optimal settings. For small problems using multiple threads may be counter-productive because of the associated overhead.

Determinism

By default the optimizer is run-to-run deterministic, which means that it will return the same answer each time it is run on the same machine with the same input, the same parameter settings (including number of threads) and no time limits.

Setting the number of threads

The number of threads the optimizer uses can be changed with the parameter *MSK_IPAR_NUM_THREADS*.

For conic problems (when the conic optimizer is used) the value set at the first optimization will remain fixed through the lifetime of the process. The thread pool will be reserved once for all and subsequent changes to *MSK_IPAR_NUM_THREADS* will have no effect. The only possibility at that point is to switch between multi-threaded and single-threaded interior-point optimization using the parameter *MSK_IPAR_INTPNT_MULTI_THREAD*.

10.4 Efficiency

Although **MOSEK** is implemented to handle memory efficiently, the user may have valuable knowledge about a problem, which could be used to improve the performance of **MOSEK**. This section discusses some tricks and general advice that hopefully make **MOSEK** process your problem faster.

Reduce the number of function calls and avoid input loops

For example, instead of setting the entries in the linear constraint matrix one by one (*MSK_putaij*) define them all at once (*MSK_putaijlist*) or in convenient large chunks (*MSK_putacollist* etc.)

Use one environment only

If possible share the environment between several tasks. For most applications you need to create only a single environment.

Read part of the solution

When fetching the solution, data has to be copied from the optimizer to the user's data structures. Instead of fetching the whole solution, consider fetching only the interesting part (see for example *MSK_getxslice* and similar).

Avoiding memory fragmentation

MOSEK stores the optimization problem in internal data structures in the memory. Initially **MOSEK** will allocate structures of a certain size, and as more items are added to the problem the structures are reallocated. For large problems the same structures may be reallocated many times causing memory fragmentation. One way to avoid this is to give **MOSEK** an estimated size of your problem using the functions:

- *MSK_putmaxnumvar*. Estimate for the number of variables.
- *MSK_putmaxnumcon*. Estimate for the number of constraints.
- *MSK_putmaxnumcone*. Estimate for the number of cones.
- *MSK_putmaxnumbarvar*. Estimate for the number of semidefinite matrix variables.
- *MSK_putmaxnumanz*. Estimate for the number of non-zeros in A .
- *MSK_putmaxnumqnz*. Estimate for the number of non-zeros in the quadratic terms.

None of these functions changes the problem, they only serve as hints. If the problem ends up growing larger, the estimates are automatically increased.

Do not mix put- and get- functions

MOSEK will queue put- requests internally until a get- function is called. If put- and get- calls are interleaved, the queue will have to be flushed more frequently, decreasing efficiency.

In general get- commands should not be called often (or at all) during problem setup.

Use the LIFO principle

When removing constraints and variables, try to use a LIFO (Last In First Out) approach. **MOSEK** can more efficiently remove constraints and variables with a high index than a small index.

An alternative to removing a constraint or a variable is to fix it at 0, and set all relevant coefficients to 0. Generally this will not have any impact on the optimization speed.

Add more constraints and variables than you need (now)

The cost of adding one constraint or one variable is about the same as adding many of them. Therefore, it may be worthwhile to add many variables instead of one. Initially fix the unused variable at zero, and then later unfix them as needed. Similarly, you can add multiple free constraints and then use them as needed.

Do not remove basic variables

When performing re-optimizations, instead of removing a basic variable it may be more efficient to fix the variable at zero and then remove it when the problem is re-optimized and it has left the basis. This makes it easier for **MOSEK** to restart the simplex optimizer.

10.5 The license system

MOSEK is a commercial product that **always** needs a valid license to work. **MOSEK** uses a third party license manager to implement license checking. The number of license tokens provided determines the number of optimizations that can be run simultaneously.

By default a license token remains checked out from the first optimization until the end of the **MOSEK** session, i.e.

- a license token is checked out when *MSK_optimize* is first called, and
- it is returned when the **MOSEK** environment is deleted.

Calling *MSK_optimize* from different threads using the same **MOSEK** environment only consumes one license token.

Starting the optimization when no license tokens are available will result in an error.

Default behaviour of the license system can be changed in several ways:

- Setting the parameter *MSK_IPAR_CACHE_LICENSE* to *MSK_OFF* will force **MOSEK** to return the license token immediately after the optimization completed.
- Setting the license wait flag with the parameter *MSK_IPAR_LICENSE_WAIT* will force **MOSEK** to wait until a license token becomes available instead of returning with an error. The wait time between checks can be set with *MSK_putlicensewait*.
- Additional license checkouts and checkins can be performed with the functions *MSK_checkinlicense* and *MSK_checkoutlicense*.
- Usually the license system is stopped automatically when the **MOSEK** library is unloaded. However, when the user explicitly unloads the library (using e.g. `FreeLibrary`), the license system must be stopped before the library is unloaded. This can be done by calling the function *MSK_licensecleanup* as the last function call to **MOSEK**.

10.6 Deployment

When redistributing a C application using the **MOSEK** Optimizer API for C 9.0.96, the following libraries must be included:

64-bit Linux	64-bit Windows	32-bit Windows	64-bit Mac OS
libmosek64.so.9.0	mosek64_9_0.dll	mosek9_0.dll	libmosek64.9.0.dylib
libcilkrts.so.5	cilkrts20.dll	cilkrts20.dll	libcilkrts.5.dylib

10.7 Strings

MOSEK supports Unicode strings. All arguments of type `char *` are allowed to be UTF8 encoded strings (<http://en.wikipedia.org/wiki/UTF-8>). Please note that

- an ASCII string is always a valid UTF8 string, and
- an UTF8 string is stored in a `char` array.

It is possible to convert between `wchar_t` strings and UTF8 strings using the functions *MSK_wchartoutf8* and *MSK_utf8towchar*. A working example is provided in the example file `unicode.c`.

Chapter 11

Case Studies

In this section we present some case studies in which the Optimizer API for C is used to solve real-life applications. These examples involve some more advanced modeling skills and possibly some input data. The user is strongly recommended to first read the basic tutorials of [Sec. 6](#) before going through these advanced case studies.

- *Portfolio Optimization*
 - **Keywords:** Markowitz model, variance, risk, efficient frontier, transaction cost, market impact cost
 - **Type:** Conic Quadratic, Power Cone, Mixed-Integer Optimization
- *Logistic regression*
 - **Keywords:** machine learning, logistic regression, classifier, log-sum-exp, softplus, regularization
 - **Type:** Exponential Cone, Quadratic Cone
- *Concurrent Optimizer*
 - **Keywords:** Concurrent optimization
 - **Type:** Linear Optimization, Mixed-Integer Optimization

11.1 Portfolio Optimization

In this section the Markowitz portfolio optimization problem and variants are implemented using the **MOSEK** optimizer API.

- *Basic Markowitz model*
- *Efficient frontier*
- *Factor model and efficiency*
- *Market impact costs*
- *Transaction costs*
- *Cardinality constraints*

11.1.1 A Basic Portfolio Optimization Model

The classical Markowitz portfolio optimization problem considers investing in n stocks or assets held over a period of time. Let x_j denote the amount invested in asset j , and assume a stochastic model where the return of the assets is a random variable r with known mean

$$\mu = \mathbf{E}r$$

and covariance

$$\Sigma = \mathbf{E}(r - \mu)(r - \mu)^T.$$

The return of the investment is also a random variable $y = r^T x$ with mean (or expected return)

$$\mathbf{E}y = \mu^T x$$

and variance

$$\mathbf{E}(y - \mathbf{E}y)^2 = x^T \Sigma x.$$

The standard deviation

$$\sqrt{x^T \Sigma x}$$

is usually associated with risk.

The problem facing the investor is to rebalance the portfolio to achieve a good compromise between risk and expected return, e.g., maximize the expected return subject to a budget constraint and an upper bound (denoted γ) on the tolerable risk. This leads to the optimization problem

$$\begin{aligned} & \text{maximize} && \mu^T x \\ & \text{subject to} && e^T x = w + e^T x^0, \\ & && x^T \Sigma x \leq \gamma^2, \\ & && x \geq 0. \end{aligned} \tag{11.1}$$

The variables x denote the investment i.e. x_j is the amount invested in asset j and x_j^0 is the initial holding of asset j . Finally, w is the initial amount of cash available.

A popular choice is $x^0 = 0$ and $w = 1$ because then x_j may be interpreted as the relative amount of the total portfolio that is invested in asset j .

Since e is the vector of all ones then

$$e^T x = \sum_{j=1}^n x_j$$

is the total investment. Clearly, the total amount invested must be equal to the initial wealth, which is

$$w + e^T x^0.$$

This leads to the first constraint

$$e^T x = w + e^T x^0.$$

The second constraint

$$x^T \Sigma x \leq \gamma^2$$

ensures that the variance, is bounded by the parameter γ^2 . Therefore, γ specifies an upper bound of the standard deviation (risk) the investor is willing to undertake. Finally, the constraint

$$x_j \geq 0$$

excludes the possibility of short-selling. This constraint can of course be excluded if short-selling is allowed.

The covariance matrix Σ is positive semidefinite by definition and therefore there exist a matrix G such that

$$\Sigma = GG^T. \quad (11.2)$$

In general the choice of G is **not** unique and one possible choice of G is the Cholesky factorization of Σ . However, in many cases another choice is better for efficiency reasons as discussed in [Sec. 11.1.3](#). For a given G we have that

$$\begin{aligned} x^T \Sigma x &= x^T G G^T x \\ &= \|G^T x\|^2. \end{aligned}$$

Hence, we may write the risk constraint as

$$\gamma \geq \|G^T x\|$$

or equivalently

$$(\gamma, G^T x) \in \mathcal{Q}^{n+1},$$

where \mathcal{Q}^{n+1} is the $(n+1)$ -dimensional quadratic cone. Therefore, problem (11.1) can be written as

$$\begin{aligned} &\text{maximize} && \mu^T x \\ &\text{subject to} && e^T x = w + e^T x^0, \\ & && (\gamma, G^T x) \in \mathcal{Q}^{n+1}, \\ & && x \geq 0, \end{aligned} \quad (11.3)$$

which is a conic quadratic optimization problem that can easily be formulated and solved with Optimizer API for C. Subsequently we will use the example data

$$\mu = \begin{bmatrix} 0.1073 \\ 0.0737 \\ 0.0627 \end{bmatrix}$$

and

$$\Sigma = 0.1 \cdot \begin{bmatrix} 0.2778 & 0.0387 & 0.0021 \\ 0.0387 & 0.1112 & -0.0020 \\ 0.0021 & -0.0020 & 0.0115 \end{bmatrix}.$$

This implies

$$G^T = \sqrt{0.1} \begin{bmatrix} 0.5271 & 0.0734 & 0.0040 \\ 0 & 0.3253 & -0.0070 \\ 0 & 0 & 0.1069 \end{bmatrix}$$

Why a Conic Formulation?

Problem (11.1) is a convex quadratically constrained optimization problem that can be solved directly using **MOSEK**. Why then reformulate it as a conic quadratic optimization problem (11.3)? The main reason for choosing a conic model is that it is more robust and usually solves faster and more reliably. For instance it is not always easy to numerically validate that the matrix Σ in (11.1) is positive semidefinite

due to the presence of rounding errors. It is also very easy to make a mistake so Σ becomes indefinite. These problems are completely eliminated in the conic formulation.

Moreover, observe the constraint

$$\|G^T x\| \leq \gamma$$

more numerically robust than

$$x^T \Sigma x \leq \gamma^2$$

for very small and very large values of γ . Indeed, if say $\gamma \approx 10^4$ then $\gamma^2 \approx 10^8$, which introduces a scaling issue in the model. Hence, using conic formulation we work with the standard deviation instead of variance, which usually gives rise to a better scaled model.

Implementing the Portfolio Model

Creating a matrix formulation

The Optimizer API for C requires that an optimization problem is entered in the following standard form:

$$\begin{aligned} & \text{maximize} && c^T \hat{x} \\ & \text{subject to} && l^c \leq A\hat{x} \leq u^c, \\ & && l^x \leq \hat{x} \leq u^x, \\ & && \hat{x} \in \mathcal{K}. \end{aligned} \tag{11.4}$$

We refer to \hat{x} as the API variable. It means we need to reformulate (11.3). The first step is to introduce auxiliary variables so that the conic constraint involves only unique variables:

$$\begin{aligned} & \text{maximize} && \mu^T x \\ & \text{subject to} && e^T x = w + e^T x^0, \\ & && G^T x - t = 0, \\ & && [s; t] \in \mathcal{Q}^{n+1}, \\ & && x \geq 0, \\ & && s = \gamma. \end{aligned} \tag{11.5}$$

Here s is an additional scalar variable and t is a vector variable of dimension n . The next step is to concatenate all the variables into one long variable vector:

$$\hat{x} = [x; s; t] = \begin{bmatrix} x \\ s \\ t \end{bmatrix} \tag{11.6}$$

The details of the concatenation are specified below.

Table 11.1: Storage layout of the \hat{x} variable.

Variable	Length	Offset
x	n	0
s	1	n
t	n	$n + 1$

The offset determines where the variable starts. (Note that all variables are indexed from 0). For instance

$$\hat{x}_{n+1+i} = t_i.$$

because the offset of the t variable is $n + 1$.

Given the ordering of the variables specified by (11.6) it is useful to visualize the linear constraints (11.4) in an explicit block matrix form:

$$\left[\begin{array}{c|c|c} 1 & 0 & 0 \\ \hline G^T & 0 & -1 \\ \hline & & -1 \end{array} \right] \cdot \begin{bmatrix} x \\ s \\ t \end{bmatrix} = \begin{bmatrix} w + e^T x_0 \\ 0 \end{bmatrix}. \quad (11.7)$$

In other words, we should define the specific components of the problem description as follows:

$$\begin{aligned} c &= \begin{bmatrix} \mu^T & 0 & 0_n \end{bmatrix}^T, \\ A &= \begin{bmatrix} e^T & 0 & 0_n \\ G^T & 0_n & -I_n \end{bmatrix}, \\ l^c &= \begin{bmatrix} w + e^T x_0 & 0_n \end{bmatrix}^T, \\ u^c &= \begin{bmatrix} w + e^T x_0 & 0_n \end{bmatrix}^T, \\ l^x &= \begin{bmatrix} 0_n & \gamma & -\infty_n \end{bmatrix}^T, \\ u^x &= \begin{bmatrix} \infty_n & \gamma & \infty_n \end{bmatrix}^T. \end{aligned} \quad (11.8)$$

Source code example

From the block matrix form (11.7) and the explicit specification (11.8), using the offset information in Table 11.1 it is easy to calculate the index and value of each entry of the linear constraint matrix. The code below sets up the general optimization problem (11.5) and solves it for the example data. Of course it is only necessary to set non-zero entries of the linear constraint matrix.

Listing 11.1: Code implementing model (11.5).

```
#include <math.h>
#include <stdio.h>
#include "mosek.h"

#define MOSEKCALL(_r,_call) if ( (_r)==MSK_RES_OK ) (_r) = (_call)

static void MSKAPI printstr(void *handle,
                           const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char **argv)
{
    char          buf[128];

    double        expret  = 0.0,
                 stddev  = 0.0,
                 xj;

    const MSKint32t n      = 3;
    const MSKrealt  gamma  = 0.05;
    const MSKrealt  mu[]   = {0.1073, 0.0737, 0.0627};
    const MSKrealt  GT[][3] = {{0.1667, 0.0232, 0.0013},
                               {0.0000, 0.1033, -0.0022},
                               {0.0000, 0.0000, 0.0338}};

    const MSKrealt  x0[3]  = {0.0, 0.0, 0.0};
    const MSKrealt  w      = 1.0;
    MSKrealt        rtemp;
    MSKenv_t        env;
```

(continues on next page)

```

MSKint32t      k, i, j, offsetx, offsets, offsett, *sub;
MSKrescodee    res = MSK_RES_OK, trmcode;
MSKtask_t      task;

/* Initial setup. */
env = NULL;
task = NULL;
MOSEKCALL(res, MSK_makeenv(&env, NULL));
MOSEKCALL(res, MSK_maketask(env, 0, 0, &task));
MOSEKCALL(res, MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr));

/* Total budget */
rtemp = w;
for (j = 0; j < n; ++j)
    rtemp += x0[j];

/* Constraints. */
MOSEKCALL(res, MSK_appendcons(task, 1 + n));

/* Total budget constraint - set bounds  $l^c = u^c$  */
MOSEKCALL(res, MSK_putconbound(task, 0, MSK_BK_FX, rtemp, rtemp));
sprintf(buf, "%s", "budget");
MOSEKCALL(res, MSK_putconname(task, 0, buf));

/* The remaining constraints  $GT * x - t = 0$  - set bounds  $l^c = u^c$  */
for (i = 0; i < n; ++i)
{
    MOSEKCALL(res, MSK_putconbound(task, 1 + i, MSK_BK_FX, 0.0, 0.0));
    sprintf(buf, "GT[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + i, buf));
}

/* Variables. */
MOSEKCALL(res, MSK_appendvars(task, 1 + 2 * n));

offsetx = 0; /* Offset of variable  $x$  into the API variable. */
offsets = n; /* Offset of variable  $x$  into the API variable. */
offsett = n + 1; /* Offset of variable  $t$  into the API variable. */

/*  $x$  variables. */
for (j = 0; j < n; ++j)
{
    /* Return of asset  $j$  in the objective */
    MOSEKCALL(res, MSK_putcj(task, offsetx + j, mu[j]));
    /* Coefficients in the first row of  $A$  */
    MOSEKCALL(res, MSK_putaij(task, 0, offsetx + j, 1.0));
    /* No short-selling -  $x^l = 0$ ,  $x^u = \text{inf}$  */
    MOSEKCALL(res, MSK_putvarbound(task, offsetx + j, MSK_BK_LO, 0.0, MSK_INFINITY));
    sprintf(buf, "x[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsetx + j, buf));
}

/*  $s$  variable is a constant equal to  $\gamma$ . */
MOSEKCALL(res, MSK_putvarbound(task, offsets + 0, MSK_BK_FX, gamma, gamma));
sprintf(buf, "s");
MOSEKCALL(res, MSK_putvarname(task, offsets + 0, buf));

/*  $t$  variables ( $t = GT * x$ ). */
for (j = 0; j < n; ++j)
{
    /* Copying the  $GT$  matrix in the appropriate block of  $A$  */

```

```

for (k = 0; k < n; ++k)
    if ( GT[k][j] != 0.0 )
        MOSEKCALL(res, MSK_putaij(task, 1 + k, offsetx + j, GT[k][j]));
/* Diagonal -1 entries in a block of A */
MOSEKCALL(res, MSK_putaij(task, 1 + j, offsett + j, -1.0));
/* Free - no bounds */
MOSEKCALL(res, MSK_putvarbound(task, offsett + j, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY));
sprintf(buf, "t[%d]", 1 + j);
MOSEKCALL(res, MSK_putvarname(task, offsett + j, buf));
}

if ( res == MSK_RES_OK )
{
    /* Define the cone spanned by variables (s, t), i.e. dimension = n + 1 */
    MSKint32t *sub = (MSKint32t *) MSK_calloc(task, n + 1, sizeof(MSKint32t));

    if ( sub )
    {
        /* Copy indices of variables involved in the conic constraint */
        sub[0] = offsets + 0;
        for (j = 0; j < n; ++j)
            sub[j + 1] = offsett + j;

        MOSEKCALL(res, MSK_appendcone(task, MSK_CT_QUAD, 0.0, n + 1, sub));
        MOSEKCALL(res, MSK_putconename(task, 0, "stddev"));

        MSK_freetask(task, sub);
    }
    else
        res = MSK_RES_ERR_SPACE;
}

MOSEKCALL(res, MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE));

#if 0
/* No log output */
MOSEKCALL(res, MSK_putintparam(task, MSK_IPAR_LOG, 0));
#endif

#if 0
/* Dump the problem to a human readable OPF file. */
MOSEKCALL(res, MSK_writedata(task, "dump.opf"));
#endif

MOSEKCALL(res, MSK_optimizetrm(task, &trmcode));

#if 1
/* Display the solution summary for quick inspection of results. */
MSK_solutionsummary(task, MSK_STREAM_MSG);
#endif

if ( res == MSK_RES_OK )
{
    expret = 0.0;
    stddev = 0.0;

    /* Read the x variables one by one and compute expected return. */
    /* Can also be obtained as value of the objective. */
    for (j = 0; j < n; ++j)
    {
        MOSEKCALL(res, MSK_getxxslice(task, MSK_SOL_ITR, offsetx + j, offsetx + j + 1, &xj));
    }
}

```

(continued from previous page)

```
    expret += mu[j] * xj;
}

/* Read the value of s. This should be gamma. */
MOSEKCALL(res, MSK_getxxslice(task, MSK_SOL_ITR, offsets + 0, offsets + 1, &stddev));

printf("\nExpected return %e for gamma %e\n", expret, stddev);
}

if ( task != NULL )
    MSK_deletetask(&task);

if ( env != NULL )
    MSK_deleteenv(&env);

return ( 0 );
}
```

The above code produces the result:

Listing 11.2: Output from the solver.

```
Interior-point solution summary
Problem status : PRIMAL_AND_DUAL_FEASIBLE
Solution status : OPTIMAL
Primal.  obj: 7.4766507287e-02    nrm: 1e+00    Viol.  con: 2e-08    var: 0e+00    cones: 2e-
↪08
Dual.    obj: 7.476654102e-02    nrm: 3e-01    Viol.  con: 0e+00    var: 3e-08    cones: 0
↪0e+00

Expected return 7.476651e-02 for gamma 5.000000e-02
```

Source code comments

The source code is a direct translation of the model (11.5) using the explicit block matrix specification (11.8) but a few comments are nevertheless in place.

The code uses a macro which can be defined as follows:

```
#define MOSEKCALL(_r,_call)  ( (_r)==MSK_RES_OK ? ( (_r) = (_call) ) : ( (_r) = (_r) ) );
```

and then used as a method of hiding multiple if statements and hence making the code more compact:

```
MOSEKCALL(res, MSK_optimize(task));

//is the same as
if ( res == MSK_RES_OK )
    res = MSK_optimize(task);
```

In the lines

```
offsetx = 0;  /* Offset of variable x into the API variable. */
offsets = n;  /* Offset of variable x into the API variable. */
offsett = n + 1; /* Offset of variable t into the API variable. */
```

offsets into the **MOSEK** API variable are stored as in Table 11.1. The code

```
for (j = 0; j < n; ++j)
{
    /* Return of asset j in the objective */
    MOSEKCALL(res, MSK_putcj(task, offsetx + j, mu[j]));
    /* Coefficients in the first row of A */
    MOSEKCALL(res, MSK_putaij(task, 0, offsetx + j, 1.0));
}
```

(continues on next page)

(continued from previous page)

```
/* No short-selling -  $x^l = 0$ ,  $x^u = \text{inf}$  */
MOSEKCALL(res, MSK_putvarbound(task, offsetx + j, MSK_BK_LO, 0.0, MSK_INFINITY));
sprintf(buf, "x[%d]", 1 + j);
MOSEKCALL(res, MSK_putvarname(task, offsetx + j, buf));
}
```

sets up the data for x variables. For instance

```
/* Return of asset  $j$  in the objective */
MOSEKCALL(res, MSK_putcj(task, offsetx + j, mu[j]));
```

inputs the objective coefficients for the x variables. Moreover, the code

```
sprintf(buf, "x[%d]", 1 + j);
MOSEKCALL(res, MSK_putvarname(task, offsetx + j, buf));
```

assigns meaningful names to the API variables. This is not needed but it makes debugging easier.

Note that the solution values are only accessed for the interesting variables; for instance the auxiliary variable t is omitted from this process.

Debugging Tips

Implementing an optimization model in Optimizer API for C can be error-prone. In order to check the code for accidental errors it is very useful to dump the problem to a file in a human readable form for visual inspection. The line

```
/* Dump the problem to a human readable OPF file. */
MOSEKCALL(res, MSK_writedata(task, "dump.opf"));
```

does that and it produces a file with the content:

Listing 11.3: Problem (11.5) stored in OPF format.

```
[comment]
  Written by MOSEK version 8.1.0.24
  Date 11-09-17
  Time 14:34:24
[/comment]

[hints]
[hint NUMVAR] 7 [/hint]
[hint NUMCON] 4 [/hint]
[hint NUMANZ] 12 [/hint]
[hint NUMQNZ] 0 [/hint]
[hint NUMCONE] 1 [/hint]
[/hints]

[variables disallow_new_variables]
  'x[1]' 'x[2]' 'x[3]' s 't[1]'
  't[2]' 't[3]'
[/variables]

[objective maximize]
  1.073e-01 'x[1]' + 7.37e-02 'x[2]' + 6.270000000000001e-02 'x[3]'
[/objective]

[constraints]
[con 'budget']  'x[1]' + 'x[2]' + 'x[3]' = 1e+00 [/con]
[con 'GT[1]']   1.667e-01 'x[1]' + 2.32e-02 'x[2]' + 1.3e-03 'x[3]' - 't[1]' = 0e+00 [/con]
[con 'GT[2]']   1.033e-01 'x[2]' - 2.2e-03 'x[3]' - 't[2]' = 0e+00 [/con]
[con 'GT[3]']   3.38e-02 'x[3]' - 't[3]' = 0e+00 [/con]
[/constraints]
```

(continues on next page)

```
[bounds]
[b] 0e+00      <= 'x[1]', 'x[2]', 'x[3]' [/b]
[b]          s = 5e-02 [/b]
[b]          't[1]', 't[2]', 't[3]' free [/b]
[cone quad 'stddev'] s, 't[1]', 't[2]', 't[3]' [/cone]
[/bounds]
```

Since the API variables have been given meaningful names it is easy to verify by hand that the model is correct.

11.1.2 The efficient Frontier

The portfolio computed by the Markowitz model is efficient in the sense that there is no other portfolio giving a strictly higher return for the same amount of risk. An efficient portfolio is also sometimes called a Pareto optimal portfolio. Clearly, an investor should only invest in efficient portfolios and therefore it may be relevant to present the investor with all efficient portfolios so the investor can choose the portfolio that has the desired tradeoff between return and risk.

Given a nonnegative α the problem

$$\begin{aligned} & \text{maximize} && \mu^T x - \alpha x^T \Sigma x \\ & \text{subject to} && e^T x = w + e^T x^0, \\ & && x \geq 0. \end{aligned} \tag{11.9}$$

is one standard way to trade the expected return against penalizing variance. Note that, in contrast to the previous example, we explicitly use the variance ($\|G^T x\|_2^2$) rather than standard deviation ($\|G^T x\|_2$), therefore the conic model includes a rotated quadratic cone:

$$\begin{aligned} & \text{maximize} && \mu^T x - \alpha s \\ & \text{subject to} && e^T x = w + e^T x^0, \\ & && G^T x - t = 0, \\ & && u = 0.5, \\ & && (s, u, t) \in Q_r^{n+2} \quad (\text{evaluates to } s \geq \|G^T x\|_2^2 = x^T \Sigma x), \\ & && x \geq 0. \end{aligned} \tag{11.10}$$

Ideally the problem (11.9) should be solved for all values $\alpha \geq 0$ but in practice it is impossible. Using the example data as before, the optimal values of return and variance for several values of α are shown below:

Listing 11.4: Results obtained solving problem (11.9) for different values of α .

alpha	exp ret	variance
0.000e+00	1.073e-01	2.779e-02
2.500e-01	1.073e-01	2.779e-02
5.000e-01	1.073e-01	2.779e-02
7.500e-01	1.057e-01	2.554e-02
1.000e+00	9.965e-02	1.851e-02
1.500e+00	8.802e-02	8.850e-03
2.000e+00	8.213e-02	5.415e-03
2.500e+00	7.860e-02	3.826e-03
3.000e+00	7.625e-02	2.963e-03
3.500e+00	7.457e-02	2.442e-03
4.000e+00	7.331e-02	2.104e-03
4.500e+00	7.232e-02	1.873e-03

Source code example

The example code in [Listing 11.5](#) demonstrates how to compute the efficient portfolios for several values of α . The code is mostly similar to the one in [Sec. 11.1.1](#), except the problem is re-optimized in a loop for varying α .

Listing 11.5: Code implementing model (11.9).

```
#include <math.h>
#include <stdio.h>

#include "mosek.h"

#define MOSEKCALL(_r,_call)  if ( (_r)==MSK_RES_OK ) (_r) = (_call)
#define LOGLEVEL             0

static void MSKAPI printstr(void      *handle,
                           const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char **argv)
{
    char          buf[128];
    const MSKint32t n      = 3,
                  numalpha = 12;
    const double  mu[]     = {0.1073, 0.0737, 0.0627},
                  x0[3]    = {0.0, 0.0, 0.0},
                  w        = 1.0,
                  alphas[12] = {0.0, 0.25, 0.5, 0.75, 1.0, 1.5, 2.0, 2.5, 3.0, 3.5, 4.0, 4.5},
                  GT[][3]  = {{0.1667, 0.0232, 0.0013},
                              {0.0000, 0.1033, -0.0022},
                              {0.0000, 0.0000, 0.0338}
                              };

    MSKenv_t      env;
    MSKint32t     k, i, j, offsetx, offsets, offsett, offsetu;
    MSKrescodeee  res = MSK_RES_OK, lres;
    MSKtask_t     task;
    MSKrealt      xj;
    MSKsolstae    solsta;

    /* Initial setup. */
    env = NULL;
    task = NULL;

    /* Replace "" with NULL in production. */
    MOSEKCALL(res, MSK_makeenv(&env, ""));

    MOSEKCALL(res, MSK_maketask(env, 0, 0, &task));
    MOSEKCALL(res, MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr));

    /* Constraints. */
    MOSEKCALL(res, MSK_appendcons(task, 1 + n));
    MOSEKCALL(res, MSK_putconbound(task, 0, MSK_BK_FX, 1.0, 1.0));
    sprintf(buf, "%s", "budget");
    MOSEKCALL(res, MSK_putconname(task, 0, buf));

    for (i = 0; i < n; ++i)
    {
        MOSEKCALL(res, MSK_putconbound(task, 1 + i, MSK_BK_FX, 0.0, 0.0));
        sprintf(buf, "GT[%d]", 1 + i);
        MOSEKCALL(res, MSK_putconname(task, 1 + i, buf));
    }

    /* Variables. */
    MOSEKCALL(res, MSK_appendvars(task, 2 + 2 * n));
```

(continues on next page)

(continued from previous page)

```
offsetx = 0;  /* Offset of variable x into the API variable. */
offsets = n;  /* Offset of variable s into the API variable. */
offsett = n + 1; /* Offset of variable t into the API variable. */
offsetu = 2*n + 1; /* Offset of variable u into the API variable. */

/* x variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putcj(task, offsetx + j, mu[j]));
    MOSEKCALL(res, MSK_putaij(task, 0, offsetx + j, 1.0));
    for (k = 0; k < n; ++k)
        if (GT[k][j] != 0.0)
            MOSEKCALL(res, MSK_putaij(task, 1 + k, offsetx + j, GT[k][j]));

    MOSEKCALL(res, MSK_putvarbound(task, offsetx + j, MSK_BK_LO, 0.0, MSK_INFINITY));
    sprintf(buf, "x[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsetx + j, buf));
}

/* s variable. */
MOSEKCALL(res, MSK_putvarbound(task, offsets + 0, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY));
sprintf(buf, "s");
MOSEKCALL(res, MSK_putvarname(task, offsets + 0, buf));

/* t variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putaij(task, 1 + j, offsett + j, -1.0));
    MOSEKCALL(res, MSK_putvarbound(task, offsett + j, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY));
    sprintf(buf, "t[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsett + j, buf));
}

/* u variable. */
MOSEKCALL(res, MSK_putvarbound(task, offsetu + 0, MSK_BK_FX, 0.5, 0.5));
sprintf(buf, "u");
MOSEKCALL(res, MSK_putvarname(task, offsetu + 0, buf));

if (res == MSK_RES_OK)
{
    /* sub should be n+2 long i.e. the dimension of the cone. */
    MSKint32t *sub = (MSKint32t *) MSK_calloc(task, n + 2, sizeof(MSKint32t));

    if (sub)
    {
        sub[0] = offsets + 0;
        sub[1] = offsetu + 0;
        for (j = 0; j < n; ++j)
            sub[j + 2] = offsett + j;

        MOSEKCALL(res, MSK_appendcone(task, MSK_CT_RQUAD, 0.0, n + 2, sub));
        MOSEKCALL(res, MSK_putconename(task, 0, "variance"));

        MSK_freetask(task, sub);
    }
    else
        res = MSK_RES_ERR_SPACE;
}

MOSEKCALL(res, MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE));
```

(continues on next page)

```

/* Set the log level */
MOSEKCALL(res, MSK_putintparam(task, MSK_IPAR_LOG, LOGLEVEL));

printf("%-12s  %-12s  %-12s\n", "alpha", "exp ret", "variance");

for (k = 0; k < numalpha && res==MSK_RES_OK; ++k)
{
    const double alpha = alphas[k];
    MSKrescodee trmcode;

    /* Sets the objective function coefficient for s. */
    MOSEKCALL(res, MSK_putcj(task, offsets + 0, -alpha));

    MOSEKCALL(res, MSK_optimizetrm(task, &trmcode));

    MOSEKCALL(res, MSK_getsolsta(task, MSK_SOL_ITR, &solsta));

    if (solsta == MSK_SOL_STA_OPTIMAL)
    {
        double expret = 0.0,
            stddev;

        for (j = 0; j < n; ++j)
        {
            MOSEKCALL(res, MSK_getxxslice(task, MSK_SOL_ITR, offsetx + j, offsetx + j + 1, &xj));
            expret += mu[j] * xj;
        }

        MOSEKCALL(res, MSK_getxxslice(task, MSK_SOL_ITR, offsets + 0, offsets + 1, &stddev));

        printf("%-12.3e  %-12.3e  %-12.3e\n", alpha, expret, stddev);
    }
    else
    {
        printf("An error occurred when solving for alpha=%e\n", alpha);
    }
}
lres = MSK_deletetask(&task);
res = res==MSK_RES_OK ? lres : res;

lres = MSK_deleteenv(&env);
res = res==MSK_RES_OK ? lres : res;

return ( res );
}

```

11.1.3 Factor model and efficiency

In practice it is often important to solve the portfolio problem very quickly. Therefore, in this section we discuss how to improve computational efficiency at the modeling stage.

The computational cost is of course to some extent dependent on the number of constraints and variables in the optimization problem. However, in practice a more important factor is the sparsity: the number of nonzeros used to represent the problem. Indeed it is often better to focus on the number of nonzeros in G see (11.2) and try to reduce that number by for instance changing the choice of G .

In other words if the computational efficiency should be improved then it is always good idea to start with focusing at the covariance matrix. As an example assume that

$$\Sigma = D + VV^T$$

where D is a positive definite diagonal matrix. Moreover, V is a matrix with n rows and p columns. Such a model for the covariance matrix is called a factor model and usually p is much smaller than n .

In practice p tends to be a small number independent of n , say less than 100.

One possible choice for G is the Cholesky factorization of Σ which requires storage proportional to $n(n+1)/2$. However, another choice is

$$G^T = \begin{bmatrix} D^{1/2} \\ V^T \end{bmatrix}$$

because then

$$GG^T = D + VV^T.$$

This choice requires storage proportional to $n + pn$ which is much less than for the Cholesky choice of G . Indeed assuming p is a constant storage requirements are reduced by a factor of n .

The example above exploits the so-called factor structure and demonstrates that an alternative choice of G may lead to a significant reduction in the amount of storage used to represent the problem. This will in most cases also lead to a significant reduction in the solution time.

The lesson to be learned is that it is important to investigate how the covariance matrix is formed. Given this knowledge it might be possible to make a special choice for G that helps reducing the storage requirements and enhance the computational efficiency. More details about this process can be found in [And13].

11.1.4 Slippage Cost

The basic Markowitz model assumes that there are no costs associated with trading the assets and that the returns of the assets are independent of the amount traded. Neither of those assumptions is usually valid in practice. Therefore, a more realistic model is

$$\begin{aligned} & \text{maximize} && \mu^T x \\ & \text{subject to} && e^T x + \sum_{j=1}^n C_j |x_j - x_j^0| = w + e^T x^0, \\ & && x^T \Sigma x \leq \gamma^2, \\ & && x \geq 0, \end{aligned} \tag{11.11}$$

where the function

$$C_j |x_j - x_j^0|$$

specifies the transaction costs when the holding of asset j is changed from its initial value. In the next two sections we show two different variants of this problem with two nonlinear cost functions T .

11.1.5 Market Impact Costs

If the initial wealth is fairly small and no short selling is allowed, then the holdings will be small and the traded amount of each asset must also be small. Therefore, it is reasonable to assume that the prices of the assets are independent of the amount traded. However, if a large volume of an asset is sold or purchased, the price, and hence return, can be expected to change. This effect is called market impact costs. It is common to assume that the market impact cost for asset j can be modeled by

$$C_j = m_j \sqrt{|x_j - x_j^0|}$$

where m_j is a constant that is estimated in some way by the trader. See [GK00] [p. 452] for details. Hence, we have

$$C_j(x_j - x_j^0) = m_j |x_j - x_j^0| \sqrt{|x_j - x_j^0|} = m_j |x_j - x_j^0|^{3/2}.$$

From the Modeling Cookbook we know that $c \geq z^{3/2}$ can be modeled directly using the power cone $\mathcal{P}_3^{2/3, 1/3}$:

$$\{(c, z) : c \geq z^{3/2}, z \geq 0\} = \{(c, z) : (c, 1, z) \in \mathcal{P}_3^{2/3, 1/3}\}$$

Hence, it follows that we can write the model as

$$\begin{aligned} z_j &= |x_j - x_j^0|, \\ (c_j, 1, z_j) &\in \mathcal{P}_3^{2/3, 1/3}, \\ \sum_{j=1}^n C_j |x_j - x_j^0| &= \sum_{j=1}^n c_j m_j. \end{aligned}$$

Unfortunately this set of constraints is nonconvex due to the constraint

$$z_j = |x_j - x_j^0| \quad (11.12)$$

but in many cases the constraint may be replaced by the relaxed constraint

$$z_j \geq |x_j - x_j^0|, \quad (11.13)$$

which is equivalent to

$$\begin{aligned} z_j &\geq x_j - x_j^0, \\ z_j &\geq -(x_j - x_j^0). \end{aligned} \quad (11.14)$$

For instance if the universe of assets contains a risk free asset then

$$z_j > |x_j - x_j^0| \quad (11.15)$$

cannot hold for an optimal solution.

If the optimal solution has the property (11.15) then the market impact cost within the model is larger than the true market impact cost and hence money are essentially considered garbage and removed by generating transaction costs. This may happen if a portfolio with very small risk is requested because the only way to obtain a small risk is to get rid of some of the assets by generating transaction costs. We generally assume that this is not the case and hence the models (11.12) and (11.13) are equivalent.

The above observations lead to

$$\begin{aligned} &\text{maximize} && \mu^T x \\ &\text{subject to} && e^T x + m^T c = w + e^T x^0, \\ & && [\gamma; G^T x] \in \mathcal{Q}^{n+1}, \\ & && z_j \geq x_j - x_j^0, \quad j = 1, \dots, n, \\ & && z_j \geq x_j^0 - x_j, \quad j = 1, \dots, n, \\ & && (c_j, 1, z_j) \in \mathcal{P}_3^{2/3, 1/3}, \quad j = 1, \dots, n, \\ & && x \geq 0. \end{aligned} \quad (11.16)$$

The revised budget constraint

$$e^T x + m^T c = w + e^T x^0$$

specifies that the initial wealth covers the investment and the transaction costs. It should be mentioned that transaction costs of the form

$$t_j \geq z_j^p$$

where $p > 1$ is a real number can be modeled with the power cone as

$$(t_j, 1, z_j) \in \mathcal{P}_3^{1/p, 1-1/p}.$$

See [Modeling Cookbook](#) for details.

Creating a matrix formulation

One more reformulation of (11.16) is needed to bring it to the standard form (11.4).

$$\begin{aligned}
& \text{maximize} && \mu^T x \\
& \text{subject to} && e^T x + m^T c = w + e^T x^0, \\
& && G^T x - t = 0, \\
& && z_j - x_j \geq -x_j^0, & j = 1, \dots, n, \\
& && z_j + x_j \geq x_j^0, & j = 1, \dots, n, \\
& && (s, t) \in \mathcal{Q}^{n+1}, \\
& && (c_j, f_j, z_j) \in \mathcal{P}_3^{2/3, 1/3}, & j = 1, \dots, n, \\
& && x \geq 0, \\
& && f_j = 1, & j = 1, \dots, n, \\
& && s = \gamma,
\end{aligned} \tag{11.17}$$

where $f \in \mathbb{R}^n$ is an additional variable representing the unused coordinate in the power cone. The formulation (11.17) is not the most compact possible, but it is easy to implement. **MOSEK** presolve will automatically simplify it.

The first step in developing the implementation is to choose an ordering of the variables. We will choose the following ordering:

$$\hat{x} = [x; s; t; c; z; f]$$

Table 11.2 shows the mapping between the \hat{x} vector and the model variables.

Table 11.2: Storage layout for \hat{x}

Variable	Length	Offset
x	n	0
s	1	n
t	n	$n + 1$
c	n	$2n + 1$
z	n	$3n + 1$
f	n	$4n + 1$

The next step is to consider how the linear constraint matrix A and the remaining data vectors are laid out. Reusing the idea in Sec. 11.1.1 we can write the data in block matrix form and read off all the required coordinates. This extension of the code setting up the constraint $G^T x - t = 0$ from Sec. 11.1.1 is shown below.

Source code example

The example code in Listing 11.6 demonstrates how to implement the model (11.17).

Listing 11.6: Code implementing model (11.17).

```

#include <math.h>
#include <stdio.h>

#include "mosek.h"

#define MOSEKCALL(_r,_call) if ( (_r)==MSK_RES_OK ) (_r) = (_call)

static void MSKAPI printstr(void *handle,
                             const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char **argv)
{

```

(continues on next page)

```

char          buf[128];
const MSKint32t n      = 3;
const double   w       = 1.0,
              x0[]     = {0.0, 0.0, 0.0},
              gamma    = 0.05,
              mu[]      = {0.1073, 0.0737, 0.0627},
              m[]       = {0.01, 0.01, 0.01},
              GT[][3]  = {{0.1667, 0.0232, 0.0013},
                          {0.0000, 0.1033, -0.0022},
                          {0.0000, 0.0000, 0.0338}
                          };

double        expret,
              stddev,
              xj;
MSKenv_t      env;
MSKint32t     k, i, j,
              offsetx, offsets, offsett, offsetc,
              offsetz, offsetf;
MSKrescodee   res = MSK_RES_OK, trmcode;
MSKtask_t     task;

/* Initial setup. */
env = NULL;
task = NULL;
MOSEKCALL(res, MSK_makeenv(&env, NULL));
MOSEKCALL(res, MSK_maketask(env, 0, 0, &task));
MOSEKCALL(res, MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr));

/* Constraints. */
MOSEKCALL(res, MSK_appendcons(task, 1 + 3 * n));
MOSEKCALL(res, MSK_putconbound(task, 0, MSK_BK_FX, w, w));
sprintf(buf, "%s", "budget");
MOSEKCALL(res, MSK_putconname(task, 0, buf));

for (i = 0; i < n; ++i)
{
    MOSEKCALL(res, MSK_putconbound(task, 1 + i, MSK_BK_FX, 0.0, 0.0));
    sprintf(buf, "GT[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + i, buf));
}

for (i = 0; i < n; ++i)
{
    MOSEKCALL(res, MSK_putconbound(task, 1 + n + i, MSK_BK_LO, -x0[i], MSK_INFINITY));
    sprintf(buf, "zabs1[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + n + i, buf));
}

for (i = 0; i < n; ++i)
{
    MOSEKCALL(res, MSK_putconbound(task, 1 + 2 * n + i, MSK_BK_LO, x0[i], MSK_INFINITY));
    sprintf(buf, "zabs2[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + 2 * n + i, buf));
}

/* Offsets of variables into the (serialized) API variable. */
offsetx = 0;
offsets = n;
offsett = n + 1;
offsetc = 2 * n + 1;
offsetz = 3 * n + 1;

```

```

offsetf = 4 * n + 1;

/* Variables. */
MOSEKCALL(res, MSK_appendvars(task, 5 * n + 1));

/* x variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putcj(task, offsetx + j, mu[j]));
    MOSEKCALL(res, MSK_putaij(task, 0, offsetx + j, 1.0));
    for (k = 0; k < n; ++k)
        if (GT[k][j] != 0.0)
            MOSEKCALL(res, MSK_putaij(task, 1 + k, offsetx + j, GT[k][j]));
    MOSEKCALL(res, MSK_putaij(task, 1 + n + j, offsetx + j, -1.0));
    MOSEKCALL(res, MSK_putaij(task, 1 + 2 * n + j, offsetx + j, 1.0));

    MOSEKCALL(res, MSK_putvarbound(task, offsetx + j, MSK_BK_LO, 0.0, MSK_INFINITY));
    sprintf(buf, "x[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsetx + j, buf));
}

/* s variable. */
MOSEKCALL(res, MSK_putvarbound(task, offsets + 0, MSK_BK_FX, gamma, gamma));
sprintf(buf, "s");
MOSEKCALL(res, MSK_putvarname(task, offsets + 0, buf));

/* t variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putaij(task, 1 + j, offsett + j, -1.0));
    MOSEKCALL(res, MSK_putvarbound(task, offsett + j, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY));
    sprintf(buf, "t[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsett + j, buf));
}

/* c variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putaij(task, 0, offsetc + j, m[j]));
    MOSEKCALL(res, MSK_putvarbound(task, offsetc + j, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY));
    sprintf(buf, "c[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsetc + j, buf));
}

/* z variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putaij(task, 1 + 1 * n + j, offsetz + j, 1.0));
    MOSEKCALL(res, MSK_putaij(task, 1 + 2 * n + j, offsetz + j, 1.0));
    MOSEKCALL(res, MSK_putvarbound(task, offsetz + j, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY));
    sprintf(buf, "z[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsetz + j, buf));
}

/* f variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putvarbound(task, offsetf + j, MSK_BK_FX, 1.0, 1.0));
    sprintf(buf, "f[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsetf + j, buf));
}

```



```

if (res == MSK_RES_OK)
{
    /* sub should be n+1 long i.e. the dimension of the cone. */
    MSKint32t *sub = (MSKint32t *) MSK_calloc(task, 3 >= n + 1 ? 3 : n + 1,
↪sizeof(MSKint32t));

    if (sub)
    {
        /* Add quadratic cone */
        sub[0] = offsets + 0;
        for (j = 0; j < n; ++j)
            sub[j + 1] = offsett + j;

        MOSEKCALL(res, MSK_appendcone(task, MSK_CT_QUAD, 0.0, n + 1, sub));
        MOSEKCALL(res, MSK_putconename(task, 0, "stddev"));

        /* Add power cones */
        for (k = 0; k < n; ++k)
        {
            sub[0] = offsetc + k, sub[1] = offsetf + k, sub[2] = offsetz + k;
            MOSEKCALL(res, MSK_appendcone(task, MSK_CT_PPOW, 2.0/3.0, 3, sub));
            sprintf(buf, "trans[%d]", 1 + k);
            MOSEKCALL(res, MSK_putconename(task, 1 + k, buf));
        }

        MSK_freetask(task, sub);
    }
    else
        res = MSK_RES_ERR_SPACE;
}

MOSEKCALL(res, MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE));

#if 0
    /* no log output. */
    MOSEKCALL(res, MSK_putintparam(task, MSK_IPAR_LOG, 0));
#endif

#if 0
    /* Dump the problem to a human readable OPF file. */
    MOSEKCALL(res, MSK_writedata(task, "dump.opf"));
#endif

MOSEKCALL(res, MSK_optimizetrm(task, &trmcode));

/* Display the solution summary for quick inspection of results. */
#if 1
    MSK_solutionsummary(task, MSK_STREAM_MSG);
#endif

if (res == MSK_RES_OK)
{
    expret = 0.0;
    stddev = 0.0;

    for (j = 0; j < n; ++j)
    {
        MOSEKCALL(res, MSK_getxxslice(task, MSK_SOL_ITR, offsetx + j, offsetx + j + 1, &xj));
        expret += mu[j] * xj;
    }
}

```

(continued from previous page)

```
MOSEKCALL(res, MSK_getxxslice(task, MSK_SOL_ITR, offsets + 0, offsets + 1, &stddev));

printf("\nExpected return %e for gamma %e\n", expret, stddev);
}

MSK_deletetask(&task);
MSK_deleteenv(&env);

return (0);
}
```

The example code above produces the result

```
Interior-point solution summary
Problem status : PRIMAL_AND_DUAL_FEASIBLE
Solution status : OPTIMAL
Primal.  obj: 7.4390639578e-02    nrm: 1e+00    Viol.  con: 1e-08    var: 0e+00    cones: 7e-
↪09
Dual.    obj: 7.4390755614e-02    nrm: 3e-01    Viol.  con: 1e-19    var: 3e-08    cones:↪
↪0e+00

Expected return 7.439064e-02 for gamma 5.000000e-02
```

If the problem is dumped to an OPF file, it has the following content.

Listing 11.7: OPF file for problem (11.17).

```
[comment]
  Written by MOSEK version 9.0.0.31
  Date 10-01-18
  Time 12:10:24
[/comment]

[hints]
[hint NUMVAR] 16 [/hint]
[hint NUMCON] 10 [/hint]
[hint NUMANZ] 27 [/hint]
[hint NUMQNZ] 0 [/hint]
[hint NUMCONE] 4 [/hint]
[/hints]

[variables disallow_new_variables]
'x[1]' 'x[2]' 'x[3]' s 't[1]'
't[2]' 't[3]' 'c[1]' 'c[2]' 'c[3]'
'z[1]' 'z[2]' 'z[3]' 'f[1]' 'f[2]'
'f[3]'
[/variables]

[objective maximize]
1.073e-01 'x[1]' + 7.37e-02 'x[2]' + 6.2700000000000001e-02 'x[3]'
[/objective]

[constraints]
[con 'budget'] 'x[1]' + 'x[2]' + 'x[3]' + 1e-02 'c[1]' + 1e-02 'c[2]'
+ 1e-02 'c[3]' = 1e+00 [/con]
[con 'GT[1]'] 1.667e-01 'x[1]' + 2.32e-02 'x[2]' + 1.3e-03 'x[3]' - 't[1]' = 0e+00 [/con]
[con 'GT[2]'] 1.033e-01 'x[2]' - 2.2e-03 'x[3]' - 't[2]' = 0e+00 [/con]
[con 'GT[3]'] 3.38e-02 'x[3]' - 't[3]' = 0e+00 [/con]
[con 'zabs1[1]'] 0e+00 <= - 'x[1]' + 'z[1]' [/con]
[con 'zabs1[2]'] 0e+00 <= - 'x[2]' + 'z[2]' [/con]
[con 'zabs1[3]'] 0e+00 <= - 'x[3]' + 'z[3]' [/con]
```

(continues on next page)

```

[con 'zabs2[1]' 0e+00 <= 'x[1]' + 'z[1]' [/con]
[con 'zabs2[2]' 0e+00 <= 'x[2]' + 'z[2]' [/con]
[con 'zabs2[3]' 0e+00 <= 'x[3]' + 'z[3]' [/con]
[/constraints]

[bounds]
[b] 0e+00 <= 'x[1]', 'x[2]', 'x[3]' [/b]
[b] s = 5e-02 [/b]
[b] 't[1]', 't[2]', 't[3]', 'c[1]', 'c[2]', 'c[3]' free [/b]
[b] 'z[1]', 'z[2]', 'z[3]' free [/b]
[b] 'f[1]', 'f[2]', 'f[3]' = 1e+00 [/b]
[cone quad 'stddev'] s, 't[1]', 't[2]', 't[3]' [/cone]
[cone ppow '6.666666666666666e-01' 'trans[1]' 'c[1]', 'f[1]', 'z[1]' [/cone]
[cone ppow '6.666666666666666e-01' 'trans[2]' 'c[2]', 'f[2]', 'z[2]' [/cone]
[cone ppow '6.666666666666666e-01' 'trans[3]' 'c[3]', 'f[3]', 'z[3]' [/cone]
[/bounds]

```

The file verifies that the correct problem has been set up.

11.1.6 Transaction Costs

Now assume there is a cost associated with trading asset j given by

$$T_j(\Delta x_j) = \begin{cases} 0, & \Delta x_j = 0, \\ f_j + g_j |\Delta x_j|, & \text{otherwise.} \end{cases}$$

Here Δx_j is the change in the holding of asset j i.e.

$$\Delta x_j = x_j - x_j^0.$$

Hence, whenever asset j is traded we pay a fixed setup cost f_j and a variable cost of g_j per unit traded. This sort of cost function can be modeled using mixed-integer optimization, in particular using a binary variable y_j to indicate if asset j is traded. Given the assumptions about transaction costs in this section problem (11.11) may be formulated as

$$\begin{aligned}
& \text{maximize} && \mu^T x \\
& \text{subject to} && e^T x + f^T y + g^T z = w + e^T x^0, \\
& && [\gamma; G^T x] \in \mathcal{Q}^{n+1}, \\
& && z_j \geq x_j - x_j^0, & j = 1, \dots, n, \\
& && z_j \geq x_j^0 - x_j, & j = 1, \dots, n, \\
& && z_j \leq U_j y_j, & j = 1, \dots, n, \\
& && y_j \in \{0, 1\}, & j = 1, \dots, n, \\
& && x \geq 0.
\end{aligned} \tag{11.18}$$

First observe that

$$z_j \geq |x_j - x_j^0| = |\Delta x_j|.$$

Here U_j is some a priori chosen upper bound on the amount of trading in asset j and therefore if $z_j > 0$ then $y_j = 1$ has to be the case. This implies that the transaction cost for asset j is given by

$$f_j y_j + g_j z_j.$$

In our problem a safe bound for each U_j is the total initial wealth $w + e^T x^0$, however knowing a tighter bound may lead to shorter solution times.

Creating a matrix formulation

One more reformulation of (11.18) is needed to bring it to the standard form (11.4).

$$\begin{aligned}
 & \text{maximize} && \mu^T x \\
 & \text{subject to} && e^T x + f^T y + g^T z = w + e^T x^0, \\
 & && G^T x - t = 0, \\
 & && z_j - x_j \geq -x_j^0, & j = 1, \dots, n, \\
 & && z_j + x_j \geq x_j^0, & j = 1, \dots, n, \\
 & && (s, t) \in \mathcal{Q}^{n+1}, \\
 & && z_j - U_j y_j \leq 0, & j = 1, \dots, n, \\
 & && x \geq 0, \\
 & && y_j \in [0, 1], & j = 1, \dots, n, \\
 & && y_j \in \mathbb{Z}, & j = 1, \dots, n, \\
 & && s = \gamma.
 \end{aligned} \tag{11.19}$$

We will choose the following ordering of variables:

$$\hat{x} = [x; s; t; z; y]$$

Table 11.3 shows the mapping between the \hat{x} vector and the model variables.

Table 11.3: Storage layout for \hat{x}

Variable	Length	Offset
x	n	0
s	1	n
t	n	$n + 1$
z	n	$2n + 1$
y	n	$3n + 1$

The next step is to consider how the linear constraint matrix A and the remaining data vectors are laid out. Reusing the idea in Sec. 11.1.1 we can write the data in block matrix form and read off all the required coordinates. This extension of the code setting up the constraint $G^T x - t = 0$ from Sec. 11.1.1 is shown below.

Example code

The following example code demonstrates how to compute an optimal portfolio when transaction setup costs are included. Note that we are now solving a problem with integer variables, and therefore the solution must be retrieved from *MSK_SOL_ITG* rather than *MSK_SOL_ITR*.

Listing 11.8: Code solving problem (11.18).

```

#include <math.h>
#include <stdio.h>

#include "mosek.h"

#define MOSEKCALL(_r,_call) if ( (_r)==MSK_RES_OK ) (_r) = (_call)

static void MSKAPI printstr(void *handle,
                           const char str[])
{
    printf("%s", str);
} /* printstr */

int main(int argc, const char **argv)
{
    char          buf[128];
    const MSKint32t n      = 3;

```

(continues on next page)

```

const double    w        = 1.0,
                x0[]      = {0.0, 0.0, 0.0},
                gamma     = 0.05,
                mu[]       = {0.1073, 0.0737, 0.0627},
                f[]        = {0.01, 0.01, 0.01},
                g[]        = {0.001, 0.001, 0.001},
                GT[][3]    = {{0.1667, 0.0232, 0.0013},
                              {0.0000, 0.1033, -0.0022},
                              {0.0000, 0.0000, 0.0338}
                              };

double          U,
                expret,
                stddev,
                xj;
MSKenv_t        env;
MSKint32t       k, i, j,
                offsetx, offsety, offsetz, offsetw;
MSKrescodee     res = MSK_RES_OK, trmcode;
MSKtask_t       task;

/* Initial setup. */
env = NULL;
task = NULL;
MOSEKCALL(res, MSK_makeenv(&env, NULL));
MOSEKCALL(res, MSK_maketask(env, 0, 0, &task));
MOSEKCALL(res, MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr));

/* Compute total wealth */
U = w;
for (k = 0; k < n; ++k) U += x0[k];

/* Constraints. */
MOSEKCALL(res, MSK_appendcons(task, 1 + 4 * n));
MOSEKCALL(res, MSK_putconbound(task, 0, MSK_BK_FX, w, w));
sprintf(buf, "%s", "budget");
MOSEKCALL(res, MSK_putconname(task, 0, buf));

for (i = 0; i < n; ++i)
{
    MOSEKCALL(res, MSK_putconbound(task, 1 + i, MSK_BK_FX, 0.0, 0.0));
    sprintf(buf, "GT[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + i, buf));
}

for (i = 0; i < n; ++i)
{
    MOSEKCALL(res, MSK_putconbound(task, 1 + n + i, MSK_BK_LO, -x0[i], MSK_INFINITY));
    sprintf(buf, "zabs1[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + n + i, buf));
}

for (i = 0; i < n; ++i)
{
    MOSEKCALL(res, MSK_putconbound(task, 1 + 2 * n + i, MSK_BK_LO, x0[i], MSK_INFINITY));
    sprintf(buf, "zabs2[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + 2 * n + i, buf));
}

for (i = 0; i < n; ++i)
{
    MOSEKCALL(res, MSK_putconbound(task, 1 + 3 * n + i, MSK_BK_UP, -MSK_INFINITY, 0.0));

```

(continues on next page)

```

    sprintf(buf, "indicator[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + 3 * n + i, buf));
}

/* Offsets of variables into the (serialized) API variable. */
offsetx = 0;
offsets = n;
offsett = n + 1;
offsetz = 2 * n + 1;
offsety = 3 * n + 1;

/* Variables. */
MOSEKCALL(res, MSK_appendvars(task, 4 * n + 1));

/* x variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putcj(task, offsetx + j, mu[j]));
    MOSEKCALL(res, MSK_putaij(task, 0, offsetx + j, 1.0));
    for (k = 0; k < n; ++k)
        if (GT[k][j] != 0.0)
            MOSEKCALL(res, MSK_putaij(task, 1 + k, offsetx + j, GT[k][j]));
    MOSEKCALL(res, MSK_putaij(task, 1 + n + j, offsetx + j, -1.0));
    MOSEKCALL(res, MSK_putaij(task, 1 + 2 * n + j, offsetx + j, 1.0));

    MOSEKCALL(res, MSK_putvarbound(task, offsetx + j, MSK_BK_LO, 0.0, MSK_INFINITY));
    sprintf(buf, "x[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsetx + j, buf));
}

/* s variable. */
MOSEKCALL(res, MSK_putvarbound(task, offsets + 0, MSK_BK_FX, gamma, gamma));
sprintf(buf, "s");
MOSEKCALL(res, MSK_putvarname(task, offsets + 0, buf));

/* t variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putaij(task, 1 + j, offsett + j, -1.0));
    MOSEKCALL(res, MSK_putvarbound(task, offsett + j, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY));
    sprintf(buf, "t[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsett + j, buf));
}

/* z variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putaij(task, 0, offsetz + j, g[j]));
    MOSEKCALL(res, MSK_putaij(task, 1 + 1 * n + j, offsetz + j, 1.0));
    MOSEKCALL(res, MSK_putaij(task, 1 + 2 * n + j, offsetz + j, 1.0));
    MOSEKCALL(res, MSK_putaij(task, 1 + 3 * n + j, offsetz + j, 1.0));
    MOSEKCALL(res, MSK_putvarbound(task, offsetz + j, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY));
    sprintf(buf, "z[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsetz + j, buf));
}

/* y variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putaij(task, 0, offsety + j, f[j]));
    MOSEKCALL(res, MSK_putaij(task, 1 + 3 * n + j, offsety + j, -U));
}

```

(continues on next page)

(continued from previous page)

```
MOSEKCALL(res, MSK_putvarbound(task, offsety + j, MSK_BK_RA, 0.0, 1.0));
MOSEKCALL(res, MSK_putvartype(task, offsety + j, MSK_VAR_TYPE_INT));
sprintf(buf, "y[%d]", 1 + j);
MOSEKCALL(res, MSK_putvarname(task, offsety + j, buf));
}

if (res == MSK_RES_OK)
{
    /* sub should be n+1 long i.e. the dimension of the cone. */
    MSKint32t *sub = (MSKint32t *) MSK_calloc(task, 3 * n + 1, sizeof(MSKint32t));

    if (sub)
    {
        /* Add quadratic cone */
        sub[0] = offsets + 0;
        for (j = 0; j < n; ++j)
            sub[j + 1] = offsett + j;

        MOSEKCALL(res, MSK_appendcone(task, MSK_CT_QUAD, 0.0, n + 1, sub));
        MOSEKCALL(res, MSK_putconename(task, 0, "stddev"));

        MSK_freetask(task, sub);
    }
    else
        res = MSK_RES_ERR_SPACE;
}

MOSEKCALL(res, MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE));

#ifdef NO_LOG
    /* no log output. */
    MOSEKCALL(res, MSK_putintparam(task, MSK_IPAR_LOG, 0));
#endif

#ifdef DUMP_PROBLEM
    /* Dump the problem to a human readable OPF file. */
    MOSEKCALL(res, MSK_writedata(task, "dump.opf"));
#endif

MOSEKCALL(res, MSK_optimizetrm(task, &trmcode));

#ifdef DISPLAY_RESULTS
    /* Display the solution summary for quick inspection of results. */
    MSK_solutionsummary(task, MSK_STREAM_MSG);
#endif

if (res == MSK_RES_OK)
{
    expret = 0.0;
    stddev = 0.0;

    for (j = 0; j < n; ++j)
    {
        MOSEKCALL(res, MSK_getxxslice(task, MSK_SOL_ITG, offsetx + j, offsetx + j + 1, &xj));
        expret += mu[j] * xj;
    }

    MOSEKCALL(res, MSK_getxxslice(task, MSK_SOL_ITG, offsets + 0, offsets + 1, &stddev));

    printf("\nExpected return %e for gamma %e\n", expret, stddev);
}
```

(continues on next page)

```

}

MSK_deletetask(&task);
MSK_deleteenv(&env);

return (0);
}

```

11.1.7 Cardinality constraints

Another method to reduce costs involved with processing transactions is to only change positions in a small number of assets. In other words, at most k of the differences $|\Delta x_j| = |x_j - x_j^0|$ are allowed to be non-zero, where k is (much) smaller than the total number of assets n .

This type of constraint can be again modeled by introducing a binary variable y_j which indicates if $\Delta x_j \neq 0$ and bounding the sum of y_j . The basic Markowitz model then gets updated as follows:

$$\begin{aligned}
& \text{maximize} && \mu^T x \\
& \text{subject to} && e^T x = w + e^T x^0, \\
& && [\gamma; G^T x] \in \mathcal{Q}^{n+1}, \\
& && U_j y_j \geq |x_j - x_j^0|, \quad j = 1, \dots, n, \\
& && y_j \in \{0, 1\}, \quad j = 1, \dots, n, \\
& && e^T y \leq k, \\
& && x \geq 0,
\end{aligned} \tag{11.20}$$

where U_j is some a priori chosen upper bound on the amount of trading in asset j . This guarantees that $|x_j - x_j^0|$ forces $y_j = 1$ and therefore $e^T y$ counts the number of assets in which we trade. In our problem a safe bound for each U_j is the total initial wealth $w + e^T x^0$, however knowing a tighter bound may lead to shorter solution times.

Creating a matrix formulation

One more reformulation of (11.20) is needed to bring it to the standard form (11.4).

$$\begin{aligned}
& \text{maximize} && \mu^T x \\
& \text{subject to} && e^T x = w + e^T x^0, \\
& && G^T x - t = 0, \\
& && z_j - x_j \geq -x_j^0, \quad j = 1, \dots, n, \\
& && z_j + x_j \geq x_j^0, \quad j = 1, \dots, n, \\
& && (s, t) \in \mathcal{Q}^{n+1}, \\
& && z_j - U_j y_j \leq 0, \quad j = 1, \dots, n, \\
& && e^T y \leq k, \\
& && x \geq 0, \\
& && y_j \in [0, 1], \quad j = 1, \dots, n, \\
& && y_j \in \mathbb{Z}, \quad j = 1, \dots, n, \\
& && s = \gamma.
\end{aligned} \tag{11.21}$$

We will choose the following ordering of variables:

$$\hat{x} = [x; s; t; z; y]$$

Table 11.4 shows the mapping between the \hat{x} vector and the model variables.

Table 11.4: Storage layout for \hat{x}

Variable	Length	Offset
x	n	0
s	1	n
t	n	$n + 1$
z	n	$2n + 1$
y	n	$3n + 1$

The next step is to consider how the linear constraint matrix A and the remaining data vectors are laid out. Reusing the idea in Sec. 11.1.1 we can write the data in block matrix form and read off all the required coordinates. This extension of the code setting up the constraint $G^T x - t = 0$ from Sec. 11.1.1 is shown below.

Example code

The following example code demonstrates how to compute an optimal portfolio with cardinality bounds. Note that we are now solving a problem with integer variables, and therefore the solution must be retrieved from `MSK_SOL_ITG`.

Listing 11.9: Code solving problem (11.20).

```
MSKrescodee markowitz_with_card(const int      n,
                                const double   x0[],
                                const double   w,
                                const double   gamma,
                                const double   mu[],
                                const double   GT[],
                                const int      k,
                                double        *xx)
{
    char          buf[128];
    double        U;
    MSKenv_t      env;
    MSKint32t     i, j,
                offsetx, offsety, offsett, offsetz, offsety;
    MSKrescodee   res = MSK_RES_OK, trmcode;
    MSKtask_t     task;

    /* Initial setup. */
    env = NULL;
    task = NULL;
    MOSEKCALL(res, MSK_makeenv(&env, NULL));
    MOSEKCALL(res, MSK_maketask(env, 0, 0, &task));
    MOSEKCALL(res, MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr));

    /* Compute total wealth */
    U = w;
    for (i = 0; i < n; ++i) U += x0[i];

    /* Constraints. */
    MOSEKCALL(res, MSK_appendcons(task, 2 + 4 * n));

    MOSEKCALL(res, MSK_putconbound(task, 0, MSK_BK_FX, w, w));
    sprintf(buf, "%s", "budget");
    MOSEKCALL(res, MSK_putconname(task, 0, buf));

    MOSEKCALL(res, MSK_putconbound(task, 1 + 4 * n, MSK_BK_UP, -MSK_INFINITY, (double)k));
    sprintf(buf, "%s", "cardinality");
    MOSEKCALL(res, MSK_putconname(task, 1 + 4 * n, buf));

    for (i = 0; i < n; ++i)
    {
        MOSEKCALL(res, MSK_putconbound(task, 1 + i, MSK_BK_FX, 0.0, 0.0));
        sprintf(buf, "GT[%d]", 1 + i);
        MOSEKCALL(res, MSK_putconname(task, 1 + i, buf));
    }

    for (i = 0; i < n; ++i)
    {
        MOSEKCALL(res, MSK_putconbound(task, 1 + n + i, MSK_BK_LO, -x0[i], MSK_INFINITY));
    }
}
```

(continues on next page)

```

    sprintf(buf, "zabs1[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + n + i, buf));
}

for (i = 0; i < n; ++i)
{
    MOSEKCALL(res, MSK_putconbound(task, 1 + 2 * n + i, MSK_BK_LO, x0[i], MSK_INFINITY));
    sprintf(buf, "zabs2[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + 2 * n + i, buf));
}

for (i = 0; i < n; ++i)
{
    MOSEKCALL(res, MSK_putconbound(task, 1 + 3 * n + i, MSK_BK_UP, -MSK_INFINITY, 0.0));
    sprintf(buf, "indicator[%d]", 1 + i);
    MOSEKCALL(res, MSK_putconname(task, 1 + 3 * n + i, buf));
}

/* Offsets of variables into the (serialized) API variable. */
offsetx = 0;
offsets = n;
offsett = n + 1;
offsetz = 2 * n + 1;
offsety = 3 * n + 1;

/* Variables. */
MOSEKCALL(res, MSK_appendvars(task, 4 * n + 1));

/* x variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putcj(task, offsetx + j, mu[j]));
    MOSEKCALL(res, MSK_putaij(task, 0, offsetx + j, 1.0));
    for (i = 0; i < n; ++i)
        if (GT[i*n+j] != 0.0)
            MOSEKCALL(res, MSK_putaij(task, 1 + i, offsetx + j, GT[i*n+j]));
    MOSEKCALL(res, MSK_putaij(task, 1 + n + j, offsetx + j, -1.0));
    MOSEKCALL(res, MSK_putaij(task, 1 + 2 * n + j, offsetx + j, 1.0));

    MOSEKCALL(res, MSK_putvarbound(task, offsetx + j, MSK_BK_LO, 0.0, MSK_INFINITY));
    sprintf(buf, "x[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsetx + j, buf));
}

/* s variable. */
MOSEKCALL(res, MSK_putvarbound(task, offsets + 0, MSK_BK_FX, gamma, gamma));
sprintf(buf, "s");
MOSEKCALL(res, MSK_putvarname(task, offsets + 0, buf));

/* t variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putaij(task, 1 + j, offsett + j, -1.0));
    MOSEKCALL(res, MSK_putvarbound(task, offsett + j, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY));
    sprintf(buf, "t[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsett + j, buf));
}

/* z variables. */
for (j = 0; j < n; ++j)
{

```

(continued from previous page)

```
MOSEKCALL(res, MSK_putaij(task, 1 + 1 * n + j, offsetz + j, 1.0));
MOSEKCALL(res, MSK_putaij(task, 1 + 2 * n + j, offsetz + j, 1.0));
MOSEKCALL(res, MSK_putaij(task, 1 + 3 * n + j, offsetz + j, 1.0));
MOSEKCALL(res, MSK_putvarbound(task, offsetz + j, MSK_BK_FR, -MSK_INFINITY, MSK_INFINITY));
sprintf(buf, "z[%d]", 1 + j);
MOSEKCALL(res, MSK_putvarname(task, offsetz + j, buf));
}

/* y variables. */
for (j = 0; j < n; ++j)
{
    MOSEKCALL(res, MSK_putaij(task, 1 + 4 * n, offsety + j, 1.0));
    MOSEKCALL(res, MSK_putaij(task, 1 + 3 * n + j, offsety + j, -U));
    MOSEKCALL(res, MSK_putvarbound(task, offsety + j, MSK_BK_RA, 0.0, 1.0));
    MOSEKCALL(res, MSK_putvartype(task, offsety + j, MSK_VAR_TYPE_INT));
    sprintf(buf, "y[%d]", 1 + j);
    MOSEKCALL(res, MSK_putvarname(task, offsety + j, buf));
}

if (res == MSK_RES_OK)
{
    /* sub should be n+1 long i.e. the dimension of the cone. */
    MSKint32t *sub = (MSKint32t *) MSK_calloc(task, 3 >= n + 1 ? 3 : n + 1,
↪sizeof(MSKint32t));

    if (sub)
    {
        /* Add quadratic cone */
        sub[0] = offsets + 0;
        for (j = 0; j < n; ++j)
            sub[j + 1] = offsett + j;

        MOSEKCALL(res, MSK_appendcone(task, MSK_CT_QUAD, 0.0, n + 1, sub));
        MOSEKCALL(res, MSK_putconename(task, 0, "stddev"));

        MSK_freetask(task, sub);
    }
    else
        res = MSK_RES_ERR_SPACE;
}

MOSEKCALL(res, MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE));

#ifdef 1
    /* no log output. */
    MOSEKCALL(res, MSK_putintparam(task, MSK_IPAR_LOG, 0));
#endif

#ifdef 0
    /* Dump the problem to a human readable OPF file. */
    MOSEKCALL(res, MSK_writedata(task, "dump.opf"));
#endif

    MOSEKCALL(res, MSK_optimizetrm(task, &trmcode));

#ifdef 1
    /* Display the solution summary for quick inspection of results. */
    MSK_solutionsummary(task, MSK_STREAM_MSG);
#endif

    if (res == MSK_RES_OK)
```

(continues on next page)

```

MOSEKCALL(res, MSK_getxxslice(task, MSK_SOL_ITG, offsetx, offsetx + n, xx));

MSK_deletetask(&task);
MSK_deleteenv(&env);

return res;
}

```

If we solve our running example with $k = 1, 2, 3$ then we get the following solutions, with increasing expected returns:

Bound 1:	x = 0.00000 0.00000 1.00000	Return: x = 0.06270
Bound 2:	x = 0.25286 0.00000 0.74714	Return: x = 0.07398
Bound 3:	x = 0.23639 0.13850 0.62511	Return: x = 0.07477

11.2 Logistic regression

Logistic regression is an example of a binary classifier, where the output takes one two values 0 or 1 for each data point. We call the two values *classes*.

Formulation as an optimization problem

Define the sigmoid function

$$S(x) = \frac{1}{1 + \exp(-x)}.$$

Next, given an observation $x \in \mathbb{R}^d$ and a weights $\theta \in \mathbb{R}^d$ we set

$$h_\theta(x) = S(\theta^T x) = \frac{1}{1 + \exp(-\theta^T x)}.$$

The weights vector θ is part of the setup of the classifier. The expression $h_\theta(x)$ is interpreted as the probability that x belongs to class 1. When asked to classify x the returned answer is

$$x \mapsto \begin{cases} 1 & h_\theta(x) \geq 1/2, \\ 0 & h_\theta(x) < 1/2. \end{cases}$$

When training a logistic regression algorithm we are given a sequence of training examples x_i , each labelled with its class $y_i \in \{0, 1\}$ and we seek to find the weights θ which maximize the likelihood function

$$\prod_i h_\theta(x_i)^{y_i} (1 - h_\theta(x_i))^{1-y_i}.$$

Of course every single y_i equals 0 or 1, so just one factor appears in the product for each training data point. By taking logarithms we can define the logistic loss function:

$$J(\theta) = - \sum_{i: y_i=1} \log(h_\theta(x_i)) - \sum_{i: y_i=0} \log(1 - h_\theta(x_i)).$$

The training problem with regularization (a standard technique to prevent overfitting) is now equivalent to

$$\min_{\theta} J(\theta) + \lambda \|\theta\|_2.$$

This can equivalently be phrased as

$$\begin{aligned} & \text{minimize} && \sum_i t_i + \lambda r \\ & \text{subject to} && t_i \geq -\log(h_\theta(x_i)) &= \log(1 + \exp(-\theta^T x_i)) & \text{if } y_i = 1, \\ & && t_i \geq -\log(1 - h_\theta(x_i)) &= \log(1 + \exp(\theta^T x_i)) & \text{if } y_i = 0, \\ & && r \geq \|\theta\|_2. \end{aligned} \tag{11.22}$$

Implementation

As can be seen from (11.22) the key point is to implement the softplus bound $t \geq \log(1 + e^u)$, which is the simplest example of a log-sum-exp constraint for two scalar variables t, u . This is equivalent to

$$\exp(u - t) + \exp(-t) \leq 1$$

and further to

$$\begin{aligned} (z_1, 1, u - t) &\in K_{\exp} & (z_1 \geq \exp(u - t)), \\ (z_2, 1, -t) &\in K_{\exp} & (z_2 \geq \exp(-t)), \\ z_1 + z_2 &\leq 1. \end{aligned} \quad (11.23)$$

To feed these constraints into **MOSEK** we add more auxiliary variables q_1, q_2, v_1, v_2 with constraints $(z_1, q_1, v_1) \in K_{\exp}$, $(z_2, q_2, v_2) \in K_{\exp}$, $q_1 = q_2 = 1$, $v_1 = u - t$ and $v_2 = -t$.

Listing 11.10: Implementation of $t \geq \log(1 + e^u)$ as in (11.23).

```
// t >= log( 1 + exp(u) )
// t_i >= log( 1 + exp(u_i) ), i = 0..n-1
// Adds auxiliary variables and constraints
MSKrescodee softplus(MSKtask_t task, MSKint32t t, MSKint32t u, int n)
{
    MSKint32t nvar, ncon;
    MSKint32t z1, z2, v1, v2, q1, q2;
    MSKint32t zcon, v1con, v2con;
    MSKint32t *subi = (MSKint32t*) calloc(7*n, sizeof(MSKint32t));
    MSKint32t *subj = (MSKint32t*) calloc(7*n, sizeof(MSKint32t));
    MSKrealt *aval = (MSKrealt*) calloc(7*n, sizeof(MSKrealt));
    int k = 0, i = 0;
    MSKrescodee res = MSK_RES_OK;

    MSKCALL(MSK_getnumvar(task, &nvar));
    MSKCALL(MSK_getnumcon(task, &ncon));
    z1 = nvar, z2 = nvar+n, v1 = nvar+2*n, v2 = nvar+3*n, q1 = nvar+4*n, q2 = nvar+5*n;
    zcon = ncon, v1con = ncon+n, v2con=ncon+2*n;
    MSKCALL(MSK_appendvars(task, 6*n));
    MSKCALL(MSK_appendcons(task, 3*n));

    // Linear constraints
    for(i = 0; i < n; i++)
    {
        // z1 + z2 = 1
        subi[k] = zcon+i; subj[k] = z1+i; aval[k] = 1; k++;
        subi[k] = zcon+i; subj[k] = z2+i; aval[k] = 1; k++;
        // u - t - v1 = 0
        subi[k] = v1con+i; subj[k] = u+i; aval[k] = 1; k++;
        subi[k] = v1con+i; subj[k] = t+i; aval[k] = -1; k++;
        subi[k] = v1con+i; subj[k] = v1+i; aval[k] = -1; k++;
        // - t - v2 = 0
        subi[k] = v2con+i; subj[k] = t+i; aval[k] = -1; k++;
        subi[k] = v2con+i; subj[k] = v2+i; aval[k] = -1; k++;
    }
    MSKCALL(MSK_putaijlist(task, 7*n, subi, subj, aval));
    MSKCALL(MSK_putconboundsliceconst(task, ncon, ncon+n, MSK_BK_FX, 1, 1));
    MSKCALL(MSK_putconboundsliceconst(task, ncon+n, ncon+3*n, MSK_BK_FX, 0, 0));

    // Bounds for variables
    MSKCALL(MSK_putvarboundsliceconst(task, nvar, nvar+4*n, MSK_BK_FR, -inf, inf));
    MSKCALL(MSK_putvarboundsliceconst(task, nvar+4*n, nvar+6*n, MSK_BK_FX, 1, 1));

    // Cones
    for(i = 0; i < n && res == MSK_RES_OK; i++)
```

(continues on next page)

(continued from previous page)

```
{
    MSKint32t csub[3];
    csub[0] = z1+i; csub[1] = q1+i; csub[2] = v1+i;
    MSKCALL(MSK_appendcone(task, MSK_CT_PEXP, 0.0, 3, csub));
    csub[0] = z2+i; csub[1] = q2+i; csub[2] = v2+i;
    MSKCALL(MSK_appendcone(task, MSK_CT_PEXP, 0.0, 3, csub));
}

free(subi); free(subj); free(aval);
return res;
}
```

Once we have this subroutine, it is easy to implement a function that builds the regularized loss function model (11.22).

Listing 11.11: Implementation of (11.22).

```
// Model logistic regression (regularized with full 2-norm of theta)
// X - n x d matrix of data points
// y - length n vector classifying training points
// lamb - regularization parameter
MSKrescodee logisticRegression(MSKenv_t env,
                               int n, // num samples
                               int d, // dimension
                               double *X,
                               int *y,
                               double lamb,
                               double *thetaVal) // result
{
    MSKrescodee res = MSK_RES_OK;
    MSKrescodee trm = MSK_RES_OK;
    MSKtask_t task = NULL;
    MSKint32t nvar = 1+d+2*n;
    MSKint32t r = 0, theta = 1, t = 1+d, u = 1+d+n;
    int i = 0;

    MSKCALL(MSK_maketask(env, 0, 0, &task));
    MSKCALL(MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr));

    // Variables [r; theta; t; u]
    MSKCALL(MSK_appendvars(task, nvar));
    MSKCALL(MSK_putvarboundsliceconst(task, 0, nvar, MSK_BK_FR, -inf, inf));

    // Constraints: theta'*X +/- u = 0
    MSKCALL(MSK_appendcons(task, n));
    MSKCALL(MSK_putconboundsliceconst(task, 0, n, MSK_BK_FX, 0, 0));

    // Objective lambda*r + sum(t)
    MSKCALL(MSK_putcj(task, r, lamb));
    for(i = 0; i < n && res == MSK_RES_OK; i++)
        MSKCALL(MSK_putcj(task, t+i, 1.0));

    // The X block in theta'*X +/- u = 0
    {
        MSKint32t *subi = (MSKint32t*) calloc(d*n+n, sizeof(MSKint32t));
        MSKint32t *subj = (MSKint32t*) calloc(d*n+n, sizeof(MSKint32t));
        MSKrealt *aval = (MSKrealt*) calloc(d*n+n, sizeof(MSKrealt));
        int j, k;

        for(i = 0; i < n; i++)
        {
```

(continues on next page)

```

for(j = 0; j < d; j++)
{
    k = i * d + j;
    subi[k] = i; subj[k] = theta+j; aval[k] = X[k];
}
subi[d*n+i] = i; subj[d*n+i] = u+i;
if (y[i]) aval[d*n+i] = 1; else aval[d*n+i] = -1;
}

MSKCALL(MSK_putaijlist(task, n*d+n, subi, subj, aval));

free(subi); free(subj); free(aval);
}

// Softplus function constraints
MSKCALL(softplus(task, t, u, n));

// Regularization
MSKCALL(MSK_appendconeseq(task, MSK_CT_QUAD, 0.0, 1+d, r));

// Solution
MSKCALL(MSK_optimizetrm(task, &trm));
MSKCALL(MSK_solutionsummary(task, MSK_STREAM_MSG));

MSKCALL(MSK_getxxslice(task, MSK_SOL_ITR, theta, theta+d, thetaVal));

return res;
}

```

Example: 2D dataset fitting

In the next figure we apply logistic regression to the training set of 2D points taken from the example `ex2data2.txt`. The two-dimensional dataset was converted into a feature vector $x \in \mathbb{R}^{28}$ using monomial coordinates of degrees at most 6.




Fig. 11.1: Logistic regression example with none, medium and strong regularization (small, medium, large λ). Without regularization we get obvious overfitting.

11.3 Concurrent optimizer

The idea of the concurrent optimizer is to run multiple optimizations of **the same problem** simultaneously, and pick the one that provides the fastest or best answer. This approach is especially useful for problems which require a very long time and it is hard to say in advance which optimizer or algorithm will perform best.

The major applications of concurrent optimization we describe in this section are:

- Using the interior-point and simplex optimizers simultaneously on a linear problem. Note that any solution present in the task will also be used for hot-starting the simplex algorithms. One

possible scenario would therefore be running a hot-start simplex in parallel with interior point, taking advantage of both the stability of the interior-point method and the ability of the simplex method to use an initial solution.

- Using multiple instances of the mixed-integer optimizer to solve many copies of one mixed-integer problem. This is not in contradiction with the run-to-run determinism of **MOSEK** if a different value of the MIO seed parameter `MSK_IPAR_MIO_SEED` is set in each instance. As a result each setting leads to a different optimizer run (each of them being deterministic in its own right).

The downloadable file contains usage examples of both kinds.

11.3.1 Common setup

We first define a method that runs a number of optimization tasks in parallel, using the standard multithreading setup available in the language. All tasks register for a callback function which will signal them to interrupt as soon as the first task completes successfully (with response code `MSK_RES_OK`).

Listing 11.12: Simple callback function which signals the optimizer to stop (C++).

```
/**
 * Defines a Mosek callback function whose only function
 * is to indicate if the optimizer should be stopped.
 */
int stop = 0;
int firstStop = -1;
MSKint32t MSKAPI callback (MSKtask_t task, MSKuserhandle_t usrptr, MSKcallbackcodee caller,
                           const MSKrealt * douinf, const MSKint32t * intinf, const MSKint64t
↳* lintinf)
{
    return stop;
}
```

When all remaining tasks respond to the stop signal, response codes and statuses are returned to the caller, together with the index of the task which won the race.

Listing 11.13: A routine for parallel task race (C++).

```
void runTask(int num,
             MSKtask_t task,
             MSKrescodee *res,
             MSKrescodee *trm)
{
    *res = MSK_optimizetrm(task, trm);
    if (*res == MSK_RES_OK) {
        if (!stop) firstStop = num;
        stop = 1;
    }
}

int optimize(int n,
             MSKtask_t *tasks,
             MSKrescodee *res,
             MSKrescodee *trm)
{
    int i;
    std::thread * jobs = new std::thread[n];

    // Set a callback function and start optimization
    for(i = 0; i < n; ++i) {
        MSK_putcallbackfunc(tasks[i], callback, NULL);
        res[i] = trm[i] = MSK_RES_ERR_UNKNOWN;
        jobs[i] = std::thread(runTask, i, tasks[i], &(res[i]), &(trm[i]));
    }
}
```

(continues on next page)

(continued from previous page)

```
}

// Join all threads
for(i = 0; i < n; ++i) jobs[i].join();
delete[] jobs;

// For debugging, print res and trm codes for all optimizers
for(i = 0; i < n; ++i)
    printf("Optimizer %d   res %d   trm %d\n", i, res[i], trm[i]);

return firstStop;
}
```

11.3.2 Linear optimization

We use the multithreaded setup to run the interior-point and simplex optimizers simultaneously on a linear problem. The next methods simply clones the given task and sets a different optimizer for each. The result is the clone which finished first.

Listing 11.14: Concurrent optimization with different optimizers (C++).

```
int optimizeconcurrent(MSKtask_t      task,
                      int             n,
                      MSKOptimizertypee *optimizers,
                      MSKtask_t        *winTask,
                      MSKrescodee       *winTrm,
                      MSKrescodee       *winRes)
{
    MSKtask_t  *tasks = new MSKtask_t[n];
    MSKrescodee *res   = new MSKrescodee[n];
    MSKrescodee *trm   = new MSKrescodee[n];

    // Clone tasks and choose various optimizers
    for (int i = 0; i < n; ++i)
    {
        MSK_clonetask(task, &(tasks[i]));
        MSK_putintparam(tasks[i], MSK_IPAR_OPTIMIZER, optimizers[i]);
    }

    // Solve tasks in parallel
    int firstOK = optimize(n, tasks, res, trm);

    if (firstOK >= 0)
    {
        *winTask = tasks[firstOK];
        *winTrm  = trm[firstOK];
        *winRes  = res[firstOK];
    }
    else
    {
        *winTask = NULL;
        *winTrm  = MSK_RES_ERR_UNKNOWN;
        *winRes  = MSK_RES_ERR_UNKNOWN;
    }

    // Cleanup
    for (int i = 0; i < n; ++i)
        if (i != firstOK) MSK_deletetask(&(tasks[i]));
}
```

(continues on next page)

(continued from previous page)

```
delete[] tasks; delete[] res; delete[] trm;
return firstOK;
}
```

It remains to call the method with a choice of optimizers, for example:

Listing 11.15: Calling concurrent linear optimization (C++).

```
MSKoptimizertypee optimizers[3] = {
    MSK_OPTIMIZER_CONIC,
    MSK_OPTIMIZER_DUAL_SIMPLEX,
    MSK_OPTIMIZER_PRIMAL_SIMPLEX
};

idx = optimizeconcurrent(task, 3, optimizers, &t, &trm, &res);
```

11.3.3 Mixed-integer optimization

We use the multithreaded setup to run many, differently seeded copies of the mixed-integer optimizer. This approach is most useful for hard problems where we don't expect an optimal solution in reasonable time. The input task would typically contain a time limit. It is possible that all the cloned tasks reach the time limit, in which case it doesn't really matter which one terminated first. Instead we examine all the task clones for the best objective value.

Listing 11.16: Concurrent optimization of a mixed-integer problem (C++).

```
int optimizeconcurrentMIO(MSKtask_t task,
                          int n,
                          int *seeds,
                          MSKtask_t *winTask,
                          MSKrescodee *winTrm,
                          MSKrescodee *winRes)
{
    MSKtask_t *tasks = new MSKtask_t[n];
    MSKrescodee *res = new MSKrescodee[n];
    MSKrescodee *trm = new MSKrescodee[n];
    *winTask = NULL;
    *winTrm = MSK_RES_ERR_UNKNOWN;
    *winRes = MSK_RES_ERR_UNKNOWN;
    int bestPos = -1;

    // Clone tasks and choose various optimizers
    for (int i = 0; i < n; ++i)
    {
        MSK_clonetask(task, &(tasks[i]));
        MSK_putintparam(tasks[i], MSK_IPAR_MIO_SEED, seeds[i]);
    }

    // Solve tasks in parallel
    int firstOK = optimize(n, tasks, res, trm);

    if (firstOK >= 0)
    {
        // Pick the task that ended with res = ok
        // and contains an integer solution with best objective value
        MSKobjsensee sense;
        double bestObj;

        MSK_getobjsense(task, &sense);
```

(continues on next page)

(continued from previous page)

```
bestObj = (sense == MSK_OBJECTIVE_SENSE_MINIMIZE) ? 1.0e+10 : -1.0e+10;

for (int i = 0; i < n; ++i) {
    double priObj;
    MSK_getprimalobj(tasks[i], MSK_SOL_ITG, &priObj);
    printf("%d\t%f\n", i, priObj);
}

for (int i = 0; i < n; ++i) {
    double priObj;
    MSKsolstae solsta;
    MSK_getprimalobj(tasks[i], MSK_SOL_ITG, &priObj);
    MSK_getsolsta(tasks[i], MSK_SOL_ITG, &solsta);

    if ((res[i] == MSK_RES_OK) &&
        (solsta == MSK_SOL_STA_PRIM_FEAS ||
         solsta == MSK_SOL_STA_INTEGER_OPTIMAL) &&
        ((sense == MSK_OBJECTIVE_SENSE_MINIMIZE) ?
         (priObj < bestObj) : (priObj > bestObj)) ) )
    {
        bestObj = priObj;
        bestPos = i;
    }
}

if (bestPos != -1)
{
    *winTask = tasks[bestPos];
    *winTrm = trm[bestPos];
    *winRes = res[bestPos];
}

// Cleanup
for (int i = 0; i < n; ++i)
    if (i != bestPos) MSK_deletetask(&(tasks[i]));

delete[] tasks; delete[] res; delete[] trm;
return bestPos;
}
```

It remains to call the method with a choice of seeds, for example:

Listing 11.17: Calling concurrent integer optimization (C++).

```
int seeds[3] = { 42, 13, 71749373 };

idx = optimizeconcurrentMIO(task, 3, seeds, &t, &trm, &res);
```

Chapter 12

Problem Formulation and Solutions

In this chapter we will discuss the following issues:

- The formal, mathematical formulations of the problem types that **MOSEK** can solve and their duals.
- The solution information produced by **MOSEK**.
- The infeasibility certificate produced by **MOSEK** if the problem is infeasible.

For the underlying mathematical concepts, derivations and proofs see the [Modeling Cookbook](#) or any book on convex optimization. This chapter explains how the related data is organized specifically within the **MOSEK** API.

12.1 Linear Optimization

MOSEK accepts linear optimization problems of the form

$$\begin{array}{llllll} \text{minimize} & & c^T x + c^f & & & \\ \text{subject to} & l^c & \leq & Ax & \leq & u^c, \\ & l^x & \leq & x & \leq & u^x, \end{array} \quad (12.1)$$

where

- m is the number of constraints.
- n is the number of decision variables.
- $x \in \mathbb{R}^n$ is a vector of decision variables.
- $c \in \mathbb{R}^n$ is the linear part of the objective function.
- $c^f \in \mathbb{R}$ is a constant term in the objective
- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.
- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.

Lower and upper bounds can be infinite, or in other words the corresponding bound may be omitted.

A primal solution (x) is *(primal) feasible* if it satisfies all constraints in (12.1). If (12.1) has at least one primal feasible solution, then (12.1) is said to be (primal) feasible. In case (12.1) does not have a feasible solution, the problem is said to be *(primal) infeasible*.

12.1.1 Duality for Linear Optimization

Corresponding to the primal problem (12.1), there is a dual problem

$$\begin{aligned} & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ & && A^T y + s_l^x - s_u^x = c, \\ & \text{subject to} && -y + s_l^c - s_u^c = 0, \\ & && s_l^c, s_u^c, s_l^x, s_u^x \geq 0. \end{aligned} \quad (12.2)$$

If a bound in the primal problem is plus or minus infinity, the corresponding dual variable is fixed at 0, and we use the convention that the product of the bound value and the corresponding dual variable is 0. This is equivalent to removing variable $(s_l^x)_j$ from the dual problem. In other words:

$$l_j^x = -\infty \quad \Rightarrow \quad (s_l^x)_j = 0 \text{ and } l_j^x \cdot (s_l^x)_j = 0.$$

A solution

$$(y, s_l^c, s_u^c, s_l^x, s_u^x)$$

to the dual problem is feasible if it satisfies all the constraints in (12.2). If (12.2) has at least one feasible solution, then (12.2) is *(dual) feasible*, otherwise the problem is *(dual) infeasible*.

A solution

$$(x^*, y^*, (s_l^c)^*, (s_u^c)^*, (s_l^x)^*, (s_u^x)^*)$$

is denoted a *primal-dual feasible solution*, if (x^*) is a solution to the primal problem (12.1) and $(y^*, (s_l^c)^*, (s_u^c)^*, (s_l^x)^*, (s_u^x)^*)$ is a solution to the corresponding dual problem (12.2). We also define an auxiliary vector

$$(x^c)^* := Ax^*$$

containing the activities of linear constraints.

For a primal-dual feasible solution we define the *duality gap* as the difference between the primal and the dual objective value,

$$\begin{aligned} & c^T x^* + c^f - \{ (l^c)^T (s_l^c)^* - (u^c)^T (s_u^c)^* + (l^x)^T (s_l^x)^* - (u^x)^T (s_u^x)^* + c^f \} \\ &= \sum_{i=0}^{m-1} [(s_l^c)^*_i ((x_i^c)^* - l_i^c) + (s_u^c)^*_i (u_i^c - (x_i^c)^*)] \\ &+ \sum_{j=0}^{n-1} [(s_l^x)^*_j (x_j - l_j^x) + (s_u^x)^*_j (u_j^x - x_j^*)] \geq 0 \end{aligned} \quad (12.3)$$

where the first relation can be obtained by transposing and multiplying the dual constraints (12.2) by x^* and $(x^c)^*$ respectively, and the second relation comes from the fact that each term in each sum is nonnegative. It follows that the primal objective will always be greater than or equal to the dual objective.

It is well-known that a linear optimization problem has an optimal solution if and only if there exist feasible primal-dual solution so that the duality gap is zero, or, equivalently, that the *complementarity conditions*

$$\begin{aligned} (s_l^c)^*_i ((x_i^c)^* - l_i^c) &= 0, & i = 0, \dots, m-1, \\ (s_u^c)^*_i (u_i^c - (x_i^c)^*) &= 0, & i = 0, \dots, m-1, \\ (s_l^x)^*_j (x_j^* - l_j^x) &= 0, & j = 0, \dots, n-1, \\ (s_u^x)^*_j (u_j^x - x_j^*) &= 0, & j = 0, \dots, n-1, \end{aligned}$$

are satisfied.

If (12.1) has an optimal solution and **MOSEK** solves the problem successfully, both the primal and dual solution are reported, including a status indicating the exact state of the solution.

12.1.2 Infeasibility for Linear Optimization

Primal Infeasible Problems

If the problem (12.1) is infeasible (has no feasible solution), **MOSEK** will report a certificate of primal infeasibility: The dual solution reported is the certificate of infeasibility, and the primal solution is undefined.

A certificate of primal infeasibility is a feasible solution to the modified dual problem

$$\begin{aligned}
& \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x \\
& \text{subject to} && A^T y + s_l^x - s_u^x = 0, \\
& && -y + s_l^c - s_u^c = 0, \\
& && s_l^c, s_u^c, s_l^x, s_u^x \geq 0,
\end{aligned} \tag{12.4}$$

such that the objective value is strictly positive, i.e. a solution

$$(y^*, (s_l^c)^*, (s_u^c)^*, (s_l^x)^*, (s_u^x)^*)$$

to (12.4) so that

$$(l^c)^T (s_l^c)^* - (u^c)^T (s_u^c)^* + (l^x)^T (s_l^x)^* - (u^x)^T (s_u^x)^* > 0.$$

Such a solution implies that (12.4) is unbounded, and that (12.1) is infeasible.

Dual Infeasible Problems

If the problem (12.2) is infeasible (has no feasible solution), **MOSEK** will report a certificate of dual infeasibility: The primal solution reported is the certificate of infeasibility, and the dual solution is undefined.

A certificate of dual infeasibility is a feasible solution to the modified primal problem

$$\begin{aligned}
& \text{minimize} && c^T x \\
& \text{subject to} && \hat{l}^c \leq Ax \leq \hat{u}^c, \\
& && \hat{l}^x \leq x \leq \hat{u}^x,
\end{aligned} \tag{12.5}$$

where

$$\hat{l}_i^c = \begin{cases} 0 & \text{if } l_i^c > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and} \quad \hat{u}_i^c := \begin{cases} 0 & \text{if } u_i^c < \infty, \\ \infty & \text{otherwise,} \end{cases}$$

and

$$\hat{l}_j^x = \begin{cases} 0 & \text{if } l_j^x > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and} \quad \hat{u}_j^x := \begin{cases} 0 & \text{if } u_j^x < \infty, \\ \infty & \text{otherwise,} \end{cases}$$

such that

$$c^T x < 0.$$

Such a solution implies that (12.5) is unbounded, and that (12.2) is infeasible.

In case that both the primal problem (12.1) and the dual problem (12.2) are infeasible, **MOSEK** will report only one of the two possible certificates — which one is not defined (**MOSEK** returns the first certificate found).

12.1.3 Minimalization vs. Maximalization

When the objective sense of problem (12.1) is maximization, i.e.

$$\begin{aligned}
& \text{maximize} && c^T x + c^f \\
& \text{subject to} && l^c \leq Ax \leq u^c, \\
& && l^x \leq x \leq u^x,
\end{aligned}$$

the objective sense of the dual problem changes to minimization, and the domain of all dual variables changes sign in comparison to (12.2). The dual problem thus takes the form

$$\begin{aligned}
& \text{minimize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\
& \text{subject to} && A^T y + s_l^x - s_u^x = c, \\
& && -y + s_l^c - s_u^c = 0, \\
& && s_l^c, s_u^c, s_l^x, s_u^x \leq 0.
\end{aligned}$$

This means that the duality gap, defined in (12.3) as the primal minus the dual objective value, becomes nonpositive. It follows that the dual objective will always be greater than or equal to the primal objective. The primal infeasibility certificate will be reported by **MOSEK** as a solution to the system

$$\begin{aligned} A^T y + s_l^x - s_u^x &= 0, \\ -y + s_l^c - s_u^c &= 0, \\ s_l^c, s_u^c, s_l^x, s_u^x &\leq 0, \end{aligned} \tag{12.6}$$

such that the objective value is strictly negative

$$(l^c)^T (s_l^c)^* - (u^c)^T (s_u^c)^* + (l^x)^T (s_l^x)^* - (u^x)^T (s_u^x)^* < 0.$$

Similarly, the certificate of dual infeasibility is an x satisfying the requirements of (12.5) such that $c^T x > 0$.

12.2 Conic Optimization

Conic optimization is an extension of linear optimization (see Sec. 12.1) allowing conic domains to be specified for subsets of the problem variables. A conic optimization problem to be solved by **MOSEK** can be written as

$$\begin{aligned} &\text{minimize} && c^T x + c^f \\ &\text{subject to} && l^c \leq Ax \leq u^c, \\ & && l^x \leq x \leq u^x, \\ & && x \in \mathcal{K}, \end{aligned} \tag{12.7}$$

where

- m is the number of constraints.
- n is the number of decision variables.
- $x \in \mathbb{R}^n$ is a vector of decision variables.
- $c \in \mathbb{R}^n$ is the linear part of the objective function.
- $c^f \in \mathbb{R}$ is a constant term in the objective
- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.
- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.

Lower and upper bounds can be infinite, or in other words the corresponding bound may be omitted.

The set \mathcal{K} is a Cartesian product of convex cones, namely $\mathcal{K} = \mathcal{K}_1 \times \cdots \times \mathcal{K}_p$. Having the domain restriction $x \in \mathcal{K}$, is thus equivalent to

$$x^t \in \mathcal{K}_t \subseteq \mathbb{R}^{n_t},$$

where $x = (x^1, \dots, x^p)$ is a partition of the problem variables. Please note that the n -dimensional Euclidean space \mathbb{R}^n is a cone itself, so simple linear variables are still allowed. The user only needs to specify subsets of variables which belong to non-trivial cones.

In this section we discuss the formulations which apply to the following cones supported by **MOSEK**:

- The set \mathbb{R}^n .
- The zero cone $\{(0, \dots, 0)\}$.
- Quadratic cone

$$\mathcal{Q}^n = \left\{ x \in \mathbb{R}^n : x_1 \geq \sqrt{\sum_{j=2}^n x_j^2} \right\}.$$

- Rotated quadratic cone

$$\mathcal{Q}_r^n = \left\{ x \in \mathbb{R}^n : 2x_1x_2 \geq \sum_{j=3}^n x_j^2, \quad x_1 \geq 0, \quad x_2 \geq 0 \right\}.$$

- Primal exponential cone

$$K_{\text{exp}} = \{x \in \mathbb{R}^3 : x_1 \geq x_2 \exp(x_3/x_2), \quad x_1, x_2 \geq 0\}$$

as well as its dual

$$K_{\text{exp}}^* = \{x \in \mathbb{R}^3 : x_1 \geq -x_3 e^{-1} \exp(x_2/x_3), \quad x_3 \leq 0, x_1 \geq 0\}.$$

- Primal power cone (with parameter $0 < \alpha < 1$)

$$\mathcal{P}_n^{\alpha, 1-\alpha} = \left\{ x \in \mathbb{R}^n : x_1^\alpha x_2^{1-\alpha} \geq \sqrt{\sum_{j=3}^n x_j^2}, \quad x_1, x_2 \geq 0 \right\}$$

as well as its dual

$$(\mathcal{P}_n^{\alpha, 1-\alpha})^* = \left\{ x \in \mathbb{R}^n : \left(\frac{x_1}{\alpha}\right)^\alpha \left(\frac{x_2}{1-\alpha}\right)^{1-\alpha} \geq \sqrt{\sum_{j=3}^n x_j^2}, \quad x_1, x_2 \geq 0 \right\}.$$

MOSEK supports also the cone of positive semidefinite matrices. Since that is handled through a separate interface, we discuss it in [Sec. 12.3](#).

12.2.1 Duality for Conic Optimization

Corresponding to the primal problem (12.7), there is a dual problem

$$\begin{aligned} & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ & \text{subject to} && A^T y + s_l^x - s_u^x + s_n^x = c \\ & && -y + s_l^c - s_u^c = 0, \\ & && s_l^c, s_u^c, s_l^x, s_u^x \geq 0, \\ & && s_n^x \in \mathcal{K}^*, \end{aligned} \tag{12.8}$$

where the dual cone \mathcal{K}^* is a Cartesian product of the cones dual to \mathcal{K}_t . In practice this means that s_n^x has one entry for each entry in x . Please note that the dual problem of the dual problem is identical to the original primal problem.

If a bound in the primal problem is plus or minus infinity, the corresponding dual variable is fixed at 0, and we use the convention that the product of the bound value and the corresponding dual variable is 0. This is equivalent to removing variable $(s_l^x)_j$ from the dual problem. In other words:

$$l_j^x = -\infty \quad \Rightarrow \quad (s_l^x)_j = 0 \text{ and } l_j^x \cdot (s_l^x)_j = 0.$$

A solution

$$(y, s_l^c, s_u^c, s_l^x, s_u^x, s_n^x)$$

to the dual problem is feasible if it satisfies all the constraints in (12.8). If (12.8) has at least one feasible solution, then (12.8) is *(dual) feasible*, otherwise the problem is *(dual) infeasible*.

A solution

$$(x^*, y^*, (s_l^c)^*, (s_u^c)^*, (s_l^x)^*, (s_u^x)^*, (s_n^x)^*)$$

is denoted a *primal-dual feasible solution*, if (x^*) is a solution to the primal problem (12.7) and $(y^*, (s_l^c)^*, (s_u^c)^*, (s_l^x)^*, (s_u^x)^*, (s_n^x)^*)$ is a solution to the corresponding dual problem (12.8). We also define an auxiliary vector

$$(x^c)^* := Ax^*$$

containing the activities of linear constraints.

For a primal-dual feasible solution we define the *duality gap* as the difference between the primal and the dual objective value,

$$\begin{aligned} & c^T x^* + c^f - \{ (l^c)^T (s_l^c)^* - (u^c)^T (s_u^c)^* + (l^x)^T (s_l^x)^* - (u^x)^T (s_u^x)^* + c^f \} \\ &= \sum_{i=0}^{m-1} [(s_l^c)^*_i ((x_i^c)^* - l_i^c) + (s_u^c)^*_i (u_i^c - (x_i^c)^*)] \\ &+ \sum_{j=0}^{n-1} [(s_l^x)^*_j (x_j - l_j^x) + (s_u^x)^*_j (u_j^x - x_j^*)] + \sum_{j=0}^{n-1} (s_n^x)^*_j x_j^* \geq 0 \end{aligned} \quad (12.9)$$

where the first relation can be obtained by transposing and multiplying the dual constraints (12.2) by x^* and $(x^c)^*$ respectively, and the second relation comes from the fact that each term in each sum is nonnegative. It follows that the primal objective will always be greater than or equal to the dual objective.

It is well-known that, under some non-degeneracy assumptions that exclude ill-posed cases, a conic optimization problem has an optimal solution if and only if there exist feasible primal-dual solution so that the duality gap is zero, or, equivalently, that the *complementarity conditions*

$$\begin{aligned} (s_l^c)^*_i ((x_i^c)^* - l_i^c) &= 0, & i = 0, \dots, m-1, \\ (s_u^c)^*_i (u_i^c - (x_i^c)^*) &= 0, & i = 0, \dots, m-1, \\ (s_l^x)^*_j (x_j^* - l_j^x) &= 0, & j = 0, \dots, n-1, \\ (s_u^x)^*_j (u_j^x - x_j^*) &= 0, & j = 0, \dots, n-1, \\ \sum_{j=0}^{n-1} (s_n^x)^*_j x_j^* &= 0. \end{aligned} \quad (12.10)$$

are satisfied.

If (12.7) has an optimal solution and **MOSEK** solves the problem successfully, both the primal and dual solution are reported, including a status indicating the exact state of the solution.

12.2.2 Infeasibility for Conic Optimization

Primal Infeasible Problems

If the problem (12.7) is infeasible (has no feasible solution), **MOSEK** will report a certificate of primal infeasibility: The dual solution reported is the certificate of infeasibility, and the primal solution is undefined.

A certificate of primal infeasibility is a feasible solution to the modified dual problem

$$\begin{aligned} & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x \\ & \text{subject to} && \\ & && A^T y + s_l^x - s_u^x + s_n^x = 0, \\ & && -y + s_l^c - s_u^c = 0, \\ & && s_l^c, s_u^c, s_l^x, s_u^x \geq 0, \\ & && s_n^x \in \mathcal{K}^*, \end{aligned} \quad (12.11)$$

such that the objective value is strictly positive, i.e. a solution

$$(y^*, (s_l^c)^*, (s_u^c)^*, (s_l^x)^*, (s_u^x)^*, (s_n^x)^*)$$

to (12.11) so that

$$(l^c)^T (s_l^c)^* - (u^c)^T (s_u^c)^* + (l^x)^T (s_l^x)^* - (u^x)^T (s_u^x)^* > 0.$$

Such a solution implies that (12.11) is unbounded, and that (12.7) is infeasible.

Dual Infeasible Problems

If the problem (12.8) is infeasible (has no feasible solution), **MOSEK** will report a certificate of dual infeasibility: The primal solution reported is the certificate of infeasibility, and the dual solution is undefined.

A certificate of dual infeasibility is a feasible solution to the modified primal problem

$$\begin{aligned} & \text{minimize} && c^T x \\ & \text{subject to} && \hat{l}^c \leq Ax \leq \hat{u}^c, \\ & && \hat{l}^x \leq x \leq \hat{u}^x, \\ & && x \in K, \end{aligned} \tag{12.12}$$

where

$$\hat{l}_i^c = \begin{cases} 0 & \text{if } l_i^c > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and} \quad \hat{u}_i^c := \begin{cases} 0 & \text{if } u_i^c < \infty, \\ \infty & \text{otherwise,} \end{cases} \tag{12.13}$$

and

$$\hat{l}_j^x = \begin{cases} 0 & \text{if } l_j^x > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and} \quad \hat{u}_j^x := \begin{cases} 0 & \text{if } u_j^x < \infty, \\ \infty & \text{otherwise,} \end{cases} \tag{12.14}$$

such that

$$c^T x < 0.$$

Such a solution implies that (12.12) is unbounded, and that (12.8) is infeasible.

In case that both the primal problem (12.7) and the dual problem (12.8) are infeasible, **MOSEK** will report only one of the two possible certificates — which one is not defined (**MOSEK** returns the first certificate found).

12.2.3 Minimalization vs. Maximalization

When the objective sense of problem (12.7) is maximization, i.e.

$$\begin{aligned} & \text{maximize} && c^T x + c^f \\ & \text{subject to} && l^c \leq Ax \leq u^c, \\ & && l^x \leq x \leq u^x, \\ & && x \in \mathcal{K}, \end{aligned}$$

the objective sense of the dual problem changes to minimization, and the domain of all dual variables changes sign in comparison to (12.2). The dual problem thus takes the form

$$\begin{aligned} & \text{minimize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ & \text{subject to} && A^T y + s_l^x - s_u^x + s_n^x = c, \\ & && -y + s_l^c - s_u^c = 0, \\ & && s_l^c, s_u^c, s_l^x, s_u^x \leq 0, \\ & && -s_n^x \in \mathcal{K}^* \end{aligned}$$

This means that the duality gap, defined in (12.9) as the primal minus the dual objective value, becomes nonpositive. It follows that the dual objective will always be greater than or equal to the primal objective. The primal infeasibility certificate will be reported by **MOSEK** as a solution to the system

$$\begin{aligned} & A^T y + s_l^x - s_u^x + s_n^x = 0, \\ & -y + s_l^c - s_u^c = 0, \\ & s_l^c, s_u^c, s_l^x, s_u^x \leq 0, \\ & -s_n^x \in \mathcal{K}^* \end{aligned} \tag{12.15}$$

such that the objective value is strictly negative

$$(l^c)^T (s_l^c)^* - (u^c)^T (s_u^c)^* + (l^x)^T (s_l^x)^* - (u^x)^T (s_u^x)^* < 0.$$

Similarly, the certificate of dual infeasibility is an x satisfying the requirements of (12.12) such that $c^T x > 0$.

12.3 Semidefinite Optimization

Semidefinite optimization is an extension of conic optimization (see Sec. 12.2) allowing positive semidefinite matrix variables to be used in addition to the usual scalar variables. All the other parts of the input are defined exactly as in Sec. 12.2, and the discussion from that section applies verbatim to all properties of problems with semidefinite variables. We only briefly indicate how the corresponding formulae should be modified with semidefinite terms.

A semidefinite optimization problem can be written as

$$\begin{aligned} & \text{minimize} && \sum_{j=0}^{n-1} c_j x_j + \sum_{j=0}^{p-1} \langle \bar{C}_j, \bar{X}_j \rangle + c^f \\ & \text{subject to} && \begin{aligned} l_i^c &\leq \sum_{j=0}^{n-1} a_{ij} x_j + \sum_{j=0}^{p-1} \langle \bar{A}_{ij}, \bar{X}_j \rangle && \leq u_i^c, \quad i = 0, \dots, m-1 \\ l_j^x &\leq x_j && \leq u_j^x, \quad j = 0, \dots, n-1 \end{aligned} \\ & && x \in \mathcal{K}, \\ & && \bar{X}_j \in \mathcal{S}_+^{r_j}, \quad j = 0, \dots, p-1 \end{aligned} \quad (12.16)$$

where the problem has p symmetric positive semidefinite variables $\bar{X}_j \in \mathcal{S}_+^{r_j}$ of dimension r_j with symmetric coefficient matrices $\bar{C}_j \in \mathcal{S}^{r_j}$ and $\bar{A}_{ij} \in \mathcal{S}^{r_j}$. We use standard notation for the matrix inner product, i.e., for $U, V \in \mathbb{R}^{m \times n}$ we have

$$\langle U, V \rangle := \sum_{i=0}^{m-1} \sum_{j=0}^{n-1} U_{ij} V_{ij}.$$

As always we write $A = (a_{i,j})$ for the linear coefficient matrix.

Duality

The definition of the dual problem (12.8) becomes:

$$\begin{aligned} & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ & \text{subject to} && \begin{aligned} A^T y + s_l^x - s_u^x + s_n^x &= c \\ -y + s_l^c - s_u^c &= 0, \\ \bar{C}_j - \sum_{i=0}^{m-1} y_i \bar{A}_{ij} &= \bar{S}_j, && j = 0, \dots, p-1 \\ s_l^c, s_u^c, s_l^x, s_u^x &\geq 0, \\ s_n^x &\in \mathcal{K}^*, \\ \bar{S}_j &\in \mathcal{S}_+^{r_j}, && j = 0, \dots, p-1. \end{aligned} \end{aligned} \quad (12.17)$$

The duality gap (12.9) is computed as:

$$\begin{aligned} & c^T x^* + c^f - \{ (l^c)^T (s_l^c)^* - (u^c)^T (s_u^c)^* + (l^x)^T (s_l^x)^* - (u^x)^T (s_u^x)^* + c^f \} \\ &= \sum_{i=0}^{m-1} [(s_l^c)^*_i ((x_i^c)^* - l_i^c) + (s_u^c)^*_i (u_i^c - (x_i^c)^*)] \\ &+ \sum_{j=0}^{n-1} [(s_l^x)^*_j (x_j - l_j^x) + (s_u^x)^*_j (u_j^x - x_j^*)] + \sum_{j=0}^{p-1} (s_n^x)^*_j x_j^* + \sum_{j=0}^{p-1} \langle \bar{X}_j, \bar{S}_j \rangle \geq 0. \end{aligned} \quad (12.18)$$

Complementarity conditions (12.10) include the additional relation:

$$\langle \bar{X}_j, \bar{S}_j \rangle = 0 \quad j = 0, \dots, p-1. \quad (12.19)$$

Infeasibility

A certificate of primal infeasibility (12.11) is now a feasible solution to:

$$\begin{aligned} & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x \\ & \text{subject to} && \begin{aligned} A^T y + s_l^x - s_u^x + s_n^x &= 0, \\ -y + s_l^c - s_u^c &= 0, \\ \sum_{i=0}^{m-1} y_i \bar{A}_{ij} + \bar{S}_j &= 0, && j = 0, \dots, p-1 \\ s_l^c, s_u^c, s_l^x, s_u^x &\geq 0, \\ s_n^x &\in \mathcal{K}^*, \\ \bar{S}_j &\in \mathcal{S}_+^{r_j}, && j = 0, \dots, p-1. \end{aligned} \end{aligned} \quad (12.20)$$

such that the objective value is strictly positive.

Similarly, a dual infeasibility certificate (12.12) is a feasible solution to

$$\begin{aligned}
& \text{minimize} && \sum_{j=0}^{n-1} c_j x_j + \sum_{j=0}^{p-1} \langle \overline{C}_j, \overline{X}_j \rangle \\
& \text{subject to} && \hat{l}_i^c \leq \sum_{j=0}^{n-1} a_{ij} x_j + \sum_{j=0}^{p-1} \langle \overline{A}_{ij}, \overline{X}_j \rangle \leq \hat{u}_i^c, \quad i = 0, \dots, m-1 \\
& && \hat{l}_j^x \leq x_j \leq \hat{u}_j^x, \quad j = 0, \dots, n-1 \\
& && x \in \mathcal{K}, \\
& && \overline{X}_j \in \mathcal{S}_+^{r_j}, \quad j = 0, \dots, p-1
\end{aligned} \tag{12.21}$$

where the modified bounds are as in (12.13) and (12.14) and the objective value is strictly negative.

12.4 Quadratic and Quadratically Constrained Optimization

A convex quadratic and quadratically constrained optimization problem has the form

$$\begin{aligned}
& \text{minimize} && \frac{1}{2} x^T Q^o x + c^T x + c^f \\
& \text{subject to} && l_k^c \leq \frac{1}{2} x^T Q^k x + \sum_{j=0}^{n-1} a_{kj} x_j \leq u_k^c, \quad k = 0, \dots, m-1, \\
& && l_j^x \leq x_j \leq u_j^x, \quad j = 0, \dots, n-1,
\end{aligned} \tag{12.22}$$

where all variables and bounds have the same meaning as for linear problems (see Sec. 12.1) and Q^o and all Q^k are symmetric matrices. Moreover, for convexity, Q^o must be a positive semidefinite matrix and Q^k must satisfy

$$\begin{aligned}
-\infty < l_k^c &\Rightarrow Q^k \text{ is negative semidefinite,} \\
u_k^c < \infty &\Rightarrow Q^k \text{ is positive semidefinite,} \\
-\infty < l_k^c \leq u_k^c < \infty &\Rightarrow Q^k = 0.
\end{aligned}$$

The convexity requirement is very important and **MOSEK** checks whether it is fulfilled.

12.4.1 A Recommendation

Any convex quadratic optimization problem can be reformulated as a conic quadratic optimization problem, see [Modeling Cookbook](#) and [And13]. In fact **MOSEK** does such conversion internally as a part of the solution process for the following reasons:

- the conic optimizer is numerically more robust than the one for quadratic problems.
- the conic optimizer is usually faster because quadratic cones are simpler than quadratic functions, even though the conic reformulation usually has more constraints and variables than the original quadratic formulation.
- it is easy to dualize the conic formulation if deemed worthwhile potentially leading to (huge) computational savings.

However, instead of relying on the automatic reformulation we recommend to formulate the problem as a conic problem from scratch because:

- it saves the computational overhead of the reformulation including the convexity check. A conic problem is convex by construction and hence no convexity check is needed for conic problems.
- usually the modeler can do a better reformulation than the automatic method because the modeler can exploit the knowledge of the problem at hand.

To summarize we recommend to formulate quadratic problems and in particular quadratically constrained problems directly in conic form.

12.4.2 Duality for Quadratic and Quadratically Constrained Optimization

The dual problem corresponding to the quadratic and quadratically constrained optimization problem (12.22) is given by

$$\begin{aligned}
& \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + \frac{1}{2} x^T \left\{ \sum_{k=0}^{m-1} y_k Q^k - Q^o \right\} x + c^f \\
& \text{subject to} && A^T y + s_l^x - s_u^x + \left\{ \sum_{k=0}^{m-1} y_k Q^k - Q^o \right\} x = c, \\
& && -y + s_l^c - s_u^c = 0, \\
& && s_l^c, s_u^c, s_l^x, s_u^x \geq 0.
\end{aligned} \tag{12.23}$$

The dual problem is related to the dual problem for linear optimization (see Sec. 12.1.1), but depends on the variable x which in general can not be eliminated. In the solutions reported by **MOSEK**, the value of x is the same for the primal problem (12.22) and the dual problem (12.23).

12.4.3 Infeasibility for Quadratic Optimization

In case **MOSEK** finds a problem to be infeasible it reports a certificate of infeasibility. We write them out explicitly for quadratic problems, that is when $Q^k = 0$ for all k and quadratic terms appear only in the objective Q^o . In this case the constraints both in the primal and dual problem are linear, and **MOSEK** produces for them the same infeasibility certificate as for linear problems.

The certificate of primal infeasibility is a solution to the problem (12.4) such that the objective value is strictly positive.

The certificate of dual infeasibility is a solution to the problem (12.5) together with an additional constraint

$$Q^o x = 0$$

such that the objective value is strictly negative.

Chapter 13

Optimizers

The most essential part of **MOSEK** are the optimizers:

- *primal simplex* (linear problems),
- *dual simplex* (linear problems),
- *interior-point* (linear, quadratic and conic problems),
- *mixed-integer* (problems with integer variables).

The structure of a successful optimization process is roughly:

- **Presolve**
 1. *Elimination*: Reduce the size of the problem.
 2. *Dualizer*: Choose whether to solve the primal or the dual form of the problem.
 3. *Scaling*: Scale the problem for better numerical stability.
- **Optimization**
 1. *Optimize*: Solve the problem using selected method.
 2. *Terminate*: Stop the optimization when specific termination criteria have been met.
 3. *Report*: Return the solution or an infeasibility certificate.

The preprocessing stage is transparent to the user, but useful to know about for tuning purposes. The purpose of the preprocessing steps is to make the actual optimization more efficient and robust. We discuss the details of the above steps in the following sections.

13.1 Presolve

Before an optimizer actually performs the optimization the problem is preprocessed using the so-called presolve. The purpose of the presolve is to

1. remove redundant constraints,
2. eliminate fixed variables,
3. remove linear dependencies,
4. substitute out (implied) free variables, and
5. reduce the size of the optimization problem in general.

After the presolved problem has been optimized the solution is automatically postsolved so that the returned solution is valid for the original problem. Hence, the presolve is completely transparent. For further details about the presolve phase, please see [\[AA95\]](#) and [\[AGMX96\]](#).

It is possible to fine-tune the behavior of the presolve or to turn it off entirely. If presolve consumes too much time or memory compared to the reduction in problem size gained it may be disabled. This is done by setting the parameter `MSK_IPAR_PRESOLVE_USE` to `MSK_PRESOLVE_MODE_OFF`. The two most time-consuming steps of the presolve are

- the eliminator, and
- the linear dependency check.

Therefore, in some cases it is worthwhile to disable one or both of these.

Numerical issues in the presolve

During the presolve the problem is reformulated so that it hopefully solves faster. However, in rare cases the presolved problem may be harder to solve than the original problem. The presolve may also be infeasible although the original problem is not. If it is suspected that presolved problem is much harder to solve than the original, we suggest to first turn the eliminator off by setting the parameter `MSK_IPAR_PRESOLVE_ELIMINATOR_MAX_NUM_TRIES` to 0. If that does not help, then trying to turn entire presolve off may help.

Since all computations are done in finite precision, the presolve employs some tolerances when concluding a variable is fixed or a constraint is redundant. If it happens that **MOSEK** incorrectly concludes a problem is primal or dual infeasible, then it is worthwhile to try to reduce the parameters `MSK_DPAR_PRESOLVE_TOL_X` and `MSK_DPAR_PRESOLVE_TOL_S`. However, if reducing the parameters actually helps then this should be taken as an indication that the problem is badly formulated.

Eliminator

The purpose of the eliminator is to eliminate free and implied free variables from the problem using substitution. For instance, given the constraints

$$\begin{aligned} y &= \sum_j x_j, \\ y, x &\geq 0, \end{aligned}$$

y is an implied free variable that can be substituted out of the problem, if deemed worthwhile. If the eliminator consumes too much time or memory compared to the reduction in problem size gained it may be disabled. This can be done by setting the parameter `MSK_IPAR_PRESOLVE_ELIMINATOR_MAX_NUM_TRIES` to 0. In rare cases the eliminator may cause that the problem becomes much hard to solve.

Linear dependency checker

The purpose of the linear dependency check is to remove linear dependencies among the linear equalities. For instance, the three linear equalities

$$\begin{aligned} x_1 + x_2 + x_3 &= 1, \\ x_1 + 0.5x_2 &= 0.5, \\ 0.5x_2 + x_3 &= 0.5. \end{aligned}$$

contain exactly one linear dependency. This implies that one of the constraints can be dropped without changing the set of feasible solutions. Removing linear dependencies is in general a good idea since it reduces the size of the problem. Moreover, the linear dependencies are likely to introduce numerical problems in the optimization phase. It is best practice to build models without linear dependencies, but that is not always easy for the user to control. If the linear dependencies are removed at the modeling stage, the linear dependency check can safely be disabled by setting the parameter `MSK_IPAR_PRESOLVE_LINDEP_USE` to `MSK_OFF`.

Dualizer

All linear, conic, and convex optimization problems have an equivalent dual problem associated with them. **MOSEK** has built-in heuristics to determine if it is more efficient to solve the primal or dual problem. The form (primal or dual) is displayed in the **MOSEK** log and available as an information item from the solver. Should the internal heuristics not choose the most efficient form of the problem it may be worthwhile to set the dualizer manually by setting the parameters:

- `MSK_IPAR_INTPTNT_SOLVE_FORM`: In case of the interior-point optimizer.
- `MSK_IPAR_SIM_SOLVE_FORM`: In case of the simplex optimizer.

Note that currently only linear and conic (but not semidefinite) problems may be automatically dualized.

Scaling

Problems containing data with large and/or small coefficients, say $1.0e+9$ or $1.0e-7$, are often hard to solve. Significant digits may be truncated in calculations with finite precision, which can result in the optimizer relying on inaccurate data. Since computers work in finite precision, extreme coefficients should be avoided. In general, data around the same *order of magnitude* is preferred, and we will refer to a problem, satisfying this loose property, as being *well-scaled*. If the problem is not well scaled, **MOSEK** will try to scale (multiply) constraints and variables by suitable constants. **MOSEK** solves the scaled problem to improve the numerical properties.

The scaling process is transparent, i.e. the solution to the original problem is reported. It is important to be aware that the optimizer terminates when the termination criterion is met on the scaled problem, therefore significant primal or dual infeasibilities may occur after unscaling for badly scaled problems. The best solution of this issue is to reformulate the problem, making it better scaled.

By default **MOSEK** heuristically chooses a suitable scaling. The scaling for interior-point and simplex optimizers can be controlled with the parameters `MSK_IPAR_INTPNT_SCALING` and `MSK_IPAR_SIM_SCALING` respectively.

13.2 Linear Optimization

13.2.1 Optimizer Selection

Two different types of optimizers are available for linear problems: The default is an interior-point method, and the alternative is the simplex method (primal or dual). The optimizer can be selected using the parameter `MSK_IPAR_OPTIMIZER`.

The Interior-point or the Simplex Optimizer?

Given a linear optimization problem, which optimizer is the best: the simplex or the interior-point optimizer? It is impossible to provide a general answer to this question. However, the interior-point optimizer behaves more predictably: it tends to use between 20 and 100 iterations, almost independently of problem size, but cannot perform warm-start. On the other hand the simplex method can take advantage of an initial solution, but is less predictable from cold-start. The interior-point optimizer is used by default.

The Primal or the Dual Simplex Variant?

MOSEK provides both a primal and a dual simplex optimizer. Predicting which simplex optimizer is faster is impossible, however, in recent years the dual optimizer has seen several algorithmic and computational improvements, which, in our experience, make it faster on average than the primal version. Still, it depends much on the problem structure and size. Setting the `MSK_IPAR_OPTIMIZER` parameter to `MSK_OPTIMIZER_FREE_SIMPLEX` instructs **MOSEK** to choose one of the simplex variants automatically.

To summarize, if you want to know which optimizer is faster for a given problem type, it is best to try all the options.

13.2.2 The Interior-point Optimizer

The purpose of this section is to provide information about the algorithm employed in the **MOSEK** interior-point optimizer for linear problems and about its termination criteria.

The homogeneous primal-dual problem

In order to keep the discussion simple it is assumed that **MOSEK** solves linear optimization problems of standard form

$$\begin{aligned} &\text{minimize} && c^T x \\ &\text{subject to} && Ax = b, \\ &&& x \geq 0. \end{aligned} \tag{13.1}$$

This is in fact what happens inside **MOSEK**; for efficiency reasons **MOSEK** converts the problem to standard form before solving, then converts it back to the input form when reporting the solution.

Since it is not known beforehand whether problem (13.1) has an optimal solution, is primal infeasible or is dual infeasible, the optimization algorithm must deal with all three situations. This is the reason why **MOSEK** solves the so-called homogeneous model

$$\begin{aligned} Ax - b\tau &= 0, \\ A^T y + s - c\tau &= 0, \\ -c^T x + b^T y - \kappa &= 0, \\ x, s, \tau, \kappa &\geq 0, \end{aligned} \tag{13.2}$$

where y and s correspond to the dual variables in (13.1), and τ and κ are two additional scalar variables. Note that the homogeneous model (13.2) always has solution since

$$(x, y, s, \tau, \kappa) = (0, 0, 0, 0, 0)$$

is a solution, although not a very interesting one. Any solution

$$(x^*, y^*, s^*, \tau^*, \kappa^*)$$

to the homogeneous model (13.2) satisfies

$$x_j^* s_j^* = 0 \text{ and } \tau^* \kappa^* = 0.$$

Moreover, there is always a solution that has the property $\tau^* + \kappa^* > 0$.

First, assume that $\tau^* > 0$. It follows that

$$\begin{aligned} A \frac{x^*}{\tau^*} &= b, \\ A^T \frac{y^*}{\tau^*} + \frac{s^*}{\tau^*} &= c, \\ -c^T \frac{x^*}{\tau^*} + b^T \frac{y^*}{\tau^*} &= 0, \\ x^*, s^*, \tau^*, \kappa^* &\geq 0. \end{aligned}$$

This shows that $\frac{x^*}{\tau^*}$ is a primal optimal solution and $(\frac{y^*}{\tau^*}, \frac{s^*}{\tau^*})$ is a dual optimal solution; this is reported as the optimal interior-point solution since

$$(x, y, s) = \left\{ \frac{x^*}{\tau^*}, \frac{y^*}{\tau^*}, \frac{s^*}{\tau^*} \right\}$$

is a primal-dual optimal solution (see Sec. 12.1 for the mathematical background on duality and optimality).

On other hand, if $\kappa^* > 0$ then

$$\begin{aligned} Ax^* &= 0, \\ A^T y^* + s^* &= 0, \\ -c^T x^* + b^T y^* &= \kappa^*, \\ x^*, s^*, \tau^*, \kappa^* &\geq 0. \end{aligned}$$

This implies that at least one of

$$c^T x^* < 0 \tag{13.3}$$

or

$$b^T y^* > 0 \tag{13.4}$$

is satisfied. If (13.3) is satisfied then x^* is a certificate of dual infeasibility, whereas if (13.4) is satisfied then y^* is a certificate of primal infeasibility.

In summary, by computing an appropriate solution to the homogeneous model, all information required for a solution to the original problem is obtained. A solution to the homogeneous model can be computed using a primal-dual interior-point algorithm [And09].

Interior-point Termination Criterion

For efficiency reasons it is not practical to solve the homogeneous model exactly. Hence, an exact optimal solution or an exact infeasibility certificate cannot be computed and a reasonable termination criterion has to be employed.

In the k -th iteration of the interior-point algorithm a trial solution

$$(x^k, y^k, s^k, \tau^k, \kappa^k)$$

to homogeneous model is generated, where

$$x^k, s^k, \tau^k, \kappa^k > 0.$$

Optimal case

Whenever the trial solution satisfies the criterion

$$\begin{aligned} \left\| A \frac{x^k}{\tau^k} - b \right\|_{\infty} &\leq \epsilon_p (1 + \|b\|_{\infty}), \\ \left\| A^T \frac{y^k}{\tau^k} + \frac{s^k}{\tau^k} - c \right\|_{\infty} &\leq \epsilon_d (1 + \|c\|_{\infty}), \text{ and} \\ \min \left(\frac{(x^k)^T s^k}{(\tau^k)^2}, \left| \frac{c^T x^k}{\tau^k} - \frac{b^T y^k}{\tau^k} \right| \right) &\leq \epsilon_g \max \left(1, \frac{\min(|c^T x^k|, |b^T y^k|)}{\tau^k} \right), \end{aligned} \quad (13.5)$$

the interior-point optimizer is terminated and

$$\frac{(x^k, y^k, s^k)}{\tau^k}$$

is reported as the primal-dual optimal solution. The interpretation of (13.5) is that the optimizer is terminated if

- $\frac{x^k}{\tau^k}$ is approximately primal feasible,
- $\left\{ \frac{y^k}{\tau^k}, \frac{s^k}{\tau^k} \right\}$ is approximately dual feasible, and
- the duality gap is almost zero.

Dual infeasibility certificate

On the other hand, if the trial solution satisfies

$$-\epsilon_i c^T x^k > \frac{\|c\|_{\infty}}{\max(1, \|b\|_{\infty})} \|Ax^k\|_{\infty}$$

then the problem is declared dual infeasible and x^k is reported as a certificate of dual infeasibility. The motivation for this stopping criterion is as follows: First assume that $\|Ax^k\|_{\infty} = 0$; then x^k is an exact certificate of dual infeasibility. Next assume that this is not the case, i.e.

$$\|Ax^k\|_{\infty} > 0,$$

and define

$$\bar{x} := \epsilon_i \frac{\max(1, \|b\|_{\infty})}{\|Ax^k\|_{\infty} \|c\|_{\infty}} x^k.$$

It is easy to verify that

$$\|A\bar{x}\|_{\infty} = \epsilon_i \frac{\max(1, \|b\|_{\infty})}{\|c\|_{\infty}} \text{ and } -c^T \bar{x} > 1,$$

which shows \bar{x} is an approximate certificate of dual infeasibility, where ϵ_i controls the quality of the approximation. A smaller value means a better approximation.

Primal infeasibility certificate

Finally, if

$$\epsilon_i b^T y^k > \frac{\|b\|_\infty}{\max(1, \|c\|_\infty)} \|A^T y^k + s^k\|_\infty$$

then y^k is reported as a certificate of primal infeasibility.

Adjusting optimality criteria

It is possible to adjust the tolerances ε_p , ε_d , ε_g and ε_i using parameters; see table for details.

Table 13.1: Parameters employed in termination criterion

ToleranceParameter	name
ε_p	<i>MSK_DPAR_INTPNT_TOL_PFEAS</i>
ε_d	<i>MSK_DPAR_INTPNT_TOL_DFEAS</i>
ε_g	<i>MSK_DPAR_INTPNT_TOL_REL_GAP</i>
ε_i	<i>MSK_DPAR_INTPNT_TOL_INFEAS</i>

The default values of the termination tolerances are chosen such that for a majority of problems appearing in practice it is not possible to achieve much better accuracy. Therefore, tightening the tolerances usually is not worthwhile. However, an inspection of (13.5) reveals that the quality of the solution depends on $\|b\|_\infty$ and $\|c\|_\infty$; the smaller the norms are, the better the solution accuracy.

The interior-point method as implemented by **MOSEK** will converge toward optimality and primal and dual feasibility at the same rate [And09]. This means that if the optimizer is stopped prematurely then it is very unlikely that either the primal or dual solution is feasible. Another consequence is that in most cases all the tolerances, ε_p , ε_d , ε_g and ε_i , have to be relaxed together to achieve an effect.

If the optimizer terminates without locating a solution that satisfies the termination criteria, for example because of a stall or other numerical issues, then it will check if the solution found up to that point satisfies the same criteria with all tolerances multiplied by the value of *MSK_DPAR_INTPNT_CO_TOL_NEAR_REL*. If this is the case, the solution is still declared as optimal.

The basis identification discussed in Sec. 13.2.2 requires an optimal solution to work well; hence basis identification should be turned off if the termination criterion is relaxed.

To conclude the discussion in this section, relaxing the termination criterion is usually not worthwhile.

Basis Identification

An interior-point optimizer does not return an optimal basic solution unless the problem has a unique primal and dual optimal solution. Therefore, the interior-point optimizer has an optional post-processing step that computes an optimal basic solution starting from the optimal interior-point solution. More information about the basis identification procedure may be found in [AY96]. In the following we provide an overall idea of the procedure.

There are some cases in which a basic solution could be more valuable:

- a basic solution is often more accurate than an interior-point solution,
- a basic solution can be used to warm-start the simplex algorithm in case of reoptimization,
- a basic solution is in general more sparse, i.e. more variables are fixed to zero. This is particularly appealing when solving continuous relaxations of mixed integer problems, as well as in all applications in which sparser solutions are preferred.

To illustrate how the basis identification routine works, we use the following trivial example:

$$\begin{aligned} &\text{minimize} && x + y \\ &\text{subject to} && x + y = 1, \\ &&& x, y \geq 0. \end{aligned}$$

It is easy to see that all feasible solutions are also optimal. In particular, there are two basic solutions, namely

$$\begin{aligned} (x_1^*, y_1^*) &= (1, 0), \\ (x_2^*, y_2^*) &= (0, 1). \end{aligned}$$

The interior point algorithm will actually converge to the center of the optimal set, i.e. to $(x^*, y^*) = (1/2, 1/2)$ (to see this in **MOSEK** deactivate *Presolve*).

In practice, when the algorithm gets close to the optimal solution, it is possible to construct in polynomial time an initial basis for the simplex algorithm from the current interior point solution. This basis is used to warm-start the simplex algorithm that will provide the optimal basic solution. In most cases the constructed basis is optimal, or very few iterations are required by the simplex algorithm to make it optimal and hence the final *clean-up* phase be short. However, for some cases of ill-conditioned problems the additional simplex clean up phase may take of lot a time.

By default **MOSEK** performs a basis identification. However, if a basic solution is not needed, the basis identification procedure can be turned off. The parameters

- `MSK_IPAR_INTPNT_BASIS`,
- `MSK_IPAR_BI_IGNORE_MAX_ITER`, and
- `MSK_IPAR_BI_IGNORE_NUM_ERROR`

control when basis identification is performed.

The type of simplex algorithm to be used (primal/dual) can be tuned with the parameter `MSK_IPAR_BI_CLEAN_OPTIMIZER`, and the maximum number of iterations can be set with `MSK_IPAR_BI_MAX_ITERATIONS`.

Finally, it should be mentioned that there is no guarantee on which basic solution will be returned.

The Interior-point Log

Below is a typical log output from the interior-point optimizer:

Optimizer	- threads	:	1						
Optimizer	- solved problem	:	the dual						
Optimizer	- Constraints	:	2						
Optimizer	- Cones	:	0						
Optimizer	- Scalar variables	:	6			conic	:	0	
Optimizer	- Semi-definite variables:	0				scalarized	:	0	
Factor	- setup time	:	0.00			dense det. time	:	0.00	
Factor	- ML order time	:	0.00			GP order time	:	0.00	
Factor	- nonzeros before factor	:	3			after factor	:	3	
Factor	- dense dim.	:	0			flops	:	7.00e+001	
ITE	PFEAS	DFEAS	GFEAS	PRSTATUS	POBJ	DOBJ	MU	TIME	
0	1.0e+000	8.6e+000	6.1e+000	1.00e+000	0.000000000e+000	-2.208000000e+003	1.0e+000	0.00	
1	1.1e+000	2.5e+000	1.6e-001	0.00e+000	-7.901380925e+003	-7.394611417e+003	2.5e+000	0.00	
2	1.4e-001	3.4e-001	2.1e-002	8.36e-001	-8.113031650e+003	-8.055866001e+003	3.3e-001	0.00	
3	2.4e-002	5.8e-002	3.6e-003	1.27e+000	-7.777530698e+003	-7.766471080e+003	5.7e-002	0.01	
4	1.3e-004	3.2e-004	2.0e-005	1.08e+000	-7.668323435e+003	-7.668207177e+003	3.2e-004	0.01	
5	1.3e-008	3.2e-008	2.0e-009	1.00e+000	-7.668000027e+003	-7.668000015e+003	3.2e-008	0.01	
6	1.3e-012	3.2e-012	2.0e-013	1.00e+000	-7.667999994e+003	-7.667999994e+003	3.2e-012	0.01	

The first line displays the number of threads used by the optimizer and the second line tells that the optimizer chose to solve the dual problem rather than the primal problem. The next line displays the problem dimensions as seen by the optimizer, and the `Factor...` lines show various statistics. This is followed by the iteration log.

Using the same notation as in [Sec. 13.2.2](#) the columns of the iteration log have the following meaning:

- **ITE:** Iteration index k .
- **PFEAS:** $\|Ax^k - b\tau^k\|_\infty$. The numbers in this column should converge monotonically towards zero but may stall at low level due to rounding errors.
- **DFEAS:** $\|A^T y^k + s^k - c\tau^k\|_\infty$. The numbers in this column should converge monotonically towards zero but may stall at low level due to rounding errors.
- **GFEAS:** $|-c^T x^k + b^T y^k - \kappa^k|$. The numbers in this column should converge monotonically towards zero but may stall at low level due to rounding errors.
- **PRSTATUS:** This number converges to 1 if the problem has an optimal solution whereas it converges to -1 if that is not the case.

- POBJ: $c^T x^k / \tau^k$. An estimate for the primal objective value.
- DOBJ: $b^T y^k / \tau^k$. An estimate for the dual objective value.
- MU: $\frac{(x^k)^T s^k + \tau^k \kappa^k}{n+1}$. The numbers in this column should always converge to zero.
- TIME: Time spent since the optimization started.

13.2.3 The Simplex Optimizer

An alternative to the interior-point optimizer is the simplex optimizer. The simplex optimizer uses a different method that allows exploiting an initial guess for the optimal solution to reduce the solution time. Depending on the problem it may be faster or slower to use an initial guess; see Sec. 13.2.1 for a discussion. **MOSEK** provides both a primal and a dual variant of the simplex optimizer.

Simplex Termination Criterion

The simplex optimizer terminates when it finds an optimal basic solution or an infeasibility certificate. A basic solution is optimal when it is primal and dual feasible; see Sec. 12.1 for a definition of the primal and dual problem. Due to the fact that computations are performed in finite precision **MOSEK** allows violations of primal and dual feasibility within certain tolerances. The user can control the allowed primal and dual tolerances with the parameters `MSK_DPAR_BASIS_TOL_X` and `MSK_DPAR_BASIS_TOL_S`.

Setting the parameter `MSK_IPAR_OPTIMIZER` to `MSK_OPTIMIZER_FREE_SIMPLEX` instructs **MOSEK** to select automatically between the primal and the dual simplex optimizers. Hence, **MOSEK** tries to choose the best optimizer for the given problem and the available solution. The same parameter can also be used to force one of the variants.

Starting From an Existing Solution

When using the simplex optimizer it may be possible to reuse an existing solution and thereby reduce the solution time significantly. When a simplex optimizer starts from an existing solution it is said to perform a *warm-start*. If the user is solving a sequence of optimization problems by solving the problem, making modifications, and solving again, **MOSEK** will warm-start automatically.

By default **MOSEK** uses presolve when performing a warm-start. If the optimizer only needs very few iterations to find the optimal solution it may be better to turn off the presolve.

Numerical Difficulties in the Simplex Optimizers

Though **MOSEK** is designed to minimize numerical instability, completely avoiding it is impossible when working in finite precision. **MOSEK** treats a “numerically unexpected behavior” event inside the optimizer as a *set-back*. The user can define how many set-backs the optimizer accepts; if that number is exceeded, the optimization will be aborted. Set-backs are a way to escape long sequences where the optimizer tries to recover from an unstable situation.

Examples of set-backs are: repeated singularities when factorizing the basis matrix, repeated loss of feasibility, degeneracy problems (no progress in objective) and other events indicating numerical difficulties. If the simplex optimizer encounters a lot of set-backs the problem is usually badly scaled; in such a situation try to reformulate it into a better scaled problem. Then, if a lot of set-backs still occur, trying one or more of the following suggestions may be worthwhile:

- Raise tolerances for allowed primal or dual feasibility: increase the value of
 - `MSK_DPAR_BASIS_TOL_X`, and
 - `MSK_DPAR_BASIS_TOL_S`.
- Raise or lower pivot tolerance: Change the `MSK_DPAR_SIMPLEX_ABS_TOL_PIV` parameter.
- Switch optimizer: Try another optimizer.
- Switch off crash: Set both `MSK_IPAR_SIM_PRIMAL_CRASH` and `MSK_IPAR_SIM_DUAL_CRASH` to 0.
- Experiment with other pricing strategies: Try different values for the parameters

- *MSK_IPAR_SIM_PRIMAL_SELECTION* and
- *MSK_IPAR_SIM_DUAL_SELECTION*.

- If you are using warm-starts, in rare cases switching off this feature may improve stability. This is controlled by the *MSK_IPAR_SIM_HOTSTART* parameter.
- Increase maximum number of set-backs allowed controlled by *MSK_IPAR_SIM_MAX_NUM_SETBACKS*.
- If the problem repeatedly becomes infeasible try switching off the special degeneracy handling. See the parameter *MSK_IPAR_SIM_DEGEN* for details.

The Simplex Log

Below is a typical log output from the simplex optimizer:

Optimizer	- solved problem	:	the primal			
Optimizer	- Constraints	:	667			
Optimizer	- Scalar variables	:	1424	conic	:	0
Optimizer	- hotstart	:	no			
ITER	DEGITER(%)	PFEAS	DFEAS	POBJ	DOBJ	TIME
↪	TOTTIME					
0	0.00	1.43e+05	NA	6.5584140832e+03	NA	0.00
↪	0.02					
1000	1.10	0.00e+00	NA	1.4588289726e+04	NA	0.13
↪	0.14					
2000	0.75	0.00e+00	NA	7.3705564855e+03	NA	0.21
↪	0.22					
3000	0.67	0.00e+00	NA	6.0509727712e+03	NA	0.29
↪	0.31					
4000	0.52	0.00e+00	NA	5.5771203906e+03	NA	0.38
↪	0.39					
4533	0.49	0.00e+00	NA	5.5018458883e+03	NA	0.42
↪	0.44					

The first lines summarize the problem the optimizer is solving. This is followed by the iteration log, with the following meaning:

- ITER: Number of iterations.
- DEGITER(%): Ratio of degenerate iterations.
- PFEAS: Primal feasibility measure reported by the simplex optimizer. The numbers should be 0 if the problem is primal feasible (when the primal variant is used).
- DFEAS: Dual feasibility measure reported by the simplex optimizer. The number should be 0 if the problem is dual feasible (when the dual variant is used).
- POBJ: An estimate for the primal objective value (when the primal variant is used).
- DOBJ: An estimate for the dual objective value (when the dual variant is used).
- TIME: Time spent since this instance of the simplex optimizer was invoked (in seconds).
- TOTTIME: Time spent since optimization started (in seconds).

13.3 Conic Optimization - Interior-point optimizer

For conic optimization problems only an interior-point type optimizer is available.

13.3.1 The homogeneous primal-dual problem

The interior-point optimizer is an implementation of the so-called homogeneous and self-dual algorithm. For a detailed description of the algorithm, please see [ART03]. In order to keep our discussion simple we will assume that **MOSEK** solves a conic optimization problem of the form:

$$\begin{aligned} & \text{minimize} && c^T x \\ & \text{subject to} && Ax = b, \\ & && x \in \mathcal{K} \end{aligned} \tag{13.6}$$

where \mathcal{K} is a convex cone. The corresponding dual problem is

$$\begin{aligned} & \text{maximize} && b^T y \\ & \text{subject to} && A^T y + s = c, \\ & && s \in \mathcal{K}^* \end{aligned} \tag{13.7}$$

where \mathcal{K}^* is the dual cone of \mathcal{K} . See Sec. 12.2 for definitions.

Since it is not known beforehand whether problem (13.6) has an optimal solution, is primal infeasible or is dual infeasible, the optimization algorithm must deal with all three situations. This is the reason that **MOSEK** solves the so-called homogeneous model

$$\begin{aligned} Ax - b\tau &= 0, \\ A^T y + s - c\tau &= 0, \\ -c^T x + b^T y - \kappa &= 0, \\ x &\in \mathcal{K}, \\ s &\in \mathcal{K}^*, \\ \tau, \kappa &\geq 0, \end{aligned} \tag{13.8}$$

where y and s correspond to the dual variables in (13.6), and τ and κ are two additional scalar variables. Note that the homogeneous model (13.8) always has a solution since

$$(x, y, s, \tau, \kappa) = (0, 0, 0, 0, 0)$$

is a solution, although not a very interesting one. Any solution

$$(x^*, y^*, s^*, \tau^*, \kappa^*)$$

to the homogeneous model (13.8) satisfies

$$(x^*)^T s^* + \tau^* \kappa^* = 0$$

i.e. complementarity. Observe that $x^* \in \mathcal{K}$ and $s^* \in \mathcal{K}^*$ implies

$$(x^*)^T s^* \geq 0$$

and therefore

$$\tau^* \kappa^* = 0.$$

since $\tau^*, \kappa^* \geq 0$. Hence, at least one of τ^* and κ^* is zero.

First, assume that $\tau^* > 0$ and hence $\kappa^* = 0$. It follows that

$$\begin{aligned} A \frac{x^*}{\tau^*} &= b, \\ A^T \frac{y^*}{\tau^*} + \frac{s^*}{\tau^*} &= c, \\ -c^T \frac{x^*}{\tau^*} + b^T \frac{y^*}{\tau^*} &= 0, \\ x^*/\tau^* &\in \mathcal{K}, \\ s^*/\tau^* &\in \mathcal{K}^*. \end{aligned}$$

This shows that $\frac{x^*}{\tau^*}$ is a primal optimal solution and $(\frac{y^*}{\tau^*}, \frac{s^*}{\tau^*})$ is a dual optimal solution; this is reported as the optimal interior-point solution since

$$(x, y, s) = \left(\frac{x^*}{\tau^*}, \frac{y^*}{\tau^*}, \frac{s^*}{\tau^*} \right)$$

is a primal-dual optimal solution.

On other hand, if $\kappa^* > 0$ then

$$\begin{aligned} Ax^* &= 0, \\ A^T y^* + s^* &= 0, \\ -c^T x^* + b^T y^* &= \kappa^*, \\ x^* &\in \mathcal{K}, \\ s^* &\in \mathcal{K}^*. \end{aligned}$$

This implies that at least one of

$$c^T x^* < 0 \quad (13.9)$$

or

$$b^T y^* > 0 \quad (13.10)$$

holds. If (13.9) is satisfied, then x^* is a certificate of dual infeasibility, whereas if (13.10) holds then y^* is a certificate of primal infeasibility.

In summary, by computing an appropriate solution to the homogeneous model, all information required for a solution to the original problem is obtained. A solution to the homogeneous model can be computed using a primal-dual interior-point algorithm [And09].

13.3.2 Interior-point Termination Criterion

Since computations are performed in finite precision, and for efficiency reasons, it is not possible to solve the homogeneous model exactly in general. Hence, an exact optimal solution or an exact infeasibility certificate cannot be computed and a reasonable termination criterion has to be employed.

In every iteration k of the interior-point algorithm a trial solution

$$(x^k, y^k, s^k, \tau^k, \kappa^k)$$

to the homogeneous model is generated, where

$$x^k \in \mathcal{K}, s^k \in \mathcal{K}^*, \tau^k, \kappa^k > 0.$$

Therefore, it is possible to compute the values:

$$\begin{aligned} \rho_p^k &= \arg \min_{\rho} \left\{ \rho \mid \left\| A \frac{x^k}{\tau^k} - b \right\|_{\infty} \leq \rho \varepsilon_p (1 + \|b\|_{\infty}) \right\}, \\ \rho_d^k &= \arg \min_{\rho} \left\{ \rho \mid \left\| A^T \frac{y^k}{\tau^k} + \frac{s^k}{\tau^k} - c \right\|_{\infty} \leq \rho \varepsilon_d (1 + \|c\|_{\infty}) \right\}, \\ \rho_g^k &= \arg \min_{\rho} \left\{ \rho \mid \left(\frac{(x^k)^T s^k}{(\tau^k)^2}, \left| \frac{c^T x^k}{\tau^k} - \frac{b^T y^k}{\tau^k} \right| \right) \leq \rho \varepsilon_g \max \left(1, \frac{\min(|c^T x^k|, |b^T y^k|)}{\tau^k} \right) \right\}, \\ \rho_{pi}^k &= \arg \min_{\rho} \left\{ \rho \mid \left\| A^T y^k + s^k \right\|_{\infty} \leq \rho \varepsilon_i b^T y^k, b^T y^k > 0 \right\} \text{ and} \\ \rho_{di}^k &= \arg \min_{\rho} \left\{ \rho \mid \left\| Ax^k \right\|_{\infty} \leq -\rho \varepsilon_i c^T x^k, c^T x^k < 0 \right\}. \end{aligned}$$

Note $\varepsilon_p, \varepsilon_d, \varepsilon_g$ and ε_i are nonnegative user specified tolerances.

Optimal Case

Observe ρ_p^k measures how far x^k/τ^k is from being a good approximate primal feasible solution. Indeed if $\rho_p^k \leq 1$, then

$$\left\| A \frac{x^k}{\tau^k} - b \right\|_{\infty} \leq \varepsilon_p (1 + \|b\|_{\infty}). \quad (13.11)$$

This shows the violations in the primal equality constraints for the solution x^k/τ^k is small compared to the size of b given ε_p is small.

Similarly, if $\rho_d^k \leq 1$, then $(y^k, s^k)/\tau^k$ is an approximate dual feasible solution. If in addition $\rho_g^k \leq 1$, then the solution $(x^k, y^k, s^k)/\tau^k$ is approximate optimal because the associated primal and dual objective values are almost identical.

In other words if $\max(\rho_p^k, \rho_d^k, \rho_g^k) \leq 1$, then

$$\frac{(x^k, y^k, s^k)}{\tau^k}$$

is an approximate optimal solution.

Dual Infeasibility Certificate

Next assume that $\rho_{di}^k \leq 1$ and hence

$$\|Ax^k\|_\infty \leq -\varepsilon_i c^T x^k \text{ and } -c^T x^k > 0$$

holds. Now in this case the problem is declared dual infeasible and x^k is reported as a certificate of dual infeasibility. The motivation for this stopping criterion is as follows. Let

$$\bar{x} := \frac{x^k}{-c^T x^k}$$

and it is easy to verify that

$$\|A\bar{x}\|_\infty \leq \varepsilon_i \text{ and } c^T \bar{x} = -1$$

which shows \bar{x} is an approximate certificate of dual infeasibility, where ε_i controls the quality of the approximation.

Primal Infeasibility Certificate

Next assume that $\rho_{pi}^k \leq 1$ and hence

$$\|A^T y^k + s^k\|_\infty \leq \varepsilon_i b^T y^k \text{ and } b^T y^k > 0$$

holds. Now in this case the problem is declared primal infeasible and (y^k, s^k) is reported as a certificate of primal infeasibility. The motivation for this stopping criterion is as follows. Let

$$\bar{y} := \frac{y^k}{b^T y^k} \text{ and } \bar{s} := \frac{s^k}{b^T y^k}$$

and it is easy to verify that

$$\|A^T \bar{y} + \bar{s}\|_\infty \leq \varepsilon_i \text{ and } b^T \bar{y} = 1$$

which shows (\bar{y}, \bar{s}) is an approximate certificate of dual infeasibility, where ε_i controls the quality of the approximation.

13.3.3 Adjusting optimality criteria

It is possible to adjust the tolerances ε_p , ε_d , ε_g and ε_i using parameters; see table for details.

Table 13.2: Parameters employed in termination criterion

ToleranceParameter	name
ε_p	<i>MSK_DPAR_INTPNT_CO_TOL_PFEAS</i>
ε_d	<i>MSK_DPAR_INTPNT_CO_TOL_DFEAS</i>
ε_g	<i>MSK_DPAR_INTPNT_CO_TOL_REL_GAP</i>
ε_i	<i>MSK_DPAR_INTPNT_CO_TOL_INFEAS</i>

The default values of the termination tolerances are chosen such that for a majority of problems appearing in practice it is not possible to achieve much better accuracy. Therefore, tightening the tolerances usually is not worthwhile. However, an inspection of (13.11) reveals that the quality of the solution depends on $\|b\|_\infty$ and $\|c\|_\infty$; the smaller the norms are, the better the solution accuracy.

The interior-point method as implemented by **MOSEK** will converge toward optimality and primal and dual feasibility at the same rate [And09]. This means that if the optimizer is stopped prematurely then it is very unlikely that either the primal or dual solution is feasible. Another consequence is that in most cases all the tolerances, ε_p , ε_d , ε_g and ε_i , have to be relaxed together to achieve an effect.

If the optimizer terminates without locating a solution that satisfies the termination criteria, for example because of a stall or other numerical issues, then it will check if the solution found up to that point satisfies the same criteria with all tolerances multiplied by the value of `MSK_DPAR_INTPNT_CO_TOL_NEAR_REL`. If this is the case, the solution is still declared as optimal.

To conclude the discussion in this section, relaxing the termination criterion is usually not worthwhile.

13.3.4 The Interior-point Log

Below is a typical log output from the interior-point optimizer:

Optimizer	- threads	:	20						
Optimizer	- solved problem	:	the primal						
Optimizer	- Constraints	:	1						
Optimizer	- Cones	:	2						
Optimizer	- Scalar variables	:	6	conic	:	6			
Optimizer	- Semi-definite variables:	0	scalarized	:	0				
Factor	- setup time	:	0.00	dense det. time	:	0.00			
Factor	- ML order time	:	0.00	GP order time	:	0.00			
Factor	- nonzeros before factor	:	1	after factor	:	1			
Factor	- dense dim.	:	0	flops	:	1.70e+01			
ITE	PFEAS	DFEAS	GFEAS	PRSTATUS	POBJ	DOBJ	MU	TIME	
0	1.0e+00	2.9e-01	3.4e+00	0.00e+00	2.414213562e+00	0.000000000e+00	1.0e+00	0.01	
1	2.7e-01	7.9e-02	2.2e+00	8.83e-01	6.969257574e-01	-9.685901771e-03	2.7e-01	0.01	
2	6.5e-02	1.9e-02	1.2e+00	1.16e+00	7.606090061e-01	6.046141322e-01	6.5e-02	0.01	
3	1.7e-03	5.0e-04	2.2e-01	1.12e+00	7.084385672e-01	7.045122560e-01	1.7e-03	0.01	
4	1.4e-08	4.2e-09	4.9e-08	1.00e+00	7.071067941e-01	7.071067599e-01	1.4e-08	0.01	

The first line displays the number of threads used by the optimizer and the second line tells that the optimizer chose to solve the dual problem rather than the primal problem. The next line displays the problem dimensions as seen by the optimizer, and the `Factor...` lines show various statistics. This is followed by the iteration log.

Using the same notation as in Sec. 13.3.1 the columns of the iteration log have the following meaning:

- ITE: Iteration index k .
- PFEAS: $\|Ax^k - b\tau^k\|_\infty$. The numbers in this column should converge monotonically towards zero but may stall at low level due to rounding errors.
- DFEAS: $\|A^T y^k + s^k - c\tau^k\|_\infty$. The numbers in this column should converge monotonically towards zero but may stall at low level due to rounding errors.
- GFEAS: $|-c^T x^k + b^T y^k - \kappa^k|$. The numbers in this column should converge monotonically towards zero but may stall at low level due to rounding errors.
- PRSTATUS: This number converges to 1 if the problem has an optimal solution whereas it converges to -1 if that is not the case.
- POBJ: $c^T x^k / \tau^k$. An estimate for the primal objective value.
- DOBJ: $b^T y^k / \tau^k$. An estimate for the dual objective value.
- MU: $\frac{(x^k)^T s^k + \tau^k \kappa^k}{n+1}$. The numbers in this column should always converge to zero.
- TIME: Time spent since the optimization started (in seconds).

13.4 The Optimizer for Mixed-integer Problems

A problem is a mixed-integer optimization problem when one or more of the variables are constrained to be integer valued. Readers unfamiliar with integer optimization are recommended to consult some relevant literature, e.g. the book [Wol98] by Wolsey.

13.4.1 The Mixed-integer Optimizer Overview

MOSEK can solve mixed-integer

- linear,
- quadratic and quadratically constrained, and
- conic

problems, except for mixed-integer semidefinite problems. The mixed-integer optimizer is specialized for solving linear and conic optimization problems. Pure quadratic and quadratically constrained problems are automatically converted to conic form.

By default the mixed-integer optimizer is run-to-run deterministic. This means that if a problem is solved twice on the same computer with identical parameter settings and no time limit then the obtained solutions will be identical. If a time limit is set then this may not be case since the time taken to solve a problem is not deterministic. The mixed-integer optimizer is parallelized i.e. it can exploit multiple cores during the optimization.

The solution process can be split into these phases:

1. **Presolve:** See [Sec. 13.1](#).
2. **Cut generation:** Valid inequalities (cuts) are added to improve the lower bound.
3. **Heuristic:** Using heuristics the optimizer tries to guess a good feasible solution. Heuristics can be controlled by the parameter `MSK_IPAR_MIO_HEURISTIC_LEVEL`.
4. **Search:** The optimal solution is located by branching on integer variables.

13.4.2 Relaxations and bounds

It is important to understand that, in a worst-case scenario, the time required to solve integer optimization problems grows exponentially with the size of the problem (solving mixed-integer problems is NP-hard). For instance, a problem with n binary variables, may require time proportional to 2^n . The value of 2^n is huge even for moderate values of n .

In practice this implies that the focus should be on computing a near-optimal solution quickly rather than on locating an optimal solution. Even if the problem is only solved approximately, it is important to know how far the approximate solution is from an optimal one. In order to say something about the quality of an approximate solution the concept of *relaxation* is important.

Consider for example a mixed-integer optimization problem

$$\begin{aligned} z^* = \quad & \text{minimize} && c^T x \\ & \text{subject to} && Ax = b, \\ & && x \geq 0 \\ & && x_j \in \mathbb{Z}, \quad \forall j \in \mathcal{J}. \end{aligned} \tag{13.12}$$

It has the continuous relaxation

$$\begin{aligned} \underline{z} = \quad & \text{minimize} && c^T x \\ & \text{subject to} && Ax = b, \\ & && x \geq 0 \end{aligned} \tag{13.13}$$

obtained simply by ignoring the integrality restrictions. The relaxation is a continuous problem, and therefore much faster to solve to optimality with a linear (or, in the general case, conic) optimizer. We call the optimal value \underline{z} the *objective bound*. The objective bound \underline{z} normally increases during the solution search process when the continuous relaxation is gradually refined.

Moreover, if \hat{x} is any feasible solution to (13.12) and

$$\bar{z} := c^T \hat{x}$$

then

$$\underline{z} \leq z^* \leq \bar{z}.$$

These two inequalities allow us to estimate the quality of the integer solution: it is no further away from the optimum than $\bar{z} - \underline{z}$ in terms of the objective value. Whenever a mixed-integer problem is solved **MOSEK** reports this lower bound so that the quality of the reported solution can be evaluated.

13.4.3 Outer approximation for mixed-integer conic problems

The relaxations of mixed integer conic problems can be solved either as a nonlinear problem with the interior point algorithm (default) or with a linear outer approximation algorithm. The type of relaxation used can be set with `MSK_IPAR_MIO_CONIC_OUTER_APPROXIMATION`. The best value for this option is highly problem dependent.

13.4.4 Randomization

A number of internal algorithms of the mixed-integer solver are dependent on random tie-breaking. The random tie-breaking can have a significant impact on the path taken by the algorithm and the optimal solution returned. The random seed can be set with the parameter `MSK_IPAR_MIO_SEED`.

13.4.5 Termination Criterion

In general, it is time consuming to find an exact feasible and optimal solution to an integer optimization problem, though in many practical cases it may be possible to find a sufficiently good solution. The issue of terminating the mixed-integer optimizer is rather delicate and the user has numerous possibilities of influencing it with various parameters. The mixed-integer optimizer employs a relaxed feasibility and optimality criterion to determine when a satisfactory solution is located.

A candidate solution that is feasible for the continuous relaxation is said to be an *integer feasible solution* if the criterion

$$\min(x_j - \lfloor x_j \rfloor, \lceil x_j \rceil - x_j) \leq \delta_1 \quad \forall j \in \mathcal{J}$$

is satisfied, meaning that x_j is at most δ_1 from the nearest integer.

Whenever the integer optimizer locates an integer feasible solution it will check if the criterion

$$\bar{z} - \underline{z} \leq \max(\delta_2, \delta_3 \max(\delta_4, |\bar{z}|))$$

is satisfied. If this is the case, the integer optimizer terminates and reports the integer feasible solution as an optimal solution.

All the δ tolerances discussed above can be adjusted using suitable parameters — see [Table 13.3](#).

Table 13.3: Tolerances for the mixed-integer optimizer.

Tolerance	Parameter name
δ_1	<code>MSK_DPAR_MIO_TOL_ABS_RELAX_INT</code>
δ_2	<code>MSK_DPAR_MIO_TOL_ABS_GAP</code>
δ_3	<code>MSK_DPAR_MIO_TOL_REL_GAP</code>
δ_4	<code>MSK_DPAR_MIO_REL_GAP_CONST</code>

In [Table 13.4](#) some other common parameters affecting the integer optimizer termination criterion are shown.

Table 13.4: Other parameters affecting the integer optimizer termination criterion.

Parameter name	Explanation
<code>MSK_IPAR_MIO_MAX_NUM_BRANCHES</code>	Maximum number of branches allowed.
<code>MSK_IPAR_MIO_MAX_NUM_RELAXS</code>	Maximum number of relaxations allowed.
<code>MSK_IPAR_MIO_MAX_NUM_SOLUTIONS</code>	Maximum number of feasible integer solutions allowed.

13.4.6 Speeding Up the Solution Process

As mentioned previously, in many cases it is not possible to find an optimal solution to an integer optimization problem in a reasonable amount of time. Some suggestions to reduce the solution time are:

- Relax the termination criterion: In case the run time is not acceptable, the first thing to do is to relax the termination criterion — see [Sec. 13.4.5](#) for details.

- Specify a good initial solution: In many cases a good feasible solution is either known or easily computed using problem-specific knowledge. If a good feasible solution is known, it is usually worthwhile to use this as a starting point for the integer optimizer. See [Sec. 6.7.2](#).
- Improve the formulation: A mixed-integer optimization problem may be impossible to solve in one form and quite easy in another form. However, it is beyond the scope of this manual to discuss good formulations for mixed-integer problems. For discussions on this topic see for example [\[Wol98\]](#).

13.4.7 Understanding Solution Quality

To determine the quality of the solution one should check the following:

- The problem status and solution status returned by **MOSEK**, as well as constraint violations in case of suboptimal solutions.
- The *optimality gap* defined as

$$\epsilon = |(\text{objective value of feasible solution}) - (\text{objective bound})| = |\bar{z} - \underline{z}|.$$

which measures how much the located solution can deviate from the optimal solution to the problem. The optimality gap can be retrieved through the information item `MSK_DINF_MIO_OBJ_ABS_GAP`. Often it is more meaningful to look at the relative optimality gap normalized against the magnitude of the solution.

$$\epsilon_{\text{rel}} = \frac{|\bar{z} - \underline{z}|}{\max(\delta_4, |\bar{z}|)}.$$

The relative optimality gap is available in the information item `MSK_DINF_MIO_OBJ_REL_GAP`.

13.4.8 The Mixed-integer Log

Below is a typical log output from the mixed-integer optimizer:

```
Presolved problem: 6573 variables, 35728 constraints, 101258 non-zeros
Presolved problem: 0 general integer, 4294 binary, 2279 continuous
Clique table size: 1636
BRANCHES RELAXS  ACT_NDS  DEPTH    BEST_INT_OBJ      BEST_RELAX_OBJ      REL_GAP(%)  TIME
0           1        0        0        NA                1.8218819866e+07     NA           1.6
0           1        0        0        1.8331557950e+07   1.8218819866e+07     0.61         3.5
0           1        0        0        1.8300507546e+07   1.8218819866e+07     0.45         4.3
Cut generation started.
0           2        0        0        1.8300507546e+07   1.8218819866e+07     0.45         5.3
Cut generation terminated. Time = 1.43
0           3        0        0        1.8286893047e+07   1.8231580587e+07     0.30         7.5
15          18        1        0        1.8286893047e+07   1.8231580587e+07     0.30         10.5
31          34        1        0        1.8286893047e+07   1.8231580587e+07     0.30         11.1
51          54        1        0        1.8286893047e+07   1.8231580587e+07     0.30         11.6
91          94        1        0        1.8286893047e+07   1.8231580587e+07     0.30         12.4
171         174        1        0        1.8286893047e+07   1.8231580587e+07     0.30         14.3
331         334        1        0        1.8286893047e+07   1.8231580587e+07     0.30         17.9

[ ... ]

Objective of best integer solution : 1.825846762609e+07
Best objective bound                : 1.823311032986e+07
Construct solution objective        : Not employed
Construct solution # roundings      : 0
User objective cut value            : 0
Number of cuts generated            : 117
  Number of Gomory cuts              : 108
  Number of CMIR cuts                : 9
```

(continues on next page)

(continued from previous page)

Number of branches	: 4425
Number of relaxations solved	: 4410
Number of interior point iterations	: 25
Number of simplex iterations	: 221131

The first lines contain a summary of the problem as seen by the optimizer. This is followed by the iteration log. The columns have the following meaning:

- BRANCHES: Number of branches generated.
- RELAXS: Number of relaxations solved.
- ACT_NDS: Number of active branch bound nodes.
- DEPTH: Depth of the recently solved node.
- BEST_INT_OBJ: The best integer objective value, \bar{z} .
- BEST_RELAX_OBJ: The best objective bound, \underline{z} .
- REL_GAP(%): Relative optimality gap, $100\% \cdot \epsilon_{\text{rel}}$
- TIME: Time (in seconds) from the start of optimization.

Following that a summary of the optimization process is printed.

Chapter 14

Additional features

In this section we describe additional features and tools which enable more detailed analysis of optimization problems with **MOSEK**.

14.1 Problem Analyzer

The problem analyzer prints a survey of the structure of the problem, with information about linear constraints and objective, quadratic constraints, conic constraints and variables.

In the initial stages of model formulation the problem analyzer may be used as a quick way of verifying that the model has been built or imported correctly. In later stages it can help revealing special structures within the model that may be used to tune the optimizer's performance or to identify the causes of numerical difficulties.

The problem analyzer is run using *MSK_analyzeproblem*. It prints its output to a log stream. The output is similar to the one below (this is the problem survey of the **aflow30a** problem from the MIPLIB 2003 collection).

Analyzing the problem					
*** Structural report					
Dimensions					
	Constraints	Variables	Matrix var.	Cones	
	479	842	0	0	
Constraint and bound types					
	Free	Lower	Upper	Ranged	Fixed
Constraints:	0	0	421	0	58
Variables:	0	0	0	842	0
Integer constraint types					
	Binary	General			
	421	0			
*** Data report					
	Nonzeros	Min	Max		
cj :	421	1.1e+01	5.0e+02		
Aij :	2091	1.0e+00	1.0e+02		
	# finite	Min	Max		
blci :	58	1.0e+00	1.0e+01		
buci :	479	0.0e+00	1.0e+01		
blxj :	842	0.0e+00	0.0e+00		
buxj :	842	1.0e+00	1.0e+02		
*** Done analyzing the problem					

The survey is divided into a structural and numerical report. The content should be self-explanatory.

14.2 Automatic Repair of Infeasible Problems

MOSEK provides an automatic repair tool for infeasible linear problems which we cover in this section. Note that most infeasible models are so due to bugs which can (and should) be more reliably fixed manually, using the knowledge of the model structure. We discuss this approach in [Sec. 8.3](#).

14.2.1 Automatic repair

The main idea can be described as follows. Consider the linear optimization problem with m constraints and n variables

$$\begin{array}{ll} \text{minimize} & c^T x + c^f \\ \text{subject to} & \begin{array}{ll} l^c & \leq Ax \leq u^c, \\ l^x & \leq x \leq u^x, \end{array} \end{array}$$

which is assumed to be infeasible.

One way of making the problem feasible is to reduce the lower bounds and increase the upper bounds. If the change is sufficiently large the problem becomes feasible. Now an obvious idea is to compute the optimal relaxation by solving an optimization problem. The problem

$$\begin{array}{ll} \text{minimize} & p(v_l^c, v_u^c, v_l^x, v_u^x) \\ \text{subject to} & \begin{array}{ll} l^c & \leq Ax + v_l^c - v_u^c \leq u^c, \\ l^x & \leq x + v_l^x - v_u^x \leq u^x, \\ & v_l^c, v_u^c, v_l^x, v_u^x \geq 0 \end{array} \end{array} \quad (14.1)$$

does exactly that. The additional variables $(v_l^c)_i$, $(v_u^c)_i$, $(v_l^x)_j$ and $(v_u^x)_j$ are *elasticity* variables because they allow a constraint to be violated and hence add some elasticity to the problem. For instance, the elasticity variable $(v_l^c)_i$ controls how much the lower bound $(l^c)_i$ should be relaxed to make the problem feasible. Finally, the so-called penalty function

$$p(v_l^c, v_u^c, v_l^x, v_u^x)$$

is chosen so it penalizes changes to bounds. Given the weights

- $w_l^c \in \mathbb{R}^m$ (associated with l^c),
- $w_u^c \in \mathbb{R}^m$ (associated with u^c),
- $w_l^x \in \mathbb{R}^n$ (associated with l^x),
- $w_u^x \in \mathbb{R}^n$ (associated with u^x),

a natural choice is

$$p(v_l^c, v_u^c, v_l^x, v_u^x) = (w_l^c)^T v_l^c + (w_u^c)^T v_u^c + (w_l^x)^T v_l^x + (w_u^x)^T v_u^x.$$

Hence, the penalty function $p()$ is a weighted sum of the elasticity variables and therefore the problem (14.1) keeps the amount of relaxation at a minimum. Please observe that

- the problem (14.1) is always feasible.
- a negative weight implies problem (14.1) is unbounded. For this reason if the value of a weight is negative **MOSEK** fixes the associated elasticity variable to zero. Clearly, if one or more of the weights are negative, it may imply that it is not possible to repair the problem.

A simple choice of weights is to set them all to 1, but of course that does not take into account that constraints may have different importance.

Caveats

Observe if the infeasible problem

$$\begin{array}{lll} \text{minimize} & x + z \\ \text{subject to} & x & = -1, \\ & x & \geq 0 \end{array}$$

is repaired then it will become unbounded. Hence, a repaired problem may not have an optimal solution.

Another and more important caveat is that only a minimal repair is performed i.e. the repair that barely makes the problem feasible. Hence, the repaired problem is barely feasible and that sometimes makes the repaired problem hard to solve.

Using the automatic repair tool

In this subsection we consider an infeasible linear optimization example:

$$\begin{array}{llll} \text{minimize} & -10x_1 & -9x_2, \\ \text{subject to} & 7/10x_1 + 1x_2 & \leq 630, \\ & 1/2x_1 + 5/6x_2 & \leq 600, \\ & 1x_1 + 2/3x_2 & \leq 708, \\ & 1/10x_1 + 1/4x_2 & \leq 135, \\ & x_1, & x_2 & \geq 0, \\ & & x_2 & \geq 650. \end{array} \quad (14.2)$$

The function *MSK_primalrepair* can be used to repair an infeasible problem. This can be used for linear and conic optimization problems, possibly with integer variables.

Listing 14.1: An example of feasibility repair applied to problem (14.2).

```
#include <math.h>
#include <stdio.h>

#include "mosek.h"

static void MSKAPI printstr(void *handle,
                             const char str[])
{
    fputs(str, stdout);
} /* printstr */

static const char * feasrepair_lp =
"minimize                                     \n"
" obj: - 10 x1 - 9 x2                         \n"
"st                                           \n"
" c1: + 7e-01 x1 + x2 <= 630                 \n"
" c2: + 5e-01 x1 + 8.333333333e-01 x2 <= 600 \n"
" c3: + x1 + 6.66666667e-01 x2 <= 708        \n"
" c4: + 1e-01 x1 + 2.5e-01 x2 <= 135         \n"
"bounds                                     \n"
"x2 >= 650                                  \n"
"end                                         \n";

int main(int argc, const char *argv[])
{
    MSKenv_t    env;
    MSKrescodee r, trmcode;
    MSKtask_t    task;

    r = MSK_makeenv(&env, NULL);
```

(continues on next page)

(continued from previous page)

```
if (r == MSK_RES_OK)
    r = MSK_makeemptytask(env, &task);

if (r == MSK_RES_OK)
    MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);

if (r == MSK_RES_OK)
    r = MSK_readlpstring(task,feasrepair_lp); /* Read problem from string */

if (r == MSK_RES_OK)
    r = MSK_putintparam(task, MSK_IPAR_LOG_FEAS_REPAIR, 3);

if (r == MSK_RES_OK)
{
    /* Weights are NULL implying all weights are 1. */
    r = MSK_primalrepair(task, NULL, NULL, NULL, NULL);
}

if (r == MSK_RES_OK)
{
    double sum_viol;

    r = MSK_getdouinf(task, MSK_DINF_PRIMAL_REPAIR_PENALTY_OBJ, &sum_viol);

    if (r == MSK_RES_OK)
    {
        printf("Minimized sum of violations = %e\n", sum_viol);

        r = MSK_optimizetrm(task, &trmcode); /* Optimize the repaired task. */

        MSK_solutionsummary(task, MSK_STREAM_MSG);
    }
}

printf("Return code: %d\n", r);

return (r);
}
```

The above code will produce the following log report:

```
MOSEK Version 9.0.0.25(ALPHA) (Build date: 2017-11-7 16:11:50)
Copyright (c) MOSEK ApS, Denmark. WWW: mosek.com
Platform: Linux/64-X86
```

```
Open file 'feasrepair.lp'
Reading started.
Reading terminated. Time: 0.00
```

Read summary

```
  Type           : LO (linear optimization problem)
Objective sense  : min
Scalar variables : 2
Matrix variables : 0
Constraints      : 4
Cones           : 0
Time            : 0.0
```

Problem

```
  Name           :
Objective sense  : min
Type            : LO (linear optimization problem)
```

(continues on next page)

(continued from previous page)

```
Constraints      : 4
Cones           : 0
Scalar variables : 2
Matrix variables : 0
Integer variables : 0

Primal feasibility repair started.
Optimizer started.
Presolve started.
Linear dependency checker started.
Linear dependency checker terminated.
Eliminator started.
Freed constraints in eliminator : 2
Eliminator terminated.
Eliminator - tries          : 1          time           : 0.00
Lin. dep. - tries          : 1          time           : 0.00
Lin. dep. - number         : 0

Presolve terminated. Time: 0.00
Problem
  Name                :
  Objective sense      : min
  Type                 : LO (linear optimization problem)
  Constraints           : 8
  Cones                : 0
  Scalar variables     : 14
  Matrix variables     : 0
  Integer variables    : 0

Optimizer - threads          : 20
Optimizer - solved problem   : the primal
Optimizer - Constraints      : 2
Optimizer - Cones           : 0
Optimizer - Scalar variables : 5          conic           : 0
Optimizer - Semi-definite variables: 0      scalarized        : 0
Factor - setup time         : 0.00        dense det. time   : 0.00
Factor - ML order time      : 0.00        GP order time     : 0.00
Factor - nonzeros before factor : 3        after factor      : 3
Factor - dense dim.         : 0          flops             : 5.00e+01
ITE PFEAS   DFEAS   GFEAS   PRSTATUS   POBJ          DOBJ          MU          TIME
0  2.7e+01  1.0e+00  4.0e+00  1.00e+00  3.000000000e+00  0.000000000e+00  1.0e+00  0.00
1  2.5e+01  9.1e-01  1.4e+00  0.00e+00  8.711262850e+00  1.115287830e+01  2.4e+00  0.00
2  2.4e+00  8.8e-02  1.4e-01  -7.33e-01  4.062505701e+01  4.422203730e+01  2.3e-01  0.00
3  9.4e-02  3.4e-03  5.5e-03  1.33e+00  4.250700434e+01  4.258548510e+01  9.1e-03  0.00
4  2.0e-05  7.2e-07  1.1e-06  1.02e+00  4.249996599e+01  4.249998669e+01  1.9e-06  0.00
5  2.0e-09  7.2e-11  1.1e-10  1.00e+00  4.250000000e+01  4.250000000e+01  1.9e-10  0.00
Basis identification started.
Basis identification terminated. Time: 0.00
Optimizer terminated. Time: 0.01

Basic solution summary
  Problem status : PRIMAL_AND_DUAL_FEASIBLE
  Solution status : OPTIMAL
  Primal.  obj: 4.250000000e+01   nrm: 6e+02   Viol.  con: 1e-13   var: 0e+00
  Dual.    obj: 4.249999999e+01   nrm: 2e+00   Viol.  con: 0e+00   var: 9e-11
Optimal objective value of the penalty problem: 4.250000000000e+01

Repairing bounds.
Increasing the upper bound 1.35e+02 on constraint 'c4' (3) with 2.25e+01.
Decreasing the lower bound 6.50e+02 on variable 'x2' (4) with 2.00e+01.
Primal feasibility repair terminated.
Optimizer started.
```

(continues on next page)

```
Optimizer terminated. Time: 0.00
```

Interior-point solution summary

```
Problem status : PRIMAL_AND_DUAL_FEASIBLE
```

```
Solution status : OPTIMAL
```

```
Primal.  obj: -5.6700000000e+03   nrm: 6e+02   Viol.  con: 0e+00   var: 0e+00
```

```
Dual.    obj: -5.6700000000e+03   nrm: 1e+01   Viol.  con: 0e+00   var: 0e+00
```

Basic solution summary

```
Problem status : PRIMAL_AND_DUAL_FEASIBLE
```

```
Solution status : OPTIMAL
```

```
Primal.  obj: -5.6700000000e+03   nrm: 6e+02   Viol.  con: 0e+00   var: 0e+00
```

```
Dual.    obj: -5.6700000000e+03   nrm: 1e+01   Viol.  con: 0e+00   var: 0e+00
```

Optimizer summary

Optimizer	-	time: 0.00
Interior-point	- iterations : 0	time: 0.00
Basis identification	-	time: 0.00
Primal	- iterations : 0	time: 0.00
Dual	- iterations : 0	time: 0.00
Clean primal	- iterations : 0	time: 0.00
Clean dual	- iterations : 0	time: 0.00
Simplex	-	time: 0.00
Primal simplex	- iterations : 0	time: 0.00
Dual simplex	- iterations : 0	time: 0.00
Mixed integer	- relaxations: 0	time: 0.00

It will also modify the task according to the optimal elasticity variables found. In this case the optimal repair it is to increase the upper bound on constraint `c4` by 22.5 and decrease the lower bound on variable `x2` by 20.

14.3 Sensitivity Analysis

Given an optimization problem it is often useful to obtain information about how the optimal objective value changes when the problem parameters are perturbed. E.g, assume that a bound represents the capacity of a machine. Now, it may be possible to expand the capacity for a certain cost and hence it is worthwhile knowing what the value of additional capacity is. This is precisely the type of questions the sensitivity analysis deals with.

Analyzing how the optimal objective value changes when the problem data is changed is called *sensitivity analysis*.

References

The book [Chv83] discusses the classical sensitivity analysis in Chapter 10 whereas the book [RTV97] presents a modern introduction to sensitivity analysis. Finally, it is recommended to read the short paper [Wal00] to avoid some of the pitfalls associated with sensitivity analysis.

Warning: Currently, sensitivity analysis is only available for continuous linear optimization problems. Moreover, **MOSEK** can only deal with perturbations of bounds and objective function coefficients.

14.3.1 Sensitivity Analysis for Linear Problems

The Optimal Objective Value Function

Assume that we are given the problem

$$\begin{aligned} z(l^c, u^c, l^x, u^x, c) = & \text{minimize} && c^T x \\ & \text{subject to} && l^c \leq Ax \leq u^c, \\ & && l^x \leq x \leq u^x, \end{aligned} \quad (14.3)$$

and we want to know how the optimal objective value changes as l_i^c is perturbed. To answer this question we define the perturbed problem for l_i^c as follows

$$\begin{aligned} f_{l_i^c}(\beta) = & \text{minimize} && c^T x \\ & \text{subject to} && l^c + \beta e_i \leq Ax \leq u^c, \\ & && l^x \leq x \leq u^x, \end{aligned}$$

where e_i is the i -th column of the identity matrix. The function

$$f_{l_i^c}(\beta) \quad (14.4)$$

shows the optimal objective value as a function of β . Please note that a change in β corresponds to a perturbation in l_i^c and hence (14.4) shows the optimal objective value as a function of varying l_i^c with the other bounds fixed.

It is possible to prove that the function (14.4) is a piecewise linear and convex function, i.e. its graph may look like in Fig. 14.1 and Fig. 14.2.




Fig. 14.1: $\beta = 0$ is in the interior of linearity interval.

Clearly, if the function $f_{l_i^c}(\beta)$ does not change much when β is changed, then we can conclude that the optimal objective value is insensitive to changes in l_i^c . Therefore, we are interested in the rate of change in $f_{l_i^c}(\beta)$ for small changes in β — specifically the gradient

$$f'_{l_i^c}(0),$$

which is called the *shadow price* related to l_i^c . The shadow price specifies how the objective value changes for small changes of β around zero. Moreover, we are interested in the *linearity interval*

$$\beta \in [\beta_1, \beta_2]$$



Fig. 14.2: $\beta = 0$ is a breakpoint.

for which

$$f'_{l_i^c}(\beta) = f'_{l_i^c}(0).$$

Since $f_{l_i^c}$ is not a smooth function $f'_{l_i^c}$ may not be defined at 0, as illustrated in Fig. 14.2. In this case we can define a left and a right shadow price and a left and a right linearity interval.

The function $f_{l_i^c}$ considered only changes in l_i^c . We can define similar functions for the remaining parameters of the z defined in (14.3) as well:

$$\begin{aligned} f_{l_i^c}(\beta) &= z(l^c + \beta e_i, u^c, l^x, u^x, c), & i = 1, \dots, m, \\ f_{u_i^c}(\beta) &= z(l^c, u^c + \beta e_i, l^x, u^x, c), & i = 1, \dots, m, \\ f_{l_j^x}(\beta) &= z(l^c, u^c, l^x + \beta e_j, u^x, c), & j = 1, \dots, n, \\ f_{u_j^x}(\beta) &= z(l^c, u^c, l^x, u^x + \beta e_j, c), & j = 1, \dots, n, \\ f_{c_j}(\beta) &= z(l^c, u^c, l^x, u^x, c + \beta e_j), & j = 1, \dots, n. \end{aligned}$$

Given these definitions it should be clear how linearity intervals and shadow prices are defined for the parameters u_i^c etc.

Equality Constraints

In **MOSEK** a constraint can be specified as either an equality constraint or a ranged constraint. If some constraint e_i^c is an equality constraint, we define the optimal value function for this constraint as

$$f_{e_i^c}(\beta) = z(l^c + \beta e_i, u^c + \beta e_i, l^x, u^x, c)$$

Thus for an equality constraint the upper and the lower bounds (which are equal) are perturbed simultaneously. Therefore, **MOSEK** will handle sensitivity analysis differently for a ranged constraint with $l_i^c = u_i^c$ and for an equality constraint.

The Basis Type Sensitivity Analysis

The classical sensitivity analysis discussed in most textbooks about linear optimization, e.g. [Chv83], is based on an optimal basis. This method may produce misleading results [RTV97] but is computationally cheap. This is the type of sensitivity analysis implemented in **MOSEK**.

We will now briefly discuss the basis type sensitivity analysis. Given an optimal basic solution which provides a partition of variables into basic and non-basic variables, the basis type sensitivity analysis

computes the linearity interval $[\beta_1, \beta_2]$ so that the basis remains optimal for the perturbed problem. A shadow price associated with the linearity interval is also computed. However, it is well-known that an optimal basic solution may not be unique and therefore the result depends on the optimal basic solution employed in the sensitivity analysis. If the optimal objective value function has a breakpoint for $\beta = 0$ then the basis type sensitivity method will only provide a subset of either the left or the right linearity interval.

In summary, the basis type sensitivity analysis is computationally cheap but does not provide complete information. Hence, the results of the basis type sensitivity analysis should be used with care.

Example: Sensitivity Analysis

As an example we will use the following transportation problem. Consider the problem of minimizing the transportation cost between a number of production plants and stores. Each plant supplies a number of goods and each store has a given demand that must be met. Supply, demand and cost of transportation per unit are shown in Fig. 14.3.




Fig. 14.3: Supply, demand and cost of transportation.

If we denote the number of transported goods from location i to location j by x_{ij} , problem can be formulated as the linear optimization problem of minimizing

$$1x_{11} + 2x_{12} + 5x_{23} + 2x_{24} + 1x_{31} + 2x_{33} + 1x_{34}$$

subject to

$$\begin{array}{rclcl}
 x_{11} & + & x_{12} & & \leq & 400, \\
 & & & x_{23} & + & x_{24} & \leq & 1200, \\
 & & & & x_{31} & + & x_{33} & + & x_{34} & \leq & 1000, \\
 x_{11} & & & & & + & x_{31} & & & = & 800, \\
 & x_{12} & & & & & & & & = & 100, \\
 & & x_{23} & + & & & & x_{33} & & = & 500, \\
 & & & x_{24} & + & & & & & = & 500, \\
 x_{11}, & x_{12}, & x_{23}, & x_{24}, & x_{31}, & x_{33}, & x_{34} & \geq & 0.
 \end{array} \tag{14.5}$$

The sensitivity parameters are shown in Table 14.1 and Table 14.2.

Table 14.1: Ranges and shadow prices related to bounds on constraints and variables.

Con.	β_1	β_2	σ_1	σ_2
1	-300.00	0.00	3.00	3.00
2	-700.00	$+\infty$	0.00	0.00
3	-500.00	0.00	3.00	3.00
4	-0.00	500.00	4.00	4.00
5	-0.00	300.00	5.00	5.00
6	-0.00	700.00	5.00	5.00
7	-500.00	700.00	2.00	2.00
Var.	β_1	β_2	σ_1	σ_2
x_{11}	$-\infty$	300.00	0.00	0.00
x_{12}	$-\infty$	100.00	0.00	0.00
x_{23}	$-\infty$	0.00	0.00	0.00
x_{24}	$-\infty$	500.00	0.00	0.00
x_{31}	$-\infty$	500.00	0.00	0.00
x_{33}	$-\infty$	500.00	0.00	0.00
x_{34}	-0.000000	500.00	2.00	2.00

Table 14.2: Ranges and shadow prices related to the objective coefficients.

Var.	β_1	β_2	σ_1	σ_2
c_1	$-\infty$	3.00	300.00	300.00
c_2	$-\infty$	∞	100.00	100.00
c_3	-2.00	∞	0.00	0.00
c_4	$-\infty$	2.00	500.00	500.00
c_5	-3.00	∞	500.00	500.00
c_6	$-\infty$	2.00	500.00	500.00
c_7	-2.00	∞	0.00	0.00

Examining the results from the sensitivity analysis we see that for constraint number 1 we have $\sigma_1 = 3$ and $\beta_1 = -300$, $\beta_2 = 0$.

If the upper bound on constraint 1 is decreased by

$$\beta \in [0, 300]$$

then the optimal objective value will increase by the value

$$\sigma_1 \beta = 3\beta.$$

14.3.2 Sensitivity Analysis with MOSEK

MOSEK provides the functions *MSK_primalsensitivity* and *MSK_dualsensitivity* for performing sensitivity analysis. The code in Listing 14.2 gives an example of its use.

Listing 14.2: Example of sensitivity analysis with the **MOSEK** Optimizer API for C.

```
#include <stdio.h>

#include "mosek.h" /* Include the MOSEK definition file. */
```

(continues on next page)

(continued from previous page)

```
static void MSKAPI printstr(void *handle,  
                           const char str[])  
{  
    printf("%s", str);  
} /* printstr */  
  
int main(int argc, char *argv[])  
{  
    const MSKint32t numcon = 7,  
                  numvar = 7;  
    MSKint32t      i, j;  
    MSKboundkeye   bkc[] = {MSK_BK_UP, MSK_BK_UP, MSK_BK_UP, MSK_BK_FX,  
                          MSK_BK_FX, MSK_BK_FX, MSK_BK_FX  
                          };  
    MSKboundkeye   bkx[] = {MSK_BK_LO, MSK_BK_LO, MSK_BK_LO,  
                          MSK_BK_LO, MSK_BK_LO, MSK_BK_LO, MSK_BK_LO  
                          };  
    MSKint32t      ptrb[] = {0, 2, 4, 6, 8, 10, 12};  
    MSKint32t      ptre[] = {2, 4, 6, 8, 10, 12, 14};  
    MSKint32t      sub[] = {0, 3, 0, 4, 1, 5, 1, 6, 2, 3, 2, 5, 2, 6};  
    MSKrealt       blc[] = {-MSK_INFINITY, -MSK_INFINITY, -MSK_INFINITY, 800, 100, 500, 500};  
    MSKrealt       buc[] = {400,          1200,          1000,          800, 100, 500, 500};  
    MSKrealt       c[]   = {1.0, 2.0, 5.0, 2.0, 1.0, 2.0, 1.0};  
    MSKrealt       blx[] = {0.0, 0.0, 0.0, 0.0, 0.0, 0.0, 0.0};  
    MSKrealt       bux[] = {MSK_INFINITY, MSK_INFINITY, MSK_INFINITY, MSK_INFINITY,  
                          MSK_INFINITY, MSK_INFINITY, MSK_INFINITY  
                          };  
    MSKrealt       val[] = {1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.  
→ 0};  
    MSKrescodee     r;  
  
    MSKenv_t        env;  
    MSKtask_t       task;  
  
    /* Create mosek environment. */  
    r = MSK_makeenv(&env, NULL);  
  
    if (r == MSK_RES_OK)  
    {  
        /* Make the optimization task. */  
        r = MSK_makeemptytask(env, &task);  
  
        if (r == MSK_RES_OK)  
        {  
            /* Directs the log task stream to the user  
             specified procedure 'printstr'. */  
  
            MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);  
  
            MSK_echotask(task,  
                        MSK_STREAM_MSG,  
                        "Defining the problem data.\n");  
        }  
  
        /* Append the constraints. */  
        if (r == MSK_RES_OK)  
            r = MSK_appendcons(task, numcon);  
  
        /* Append the variables. */  
        if (r == MSK_RES_OK)
```

(continues on next page)

```

    r = MSK_appendvars(task, numvar);

    /* Put C. */
    if (r == MSK_RES_OK)
        r = MSK_putcfix(task, 0.0);

    if (r == MSK_RES_OK)
        r = MSK_putcslice(task, 0, numvar, c);

    /* Put constraint bounds. */
    if (r == MSK_RES_OK)
        r = MSK_putconboundslice(task, 0, numcon, bkc, blc, buc);

    /* Put variable bounds. */
    if (r == MSK_RES_OK)
        r = MSK_putvarboundslice(task, 0, numvar, bkc, blc, buc);

    /* Put A. */
    if (r == MSK_RES_OK)
        r = MSK_putacolslice(task, 0, numvar, ptrb, pre, sub, val);

    if (r == MSK_RES_OK)
        r = MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MINIMIZE);

    if (r == MSK_RES_OK)
        r = MSK_optimizetrm(task, NULL);

    if (r == MSK_RES_OK)
    {
        /* Analyze upper bound on c1 and the equality constraint on c4 */
        MSKint32t subi[] = {0, 3};
        MSKmarke marki[] = {MSK_MARK_UP, MSK_MARK_UP};

        /* Analyze lower bound on the variables x12 and x31 */
        MSKint32t subj[] = {1, 4};
        MSKmarke markj[] = {MSK_MARK_LO, MSK_MARK_LO};

        MSKrealt leftpricei[2];
        MSKrealt rightpricei[2];
        MSKrealt leftrangei[2];
        MSKrealt rightrangei[2];
        MSKrealt leftpricej[2];
        MSKrealt rightpricej[2];
        MSKrealt leftrangej[2];
        MSKrealt rightrangej[2];

        r = MSK_primalsensitivity(task,
                                2,
                                subi,
                                marki,
                                2,
                                subj,
                                markj,
                                leftpricei,
                                rightpricei,
                                leftrangei,
                                rightrangei,
                                leftpricej,
                                rightpricej,
                                leftrangej,
                                rightrangej);
    }

```

```

printf("Results from sensitivity analysis on bounds:\n");

printf("For constraints:\n");
for (i = 0; i < 2; ++i)
    printf("leftprice = %e, rightprice = %e, leftrange = %e, rightrange = %e\n",
           leftpricei[i], rightpricei[i], leftrangei[i], rightrangei[i]);

printf("For variables:\n");
for (i = 0; i < 2; ++i)
    printf("leftprice = %e, rightprice = %e, leftrange = %e, rightrange = %e\n",
           leftpricej[i], rightpricej[i], leftrangej[i], rightrangej[i]);
}

if (r == MSK_RES_OK)
{
    MSKint32t subj[] = {2, 5};
    MSKrealt leftprice[2];
    MSKrealt rightprice[2];
    MSKrealt leftrange[2];
    MSKrealt rightrange[2];

    r = MSK_dualsensitivity(task,
                           2,
                           subj,
                           leftprice,
                           rightprice,
                           leftrange,
                           rightrange
                           );

    printf("Results from sensitivity analysis on objective coefficients:\n");

    for (i = 0; i < 2; ++i)
        printf("leftprice = %e, rightprice = %e, leftrange = %e, rightrange = %e\n",
               leftprice[i], rightprice[i], leftrange[i], rightrange[i]);
}

MSK_deletetask(&task);
}

MSK_deleteenv(&env);

printf("Return code: %d (0 means no error occurred.)\n", r);
return (r);
} /* main */

```

Chapter 15

API Reference

This section contains the complete reference of the **MOSEK** Optimizer API for C. It is organized as follows:

- *General API conventions.*
- **Functions:**
 - *Full list*
 - *Browse by topic*
- **Optimizer parameters:**
 - *Double, Integer, String*
 - *Full list*
 - *Browse by topic*
- **Optimizer information items:**
 - *Double, Integer, Long*
- *Optimizer response codes*
- *Constants*
- *User-defined function types*
- *Simple data types*
- *Nonlinear API (SCopt, DGopt, EXPopt)*

15.1 API Conventions

15.1.1 Function arguments

Naming Convention

In the definition of the **MOSEK** Optimizer API for C a consistent naming convention has been used. This implies that whenever for example `numcon` is an argument in a function definition it indicates the number of constraints. In Table 15.1 the variable names used to specify the problem parameters are listed.

Table 15.1: Naming conventions used in the **MOSEK** Optimizer API for C.

API name	API type	Dimension	Related problem parameter
numcon	int		m
numvar	int		n
numcone	int		t
aptrb	int []	numvar	a_{ij}
aptre	int []	numvar	a_{ij}
asub	int []	aptre[numvar-1]	a_{ij}
aval	double []	aptre[numvar-1]	a_{ij}
c	double []	numvar	c_j
cfix	double		c^f
blc	double []	numcon	l_k^c
buc	double []	numcon	u_k^c
blx	double []	numvar	l_k^x
bux	double []	numvar	u_k^x
numqonz	int		q_{ij}^o
qosubi	int []	numqonz	q_{ij}^o
qosubj	int []	numqonz	q_{ij}^o
qoval	double*	numqonz	q_{ij}^o
numqcnz	int		q_{ij}^k
qsubk	int []	numqcnz	q_{ij}^k
qsubi	int []	numqcnz	q_{ij}^k
qsubj	int []	numqcnz	q_{ij}^k
qcval	double*	numqcnz	q_{ij}^k
bkc	MSKboundkey*	numcon	l_k^c and u_k^c
bkx	MSKboundkey*	numvar	l_k^x and u_k^x

The relation between the variable names and the problem parameters is as follows:

- The quadratic terms in the objective: $q_{qosubi[t],qosubj[t]}^o = qoval[t]$, $t = 0, \dots, numqonz - 1$.
- The linear terms in the objective : $c_j = c[j]$, $j = 0, \dots, numvar - 1$
- The fixed term in the objective : $c^f = cfix$.
- The quadratic terms in the constraints: $q_{qsubi[t],qsubj[t]}^{qsubk[t]} = qcval[t]$, $t = 0, \dots, numqcnz - 1$
- The linear terms in the constraints: $a_{asub[t],j} = aval[t]$, $t = ptrb[j], \dots, ptre[j] - 1$, $j = 0, \dots, numvar - 1$

Passing arguments by reference

An argument described as **T** *by reference* indicates that the function interprets its given argument as a reference to a variable of type **T**. This usually means that the argument is used to output or update a value of type **T**. For example, suppose we have a function documented as

```
MSKrescodee MSK_foo (... , int * nzc, ...)
```

- **nzc** (**int** *by reference*) – The number of nonzero elements in the matrix. (output)

Then it could be called as follows.

```
int nzc;
MSK_foo (... , &nzc, ...)
printf("The number of nonzero elements: %d\n", nzc)
```

Information about input/output arguments

The following are purely informational tags which indicate how **MOSEK** treats a specific function argument.

- (input) An input argument. It is used to input data to **MOSEK**.
- (output) An output argument. It can be a user-preallocated data structure, a reference, a string buffer etc. where **MOSEK** will output some data.
- (input/output) An input/output argument. **MOSEK** will read the data and overwrite it with new/updated information.

15.1.2 Bounds

The bounds on the constraints and variables are specified using the variables **bkc**, **blc**, and **buc**. The components of the integer array **bkc** specify the bound type according to [Table 15.2](#)

Table 15.2: Symbolic key for variable and constraint bounds.

Symbolic constant	Lower bound	Upper bound
<i>MSK_BK_FX</i>	finite	identical to the lower bound
<i>MSK_BK_FR</i>	minus infinity	plus infinity
<i>MSK_BK_LO</i>	finite	plus infinity
<i>MSK_BK_RA</i>	finite	finite
<i>MSK_BK_UP</i>	minus infinity	finite

For instance **bkc[2]=*MSK_BK_LO*** means that $-\infty < l_2^c$ and $u_2^c = \infty$. Even if a variable or constraint is bounded only from below, e.g. $x \geq 0$, both bounds are inputted or extracted; the irrelevant value is ignored.

Finally, the numerical values of the bounds are given by

$$l_k^c = \text{blc}[\mathbf{k}], \quad k = 0, \dots, \text{numcon} - 1$$

$$u_k^c = \text{buc}[\mathbf{k}], \quad k = 0, \dots, \text{numcon} - 1.$$

The bounds on the variables are specified using the variables **blk**, **blx**, and **bux** in the same way. The numerical values for the lower bounds on the variables are given by

$$l_j^x = \text{blk}[\mathbf{j}], \quad j = 0, \dots, \text{numvar} - 1.$$

$$u_j^x = \text{bux}[\mathbf{j}], \quad j = 0, \dots, \text{numvar} - 1.$$

15.1.3 Vector Formats

Three different vector formats are used in the **MOSEK** API:

Full (dense) vector

This is simply an array where the first element corresponds to the first item, the second element to the second item etc. For example to get the linear coefficients of the objective in **task** with **numvar** variables, one would write

```
MSKrealt * c = MSK_calloc(task, numvar, sizeof(MSKrealt));

if ( c )
    res = MSK_getc(task,c);
else
    printf("Out of space\n");
```

Vector slice

A vector slice is a range of values from **first** up to and **not including last** entry in the vector, i.e. for the set of indices i such that $\text{first} \leq i < \text{last}$. For example, to get the bounds associated with constraints 2 through 9 (both inclusive) one would write

```
MSKrealt * upper_bound = MSK_calloc(task,8,sizeof(MSKrealt));
MSKrealt * lower_bound = MSK_calloc(task,8,sizeof(MSKrealt));
MSKboundkey * bound_key = MSK_calloc(task,8,sizeof(MSKboundkey));
res = MSK_getconboundslice(task, 2,10,
                           bound_key,lower_bound,upper_bound);
```

Sparse vector

A sparse vector is given as an array of indexes and an array of values. The indexes need not be ordered. For example, to input a set of bounds associated with constraints number 1, 6, 3, and 9, one might write

```
MSKint32t bound_index[] = { 1, 6, 3, 9 };
MSKboundkey bound_key[] = { MSK_BK_FR, MSK_BK_LO, MSK_BK_UP, MSK_BK_FX };
MSKrealt lower_bound[] = { 0.0, -10.0, 0.0, 5.0 };
MSKrealt upper_bound[] = { 0.0, 0.0, 6.0, 5.0 };

res = MSK_putconboundlist(task, 4, bound_index,
                          bound_key,lower_bound,upper_bound);
```

15.1.4 Matrix Formats

The coefficient matrices in a problem are inputted and extracted in a sparse format. That means only the nonzero entries are listed.

Unordered Triplets

In unordered triplet format each entry is defined as a row index, a column index and a coefficient. For example, to input the A matrix coefficients for $a_{1,2} = 1.1$, $a_{3,3} = 4.3$, and $a_{5,4} = 0.2$, one would write as follows:

```
MSKint32t subi[] = { 1, 3, 5 },
             subj[] = { 2, 3, 4 };
MSKrealt cof[] = { 1.1, 4.3, 0.2 };

res = MSK_putaijlist(task,3, subi,subj,cof);
```

Please note that in some cases (like *MSK_putaijlist*) *only* the specified indexes are modified — all other are unchanged. In other cases (such as *MSK_putqconk*) the triplet format is used to modify *all* entries — entries that are not specified are set to 0.

Column or Row Ordered Sparse Matrix

In a sparse matrix format only the non-zero entries of the matrix are stored. **MOSEK** uses a sparse packed matrix format ordered either by columns or rows. Here we describe the column-wise format. The row-wise format is based on the same principle.

Column ordered sparse format

A sparse matrix in column ordered format is essentially a list of all non-zero entries read column by column from left to right and from top to bottom within each column. The exact representation uses four arrays:

- **asub**: Array of size equal to the number of nonzeros. List of row indexes.

- **aval**: Array of size equal to the number of nonzeros. List of non-zero entries of A ordered by columns.
- **ptrb**: Array of size `numcol`, where `ptrb[j]` is the position of the first value/index in **aval**/**asub** for the j -th column.
- **ptre**: Array of size `numcol`, where `ptre[j]` is the position of the last value/index plus one in **aval**/**asub** for the j -th column.

With this representation the values of a matrix A with `numcol` columns are assigned using:

$$a_{\text{asub}[k],j} = \text{aval}[k] \quad \text{for } j = 0, \dots, \text{numcol} - 1, \quad k = \text{ptrb}[j], \dots, \text{ptre}[j] - 1.$$

As an example consider the matrix

$$A = \begin{bmatrix} 1.1 & & 1.3 & 1.4 & & \\ & 2.2 & & & 2.5 & \\ 3.1 & & & 3.4 & & \\ & & 4.4 & & & \end{bmatrix} \quad (15.1)$$

which can be represented in the column ordered sparse matrix format as

$$\begin{aligned} \text{ptrb} &= [0, 2, 3, 5, 7], \\ \text{ptre} &= [2, 3, 5, 7, 8], \\ \text{asub} &= [0, 2, 1, 0, 3, 0, 2, 1], \\ \text{aval} &= [1.1, 3.1, 2.2, 1.3, 4.4, 1.4, 3.4, 2.5]. \end{aligned}$$

Fig. 15.1 illustrates how the matrix A in (15.1) is represented in column ordered sparse matrix format.




Fig. 15.1: The matrix A (15.1) represented in column ordered packed sparse matrix format.

Column ordered sparse format with nonzeros

Note that `nzc[j] := pre[j] - ptrb[j]` is exactly the number of nonzero elements in the j -th column of A . In some functions a sparse matrix will be represented using the equivalent dataset **asub**, **aval**, **ptrb**, **nzc**. The matrix A (15.1) would now be represented as:

$$\begin{aligned} \text{ptrb} &= [0, 2, 3, 5, 7], \\ \text{nzc} &= [2, 1, 2, 2, 1], \\ \text{asub} &= [0, 2, 1, 0, 3, 0, 2, 1], \\ \text{aval} &= [1.1, 3.1, 2.2, 1.3, 4.4, 1.4, 3.4, 2.5]. \end{aligned}$$

Row ordered sparse matrix

The matrix A (15.1) can also be represented in the row ordered sparse matrix format as:

$$\begin{aligned} \text{ptrb} &= [0, 3, 5, 7], \\ \text{pre} &= [3, 5, 7, 8], \\ \text{asub} &= [0, 2, 3, 1, 4, 0, 3, 2], \\ \text{aval} &= [1.1, 1.3, 1.4, 2.2, 2.5, 3.1, 3.4, 4.4]. \end{aligned}$$

15.2 Functions grouped by topic

Callback

- *MSK_linkfunctotaskstream* – Connects a user-defined function to a task stream.
- *MSK_putcallbackfunc* – Input the progress callback function.
- Infrequent: *MSK_getcallbackfunc*, *MSK_linkfunctoenvstream*, *MSK_putexitfunc*, *MSK_putresponsefunc*, *MSK_unlinkfuncfromenvstream*, *MSK_unlinkfuncfromtaskstream*

Environment and task management

- *MSK_clonetask* – Creates a clone of an existing task.
- *MSK_deleteenv* – Delete a MOSEK environment.
- *MSK_deletetask* – Deletes a task.
- *MSK_makeenv* – Creates a new MOSEK environment.
- *MSK_maketask* – Creates a new task.
- *MSK_puttaskname* – Assigns a new name to the task.
- Infrequent: *MSK_commitchanges*, *MSK_deletesolution*, *MSK_getenv*, *MSK_makeemptytask*, *MSK_makeenvalloc*, *MSK_putmaxnumanz*, *MSK_putmaxnumbarvar*, *MSK_putmaxnumcon*, *MSK_putmaxnumcone*, *MSK_putmaxnumqnz*, *MSK_putmaxnumvar*, *MSK_resizetask*

Infeasibility diagnostic

- *MSK_getinfeasiblesubproblem* – Obtains an infeasible subproblem.
- *MSK_primalrepair* – Repairs a primal infeasible optimization problem by adjusting the bounds on the constraints and variables.

Information items and statistics

- *MSK_getdoublinf* – Obtains a double information item.
- *MSK_getintinf* – Obtains an integer information item.
- *MSK_getlintinf* – Obtains a long integer information item.
- *MSK_updatesolutioninfo* – Update the information items related to the solution.
- Infrequent: *MSK_getinfindex*, *MSK_getinfmax*, *MSK_getinfname*, *MSK_getnadouinf*, *MSK_getnaintinf*

Input/Output

- *MSK_readdata* – Reads problem data from a file.
- *MSK_writedata* – Writes problem data to a file.
- *MSK_writesolution* – Write a solution to a file.
- Infrequent: *MSK_echotask*, *MSK_readdataautoformat*, *MSK_readdataformat*, *MSK_readjsonstring*, *MSK_readlpstring*, *MSK_readopfstring*, *MSK_readparamfile*, *MSK_readptfstring*, *MSK_readsolution*, *MSK_readsummary*, *MSK_readtask*, *MSK_writejsonsol*, *MSK_writeparamfile*, *MSK_writetask*

Inspecting the task

- *MSK_analyzeproblem* – Analyze the data of a task.
- *MSK_getnumcon* – Obtains the number of constraints.
- *MSK_getnumcone* – Obtains the number of cones.
- *MSK_getnumvar* – Obtains the number of variables.
- *Infrequent:* *MSK_analyzesolution*, *MSK_getacol*, *MSK_getacolnumnz*, *MSK_getacolslice*, *MSK_getacolslice64*, *MSK_getacolslicenumnz*, *MSK_getacolslicenumnz64*, *MSK_getacolslicetrip*, *MSK_getaij*, *MSK_getapiecennumnz*, *MSK_getarow*, *MSK_getarownumnz*, *MSK_getarowslice*, *MSK_getarowslice64*, *MSK_getarowslicenumnz*, *MSK_getarowslicenumnz64*, *MSK_getarowslicetrip*, *MSK_getbarablocktriplet*, *MSK_getbaraidx*, *MSK_getbaraidxij*, *MSK_getbaraidxinfo*, *MSK_getbarasparsity*, *MSK_getbarcbblocktriplet*, *MSK_getbarcidx*, *MSK_getbarcidxinfo*, *MSK_getbarcidxj*, *MSK_getbarcsparsity*, *MSK_getbarvarname*, *MSK_getbarvarnameindex*, *MSK_getbarvarnamelen*, *MSK_getc*, *MSK_getcfix*, *MSK_getcj*, *MSK_getclist*, *MSK_getconbound*, *MSK_getconboundslice*, *MSK_getcone*, *MSK_getconeinfo*, *MSK_getconename*, *MSK_getconenameindex*, *MSK_getconenamelen*, *MSK_getconname*, *MSK_getconnameindex*, *MSK_getconnamelen*, *MSK_getcslice*, *MSK_getdimbarvarj*, *MSK_getlenbarvarj*, *MSK_getmaxnamelen*, *MSK_getmaxnumanz*, *MSK_getmaxnumanz64*, *MSK_getmaxnumbarvar*, *MSK_getmaxnumcon*, *MSK_getmaxnumcone*, *MSK_getmaxnumqnz*, *MSK_getmaxnumqnz64*, *MSK_getmaxnumvar*, *MSK_getnumanz*, *MSK_getnumanz64*, *MSK_getnumbarablocktriplets*, *MSK_getnumbaranz*, *MSK_getnumbarcbblocktriplets*, *MSK_getnumbarcnz*, *MSK_getnumbarvar*, *MSK_getnumconemem*, *MSK_getnumintvar*, *MSK_getnumparam*, *MSK_getnumqconknz*, *MSK_getnumqconknz64*, *MSK_getnumqobjnz*, *MSK_getnumqobjnz64*, *MSK_getnumsymmat*, *MSK_getobjname*, *MSK_getobjnamelen*, *MSK_getprobtype*, *MSK_getqconk*, *MSK_getqconk64*, *MSK_getqobj*, *MSK_getqobj64*, *MSK_getqobjij*, *MSK_getsparsesymmat*, *MSK_getsymmatinfo*, *MSK_gettaskname*, *MSK_gettasknamelen*, *MSK_getvarbound*, *MSK_getvarboundslice*, *MSK_getvarname*, *MSK_getvarnameindex*, *MSK_getvarnamelen*, *MSK_getvartype*, *MSK_getvartypelist*, *MSK_printparam*, *MSK_probtypetostr*, *MSK_readsummary*

License system

- *MSK_checkoutlicense* – Check out a license feature from the license server ahead of time.
- *MSK_putlicensedebug* – Enables debug information for the license system.
- *MSK_putlicensepath* – Set the path to the license file.
- *MSK_putlicensewait* – Control whether mosek should wait for an available license if no license is available.
- *Infrequent:* *MSK_checkinall*, *MSK_checkinlicense*, *MSK_licensecleanup*, *MSK_putlicensecode*

Linear algebra

- *Infrequent:* *MSK_axpy*, *MSK_computesparseseholesky*, *MSK_dot*, *MSK_gemm*, *MSK_gemv*, *MSK_potrf*, *MSK_sparsetriangularsolvedense*, *MSK_syeig*, *MSK_syeud*, *MSK_syrk*

Logging

- *MSK_linkfiletotaskstream* – Directs all output from a task stream to a file.
- *MSK_linkfunctotaskstream* – Connects a user-defined function to a task stream.
- *MSK_onesolutionsummary* – Prints a short summary of a specified solution.
- *MSK_optimizersummary* – Prints a short summary with optimizer statistics from last optimization.
- *MSK_solutionsummary* – Prints a short summary of the current solutions.
- Infrequent: *MSK_echoenv*, *MSK_echointro*, *MSK_linkfiletoenvstream*, *MSK_linkfunctoenvstream*, *MSK_printparam*, *MSK_putexitfunc*, *MSK_putresponsefunc*, *MSK_unlinkfuncfromenvstream*, *MSK_unlinkfuncfromtaskstream*

Names

- *MSK_getcodedesc* – Obtains a short description of a response code.
- *MSK_putbarvarname* – Sets the name of a semidefinite variable.
- *MSK_putconename* – Sets the name of a cone.
- *MSK_putconname* – Sets the name of a constraint.
- *MSK_putobjname* – Assigns a new name to the objective.
- *MSK_puttaskname* – Assigns a new name to the task.
- *MSK_putvarname* – Sets the name of a variable.
- Infrequent: *MSK_analyzenames*, *MSK_bktostr*, *MSK_callbackcodetostr*, *MSK_conetypetostr*, *MSK_generateconenames*, *MSK_generateconnames*, *MSK_generatevarnames*, *MSK_getbarvarname*, *MSK_getbarvarnameindex*, *MSK_getbarvarnamelen*, *MSK_getconename*, *MSK_getconenameindex*, *MSK_getconenamelen*, *MSK_getconname*, *MSK_getconnameindex*, *MSK_getconnamelen*, *MSK_getinfname*, *MSK_getmaxnamelen*, *MSK_getnastrparam*, *MSK_getobjname*, *MSK_getobjnamelen*, *MSK_getparamname*, *MSK_getstrparam*, *MSK_getstrparamlen*, *MSK_getsymbcon*, *MSK_gettaskname*, *MSK_gettasknamelen*, *MSK_getvarname*, *MSK_getvarnameindex*, *MSK_getvarnamelen*, *MSK_iparvaltosymnam*, *MSK_isdoupvarname*, *MSK_isintparname*, *MSK_isstrparname*, *MSK_probtypetostr*, *MSK_prostattostr*, *MSK_skttostr*, *MSK_solstattostr*, *MSK_strtoconetype*, *MSK_strtosk*, *MSK_whichparam*

Optimization

- *MSK_optimize* – Optimizes the problem.
- *MSK_optimizetrm* – Optimizes the problem.

Parameters

- *MSK_putdoupparam* – Sets a double parameter.
- *MSK_putintparam* – Sets an integer parameter.
- *MSK_putparam* – Modifies the value of parameter.
- *MSK_putstrparam* – Sets a string parameter.
- *MSK_setdefaults* – Resets all parameter values.

- *Infrequent:* `MSK_getatruncatetol`, `MSK_getdoupparam`, `MSK_getintparam`, `MSK_getnadoupparam`, `MSK_getnaintparam`, `MSK_getnastrparam`, `MSK_getnastrparamal`, `MSK_getnumparam`, `MSK_getparammax`, `MSK_getparamname`, `MSK_getstrparam`, `MSK_getstrparamal`, `MSK_getstrparamlen`, `MSK_getsybcondim`, `MSK_iparvaltosymnam`, `MSK_isdoupname`, `MSK_isintparname`, `MSK_isstrparname`, `MSK_putnadoupparam`, `MSK_putnaintparam`, `MSK_putnastrparam`, `MSK_symnamtovalue`, `MSK_whichparam`, `MSK_writetparamfile`

Problem data - bounds

- `MSK_putconbound` – Changes the bound for one constraint.
- `MSK_putconboundslice` – Changes the bounds for a slice of the constraints.
- `MSK_putvarbound` – Changes the bounds for one variable.
- `MSK_putvarboundslice` – Changes the bounds for a slice of the variables.
- *Infrequent:* `MSK_chgconbound`, `MSK_chgvarbound`, `MSK_getconbound`, `MSK_getconboundslice`, `MSK_getvarbound`, `MSK_getvarboundslice`, `MSK_inputdata`, `MSK_inputdata64`, `MSK_putconboundlist`, `MSK_putconboundlistconst`, `MSK_putconboundsliceconst`, `MSK_putvarboundlist`, `MSK_putvarboundlistconst`, `MSK_putvarboundsliceconst`

Problem data - cones

- `MSK_appendcone` – Appends a new conic constraint to the problem.
- `MSK_appendconesseq` – Appends multiple conic constraints to the problem.
- `MSK_getnumcone` – Obtains the number of cones.
- `MSK_putcone` – Replaces a conic constraint.
- `MSK_putconename` – Sets the name of a cone.
- `MSK_removecones` – Removes a number of conic constraints from the problem.
- *Infrequent:* `MSK_appendconesseq`, `MSK_generateconenames`, `MSK_getcone`, `MSK_getconeinfo`, `MSK_getconename`, `MSK_getconenameindex`, `MSK_getconenamelen`, `MSK_getmaxnumcone`, `MSK_getnumconemem`, `MSK_putmaxnumcone`

Problem data - constraints

- `MSK_appendcons` – Appends a number of constraints to the optimization task.
- `MSK_getnumcon` – Obtains the number of constraints.
- `MSK_putconbound` – Changes the bound for one constraint.
- `MSK_putconboundslice` – Changes the bounds for a slice of the constraints.
- `MSK_putconname` – Sets the name of a constraint.
- `MSK_removecons` – Removes a number of constraints.
- *Infrequent:* `MSK_chgconbound`, `MSK_generateconnames`, `MSK_getconbound`, `MSK_getconboundslice`, `MSK_getconname`, `MSK_getconnameindex`, `MSK_getconenamelen`, `MSK_getmaxnumcon`, `MSK_getnumqconknz`, `MSK_getnumqconknz64`, `MSK_getqconk`, `MSK_getqconk64`, `MSK_inputdata`, `MSK_inputdata64`, `MSK_putconboundlist`, `MSK_putconboundlistconst`, `MSK_putconboundsliceconst`, `MSK_putmaxnumcon`

Problem data - linear part

- *MSK_appendcons* – Appends a number of constraints to the optimization task.
- *MSK_appendvars* – Appends a number of variables to the optimization task.
- *MSK_getnumcon* – Obtains the number of constraints.
- *MSK_putacol* – Replaces all elements in one column of the linear constraint matrix.
- *MSK_putacolslice* – Replaces all elements in a sequence of columns the linear constraint matrix.
- *MSK_putacolslice64* – Replaces all elements in a sequence of columns the linear constraint matrix.
- *MSK_putaij* – Changes a single value in the linear coefficient matrix.
- *MSK_putaijlist* – Changes one or more coefficients in the linear constraint matrix.
- *MSK_putaijlist64* – Changes one or more coefficients in the linear constraint matrix.
- *MSK_putarow* – Replaces all elements in one row of the linear constraint matrix.
- *MSK_putarowslice* – Replaces all elements in several rows the linear constraint matrix.
- *MSK_putarowslice64* – Replaces all elements in several rows the linear constraint matrix.
- *MSK_putcfix* – Replaces the fixed term in the objective.
- *MSK_putcj* – Modifies one linear coefficient in the objective.
- *MSK_putconbound* – Changes the bound for one constraint.
- *MSK_putconboundslice* – Changes the bounds for a slice of the constraints.
- *MSK_putconname* – Sets the name of a constraint.
- *MSK_putcslice* – Modifies a slice of the linear objective coefficients.
- *MSK_putobjname* – Assigns a new name to the objective.
- *MSK_putobjsense* – Sets the objective sense.
- *MSK_putvarbound* – Changes the bounds for one variable.
- *MSK_putvarboundslice* – Changes the bounds for a slice of the variables.
- *MSK_putvarname* – Sets the name of a variable.
- *MSK_removecons* – Removes a number of constraints.
- *MSK_removevars* – Removes a number of variables.
- *Infrequent:* *MSK_chgconbound*, *MSK_chgvarbound*, *MSK_generateconnames*, *MSK_generatevarnames*, *MSK_getacol*, *MSK_getacolnumz*, *MSK_getacolslice*, *MSK_getacolslice64*, *MSK_getacolslicenumz*, *MSK_getacolslicenumz64*, *MSK_getacolslicetrip*, *MSK_getaij*, *MSK_getapiecenumz*, *MSK_getarow*, *MSK_getarownumz*, *MSK_getarowslice*, *MSK_getarowslice64*, *MSK_getarowslicenumz*, *MSK_getarowslicenumz64*, *MSK_getarowslicetrip*, *MSK_getatruncatetol*, *MSK_getc*, *MSK_getcfix*, *MSK_getcj*, *MSK_getclist*, *MSK_getconbound*, *MSK_getconboundslice*, *MSK_getconname*, *MSK_getconnameindex*, *MSK_getconnamelen*, *MSK_getcslice*, *MSK_getmaxnumanz*, *MSK_getmaxnumanz64*, *MSK_getmaxnumcon*, *MSK_getmaxnumvar*, *MSK_getnumanz*, *MSK_getnumanz64*, *MSK_getobjsense*, *MSK_getvarbound*, *MSK_getvarboundslice*, *MSK_getvarname*, *MSK_getvarnameindex*, *MSK_getvarnamelen*, *MSK_inputdata*, *MSK_inputdata64*, *MSK_putacollist*, *MSK_putacollist64*, *MSK_putarowlist*, *MSK_putarowlist64*, *MSK_putatruncatetol*, *MSK_putclist*, *MSK_putconboundlist*, *MSK_putconboundlistconst*, *MSK_putconboundsliceconst*, *MSK_putvarboundlist*, *MSK_putvarboundlistconst*, *MSK_putvarboundsliceconst*

Problem data - objective

- *MSK_putbarcj* – Changes one element in barc.
- *MSK_putcfix* – Replaces the fixed term in the objective.
- *MSK_putcj* – Modifies one linear coefficient in the objective.
- *MSK_putcslice* – Modifies a slice of the linear objective coefficients.
- *MSK_putobjname* – Assigns a new name to the objective.
- *MSK_putobjsense* – Sets the objective sense.
- *MSK_putqobj* – Replaces all quadratic terms in the objective.
- *MSK_putqobjij* – Replaces one coefficient in the quadratic term in the objective.
- Infrequent: *MSK_putclist*

Problem data - quadratic part

- *MSK_putqcon* – Replaces all quadratic terms in constraints.
- *MSK_putqconk* – Replaces all quadratic terms in a single constraint.
- *MSK_putqobj* – Replaces all quadratic terms in the objective.
- *MSK_putqobjij* – Replaces one coefficient in the quadratic term in the objective.
- Infrequent: *MSK_getmaxnumqnz*, *MSK_getmaxnumqnz64*, *MSK_getnumqconknz*, *MSK_getnumqconknz64*, *MSK_getnumqobjnz*, *MSK_getnumqobjnz64*, *MSK_getqconk*, *MSK_getqconk64*, *MSK_getqobj*, *MSK_getqobj64*, *MSK_getqobjij*, *MSK_putmaxnumqnz*, *MSK_toconic*

Problem data - semidefinite

- *MSK_appendbarvars* – Appends semidefinite variables to the problem.
- *MSK_appendsparsesymmat* – Appends a general sparse symmetric matrix to the storage of symmetric matrices.
- *MSK_appendsparsesymmatlist* – Appends a general sparse symmetric matrix to the storage of symmetric matrices.
- *MSK_putbaraij* – Inputs an element of barA.
- *MSK_putbaraijlist* – Inputs list of elements of barA.
- *MSK_putbararowlist* – Replace a set of rows of barA.
- *MSK_putbarcj* – Changes one element in barc.
- *MSK_putbarvarname* – Sets the name of a semidefinite variable.
- Infrequent: *MSK_getbarablocktriplet*, *MSK_getbaraidx*, *MSK_getbaraidxij*, *MSK_getbaraidxinfo*, *MSK_getbarasparsity*, *MSK_getbarcblocktriplet*, *MSK_getbarcidx*, *MSK_getbarcidxinfo*, *MSK_getbarcidxj*, *MSK_getbarcsparsity*, *MSK_getdimbarvarj*, *MSK_getlenbarvarj*, *MSK_getmaxnumbarvar*, *MSK_getnumbarablocktriplets*, *MSK_getnumbaranz*, *MSK_getnumbarcblocktriplets*, *MSK_getnumbarcnz*, *MSK_getnumbarvar*, *MSK_getnumsymmat*, *MSK_getsparsesymmat*, *MSK_getsymmatinfo*, *MSK_putbarablocktriplet*, *MSK_putbarcblocktriplet*, *MSK_putmaxnumanz*, *MSK_putmaxnumbarvar*, *MSK_removebarvars*

Problem data - variables

- *MSK_appendvars* – Appends a number of variables to the optimization task.
- *MSK_getnumvar* – Obtains the number of variables.
- *MSK_putvarbound* – Changes the bounds for one variable.
- *MSK_putvarboundslice* – Changes the bounds for a slice of the variables.
- *MSK_putvarname* – Sets the name of a variable.
- *MSK_putvartype* – Sets the variable type of one variable.
- *MSK_removevars* – Removes a number of variables.
- Infrequent: *MSK_chgvarbound*, *MSK_generatevarnames*, *MSK_getc*, *MSK_getcj*, *MSK_getmaxnumvar*, *MSK_getnumintvar*, *MSK_getvarbound*, *MSK_getvarboundslice*, *MSK_getvarname*, *MSK_getvarnameindex*, *MSK_getvarnamelen*, *MSK_getvartype*, *MSK_getvartypelist*, *MSK_putclist*, *MSK_putmaxnumvar*, *MSK_putvarboundlist*, *MSK_putvarboundlistconst*, *MSK_putvarboundsliceconst*, *MSK_putvartypelist*

Remote optimization

- *MSK_asyncgetresult* – Request a response from a remote job.
- *MSK_asyncoptimize* – Offload the optimization task to a solver server.
- *MSK_asyncpoll* – Requests information about the status of the remote job.
- *MSK_asyncstop* – Request that the job identified by the token is terminated.
- *MSK_optimizermt* – Offload the optimization task to a solver server.

Responses, errors and warnings

- *MSK_getcodedesc* – Obtains a short description of a response code.
- Infrequent: *MSK_getlasterror*, *MSK_getlasterror64*, *MSK_getresponseclass*

Sensitivity analysis

- *MSK_dualsensitivity* – Performs sensitivity analysis on objective coefficients.
- *MSK_primalsensitivity* – Perform sensitivity analysis on bounds.
- *MSK_sensitivityreport* – Creates a sensitivity report.

Solution - dual

- *MSK_getdualobj* – Computes the dual objective value associated with the solution.
- *MSK_gety* – Obtains the y vector for a solution.
- *MSK_getyslice* – Obtains a slice of the y vector for a solution.
- Infrequent: *MSK_getreducedcosts*, *MSK_getslc*, *MSK_getslcslice*, *MSK_getslx*, *MSK_getslxslice*, *MSK_getsnx*, *MSK_getsnxslice*, *MSK_getsolution*, *MSK_getsolutionslice*, *MSK_getsuc*, *MSK_getsucslice*, *MSK_getsux*, *MSK_getsuxslice*, *MSK_putconsolutioni*, *MSK_putslc*, *MSK_putslcslice*, *MSK_putslx*, *MSK_putslxslice*, *MSK_putsnx*, *MSK_putsnxslice*, *MSK_putsolution*, *MSK_putsolutionyi*, *MSK_putsuc*, *MSK_putsucslice*, *MSK_putsux*, *MSK_putsuxslice*, *MSK_putvarsolutionj*, *MSK_putyslice*

Solution - primal

- *MSK_getprimalobj* – Computes the primal objective value for the desired solution.
- *MSK_getxx* – Obtains the xx vector for a solution.
- *MSK_getxxslice* – Obtains a slice of the xx vector for a solution.
- *MSK_putxx* – Sets the xx vector for a solution.
- *MSK_putxxslice* – Sets a slice of the xx vector for a solution.
- Infrequent: *MSK_getsolution*, *MSK_getsolutionslice*, *MSK_getxc*, *MSK_getxcslice*, *MSK_putconsolutioni*, *MSK_putsolution*, *MSK_putvarsolutionj*, *MSK_putxc*, *MSK_putxcslice*, *MSK_puty*

Solution - semidefinite

- *MSK_getbarsj* – Obtains the dual solution for a semidefinite variable.
- *MSK_getbarsslice* – Obtains the dual solution for a sequence of semidefinite variables.
- *MSK_getbarxj* – Obtains the primal solution for a semidefinite variable.
- *MSK_getbarxslice* – Obtains the primal solution for a sequence of semidefinite variables.
- Infrequent: *MSK_putbarsj*, *MSK_putbarxj*

Solution information

- *MSK_getdualobj* – Computes the dual objective value associated with the solution.
- *MSK_getprimalobj* – Computes the primal objective value for the desired solution.
- *MSK_getprosta* – Obtains the problem status.
- *MSK_getpviolcon* – Computes the violation of a primal solution associated to a constraint.
- *MSK_getpviolvar* – Computes the violation of a primal solution for a list of scalar variables.
- *MSK_getsolsta* – Obtains the solution status.
- *MSK_getsolutioninfo* – Obtains information about of a solution.
- *MSK_onesolutionsummary* – Prints a short summary of a specified solution.
- *MSK_solutiondef* – Checks whether a solution is defined.
- *MSK_solutionsummary* – Prints a short summary of the current solutions.
- Infrequent: *MSK_analyzesolution*, *MSK_deletesolution*, *MSK_getdualsolutionnorms*, *MSK_getdviolbarvar*, *MSK_getdviolcon*, *MSK_getdviolcones*, *MSK_getdviolvar*, *MSK_getprimalsolutionnorms*, *MSK_getpviolbarvar*, *MSK_getpviolcones*, *MSK_getskc*, *MSK_getskcslice*, *MSK_getskn*, *MSK_getskx*, *MSK_getskxslice*, *MSK_getsolution*, *MSK_getsolutionslice*, *MSK_prostatostr*, *MSK_putconsolutioni*, *MSK_putskc*, *MSK_putskcslice*, *MSK_putskx*, *MSK_putskxslice*, *MSK_putsolution*, *MSK_putsolutionyi*, *MSK_putvarsolutionj*

Solving systems with basis matrix

- Infrequent: *MSK_basiscond*, *MSK_initbasissolve*, *MSK_solvewithbasis*

System, memory and debugging

- *Infrequent:* `MSK_callocdbgenv`, `MSK_callocdbgtask`, `MSK_callocenv`, `MSK_calloctask`, `MSK_checkmemenv`, `MSK_checkmemtask`, `MSK_freedbgenv`, `MSK_freedbgtask`, `MSK_freeenv`, `MSK_freetask`, `MSK_getmemusagetask`, `MSK_setupthreads`, `MSK_strdupdbgtask`, `MSK_strduptask`, `MSK_utf8towchar`, `MSK_wchartoutf8`

Versions

- `MSK_getversion` – Obtains MOSEK version information.
- *Infrequent:* `MSK_checkversion`, `MSK_getbuildinfo`

Other

- *Infrequent:* `MSK_isinfinity`

15.3 Functions in alphabetical order

MSK_analyzenames

```
MSKrescodee (MSKAPI MSK_analyzenames) (  
    MSKtask_t task,  
    MSKstreamtypee whichstream,  
    MSKnametypee nametype)
```

The function analyzes the names and issues an error if a name is invalid.

Parameters

- `task` (`MSKtask_t`) – An optimization task. (input)
- `whichstream` (`MSKstreamtypee`) – Index of the stream. (input)
- `nametype` (`MSKnametypee`) – The type of names e.g. valid in MPS or LP files. (input)

Return (`MSKrescodee`) – The function response code.

Groups *Names*

MSK_analyzeproblem

```
MSKrescodee (MSKAPI MSK_analyzeproblem) (  
    MSKtask_t task,  
    MSKstreamtypee whichstream)
```

The function analyzes the data of a task and writes out a report.

Parameters

- `task` (`MSKtask_t`) – An optimization task. (input)
- `whichstream` (`MSKstreamtypee`) – Index of the stream. (input)

Return (`MSKrescodee`) – The function response code.

Groups *Inspecting the task*

MSK_analyzesolution

```
MSKrescodee (MSKAPI MSK_analyzesolution) (  
    MSKtask_t task,  
    MSKstreamtypee whichstream,  
    MSKsoltypee whichsol)
```

Print information related to the quality of the solution and other solution statistics.

By default this function prints information about the largest infeasibilities in the solution, the primal (and possibly dual) objective value and the solution status.

Following parameters can be used to configure the printed statistics:

- *MSK_IPAR_ANA_SOL_BASIS* enables or disables printing of statistics specific to the basis solution (condition number, number of basic variables etc.). Default is on.
- *MSK_IPAR_ANA_SOL_PRINT_VIOLATED* enables or disables listing names of all constraints (both primal and dual) which are violated by the solution. Default is off.
- *MSK_DPAR_ANA_SOL_INFEAS_TOL* is the tolerance defining when a constraint is considered violated. If a constraint is violated more than this, it will be listed in the summary.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *whichstream* (*MSKstreamtypee*) – Index of the stream. (input)
- *whichsol* (*MSKsoltypee*) – Selects a solution. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information, Inspecting the task*

MSK_appendbarvars

```
MSKrescodee (MSKAPI MSK_appendbarvars) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * dim)
```

Appends positive semidefinite matrix variables of dimensions given by *dim* to the problem.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *num* (*MSKint32t*) – Number of symmetric matrix variables to be appended. (input)
- *dim* (*MSKint32t**) – Dimensions of symmetric matrix variables to be added. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite*

MSK_appendcone

```
MSKrescodee (MSKAPI MSK_appendcone) (
    MSKtask_t task,
    MSKconetypee ct,
    MSKrealt coneapar,
    MSKint32t nummem,
    const MSKint32t * submem)
```

Appends a new conic constraint to the problem. Hence, add a constraint

$$\hat{x} \in \mathcal{K}$$

to the problem, where \mathcal{K} is a convex cone. \hat{x} is a subset of the variables which will be specified by the argument *submem*. Cone type is specified by *ct*.

Define

$$\hat{x} = x_{\text{submem}[0]}, \dots, x_{\text{submem}[\text{nummem}-1]}.$$

Depending on the value of *ct* this function appends one of the constraints:

- Quadratic cone (*MSK_CT_QUAD*, requires `nummem` ≥ 1):

$$\hat{x}_0 \geq \sqrt{\sum_{i=1}^{i < \text{nummem}} \hat{x}_i^2}$$

- Rotated quadratic cone (*MSK_CT_RQUAD*, requires `nummem` ≥ 2):

$$2\hat{x}_0\hat{x}_1 \geq \sum_{i=2}^{i < \text{nummem}} \hat{x}_i^2, \quad \hat{x}_0, \hat{x}_1 \geq 0$$

- Primal exponential cone (*MSK_CT_PEXP*, requires `nummem` = 3):

$$\hat{x}_0 \geq \hat{x}_1 \exp(\hat{x}_2/\hat{x}_1), \quad \hat{x}_0, \hat{x}_1 \geq 0$$

- Primal power cone (*MSK_CT_PPOW*, requires `nummem` ≥ 2):

$$\hat{x}_0^\alpha \hat{x}_1^{1-\alpha} \geq \sqrt{\sum_{i=2}^{i < \text{nummem}} \hat{x}_i^2}, \quad \hat{x}_0, \hat{x}_1 \geq 0$$

where α is the cone parameter specified by `conepar`.

- Dual exponential cone (*MSK_CT_DEXP*, requires `nummem` = 3):

$$\hat{x}_0 \geq -\hat{x}_2 e^{-1} \exp(\hat{x}_1/\hat{x}_2), \quad \hat{x}_2 \leq 0, \hat{x}_0 \geq 0$$

- Dual power cone (*MSK_CT_DPOW*, requires `nummem` ≥ 2):

$$\left(\frac{\hat{x}_0}{\alpha}\right)^\alpha \left(\frac{\hat{x}_1}{1-\alpha}\right)^{1-\alpha} \geq \sqrt{\sum_{i=2}^{i < \text{nummem}} \hat{x}_i^2}, \quad \hat{x}_0, \hat{x}_1 \geq 0$$

where α is the cone parameter specified by `conepar`.

- Zero cone (*MSK_CT_ZERO*):

$$\hat{x}_i = 0 \text{ for all } i$$

Please note that the sets of variables appearing in different conic constraints must be disjoint.
For an explained code example see [Sec. 6.3](#), [Sec. 6.5](#) or [Sec. 6.4](#).

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `ct` (*MSKconetypeee*) – Specifies the type of the cone. (input)
- `conepar` (*MSKrealt*) – For the power cone it denotes the exponent alpha. For other cone types it is unused and can be set to 0. (input)
- `nummem` (*MSKint32t*) – Number of member variables in the cone. (input)
- `submem` (*MSKint32t**) – Variable subscripts of the members in the cone. (input)

Return (*MSKrescodeee*) – The function response code.

Groups *Problem data - cones*

MSK_appendconeseq

```
MSKrescodeee (MSKAPI MSK_appendconeseq) (
    MSKtask_t task,
    MSKconetypeee ct,
    MSKrealt conepar,
    MSKint32t nummem,
    MSKint32t j)
```

Appends a new conic constraint to the problem, as in *MSK_appendcone*. The function assumes the members of cone are sequential where the first member has index j and the last $j+\text{nummem}-1$.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **ct** (*MSKconetypee*) – Specifies the type of the cone. (input)
- **conepar** (*MSKrealt*) – For the power cone it denotes the exponent alpha. For other cone types it is unused and can be set to 0. (input)
- **nummem** (*MSKint32t*) – Number of member variables in the cone. (input)
- **j** (*MSKint32t*) – Index of the first variable in the conic constraint. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - cones*

MSK_appendconesseq

```
MSKrescodee (MSKAPI MSK_appendconesseq) (
    MSKtask_t task,
    MSKint32t num,
    const MSKconetypee * ct,
    const MSKrealt * conepar,
    const MSKint32t * nummem,
    MSKint32t j)
```

Appends a number of conic constraints to the problem, as in *MSK_appendcone*. The k th cone is assumed to be of dimension $\text{nummem}[k]$. Moreover, it is assumed that the first variable of the first cone has index j and starting from there the sequentially following variables belong to the first cone, then to the second cone and so on.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint32t*) – Number of cones to be added. (input)
- **ct** (*MSKconetypee**) – Specifies the type of the cone. (input)
- **conepar** (*MSKrealt**) – For the power cone it denotes the exponent alpha. For other cone types it is unused and can be set to 0. (input)
- **nummem** (*MSKint32t**) – Numbers of member variables in the cones. (input)
- **j** (*MSKint32t*) – Index of the first variable in the first cone to be appended. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - cones*

MSK_appendcons

```
MSKrescodee (MSKAPI MSK_appendcons) (
    MSKtask_t task,
    MSKint32t num)
```

Appends a number of constraints to the model. Appended constraints will be declared free. Please note that **MOSEK** will automatically expand the problem dimension to accommodate the additional constraints.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint32t*) – Number of constraints which should be appended. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - constraints*

MSK_appendsparsesymmat

```
MSKrescodee (MSKAPI MSK_appendsparsesymmat) (  
    MSKtask_t task,  
    MSKint32t dim,  
    MSKint64t nz,  
    const MSKint32t * subi,  
    const MSKint32t * subj,  
    const MSKrealt * valij,  
    MSKint64t * idx)
```

MOSEK maintains a storage of symmetric data matrices that is used to build \bar{C} and \bar{A} . The storage can be thought of as a vector of symmetric matrices denoted E . Hence, E_i is a symmetric matrix of certain dimension.

This function appends a general sparse symmetric matrix on triplet form to the vector E of symmetric matrices. The vectors `subi`, `subj`, and `valij` contains the row subscripts, column subscripts and values of each element in the symmetric matrix to be appended. Since the matrix that is appended is symmetric, only the lower triangular part should be specified. Moreover, duplicates are not allowed.

Observe the function reports the index (position) of the appended matrix in E . This index should be used for later references to the appended matrix.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `dim` (*MSKint32t*) – Dimension of the symmetric matrix that is appended. (input)
- `nz` (*MSKint64t*) – Number of triplets. (input)
- `subi` (*MSKint32t**) – Row subscript in the triplets. (input)
- `subj` (*MSKint32t**) – Column subscripts in the triplets. (input)
- `valij` (*MSKrealt**) – Values of each triplet. (input)
- `idx` (*MSKint64t by reference*) – Unique index assigned to the inputted matrix that can be used for later reference. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite*

MSK_appendsparsesymmatlist

```
MSKrescodee (MSKAPI MSK_appendsparsesymmatlist) (  
    MSKtask_t task,  
    MSKint32t num,  
    const MSKint32t * dims,  
    const MSKint64t * nz,  
    const MSKint32t * subi,  
    const MSKint32t * subj,  
    const MSKrealt * valij,  
    MSKint64t * idx)
```

MOSEK maintains a storage of symmetric data matrices that is used to build \bar{C} and \bar{A} . The storage can be thought of as a vector of symmetric matrices denoted E . Hence, E_i is a symmetric matrix of certain dimension.

This function appends general sparse symmetric matrixes on triplet form to the vector E of symmetric matrices. The vectors `subi`, `subj`, and `valij` contains the row subscripts, column subscripts and values of each element in the symmetric matrix to be appended. Since the matrix that is appended is symmetric, only the lower triangular part should be specified. Moreover, duplicates are not allowed.

Observe the function reports the index (position) of the appended matrix in E . This index should be used for later references to the appended matrix.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of matrixes to append. (input)
- `dims` (*MSKint32t**) – Dimensions of the symmetric matrixes. (input)
- `nz` (*MSKint64t**) – Number of nonzeros for each matrix. (input)
- `subi` (*MSKint32t**) – Row subscript in the triplets. (input)
- `subj` (*MSKint32t**) – Column subscripts in the triplets. (input)
- `valij` (*MSKrealt**) – Values of each triplet. (input)
- `idx` (*MSKint64t**) – Unique index assigned to the inputted matrix that can be used for later reference. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite*

MSK_appendvars

```
MSKrescodee (MSKAPI MSK_appendvars) (  
    MSKtask_t task,  
    MSKint32t num)
```

Appends a number of variables to the model. Appended variables will be fixed at zero. Please note that **MOSEK** will automatically expand the problem dimension to accommodate the additional variables.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of variables which should be appended. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - variables*

MSK_asyncgetresult

```
MSKrescodee (MSKAPI MSK_asyncgetresult) (  
    MSKtask_t task,  
    const char * server,  
    const char * port,  
    const char * token,  
    MSKboolean * respavailable,  
    MSKrescodee * resp,  
    MSKrescodee * trm)
```

Request a response from a remote job. If successful, solver response, termination code and solutions are retrieved.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `server` (*MSKstring_t*) – Name or IP address of the solver server. (input)
- `port` (*MSKstring_t*) – Network port of the solver service. (input)
- `token` (*MSKstring_t*) – The task token. (input)
- `respavailable` (*MSKboolean by reference*) – Indicates if a remote response is available. If this is not true, `resp` and `trm` should be ignored. (output)
- `resp` (*MSKrescodee by reference*) – Is the response code from the remote solver. (output)
- `trm` (*MSKrescodee by reference*) – Is either *MSK_RES_OK* or a termination response code. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Remote optimization*

MSK_asyncoptimize

```
MSKrescodee (MSKAPI MSK_asyncoptimize) (  
    MSKtask_t task,  
    const char * server,  
    const char * port,  
    char * token)
```

Offload the optimization task to a solver server defined by `server:port`. The call will return immediately and not wait for the result.

If the string parameter `MSK_SPAR_REMOTE_ACCESS_TOKEN` is not blank, it will be passed to the server as authentication.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `server` (*MSKstring_t*) – Name or IP address of the solver server (input)
- `port` (*MSKstring_t*) – Network port of the solver service (input)
- `token` (*MSKstring_t*) – Returns the task token (output)

Return (*MSKrescodee*) – The function response code.

Groups *Remote optimization*

MSK_asyncpoll

```
MSKrescodee (MSKAPI MSK_asyncpoll) (  
    MSKtask_t task,  
    const char * server,  
    const char * port,  
    const char * token,  
    MSKboolean * respavailable,  
    MSKrescodee * resp,  
    MSKrescodee * trm)
```

Requests information about the status of the remote job.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `server` (*MSKstring_t*) – Name or IP address of the solver server (input)
- `port` (*MSKstring_t*) – Network port of the solver service (input)
- `token` (*MSKstring_t*) – The task token (input)
- `respavailable` (*MSKboolean by reference*) – Indicates if a remote response is available. If this is not true, `resp` and `trm` should be ignored. (output)
- `resp` (*MSKrescodee by reference*) – Is the response code from the remote solver. (output)
- `trm` (*MSKrescodee by reference*) – Is either `MSK_RES_OK` or a termination response code. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Remote optimization*

MSK_asyncstop

```
MSKrescodee (MSKAPI MSK_asyncstop) (  
    MSKtask_t task,  
    const char * server,  
    const char * port,  
    const char * token)
```

Request that the job identified by the `token` is terminated.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **server** (*MSKstring_t*) – Name or IP address of the solver server (input)
- **port** (*MSKstring_t*) – Network port of the solver service (input)
- **token** (*MSKstring_t*) – The task token (input)

Return (*MSKrescodee*) – The function response code.

Groups *Remote optimization*

MSK_axpy

```
MSKrescodee (MSKAPI MSK_axpy) (  
    MSKenv_t env,  
    MSKint32t n,  
    MSKrealt alpha,  
    const MSKrealt * x,  
    MSKrealt * y)
```

Adds αx to y , i.e. performs the update

$$y := \alpha x + y.$$

Note that the result is stored overwriting y .

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **n** (*MSKint32t*) – Length of the vectors. (input)
- **alpha** (*MSKrealt*) – The scalar that multiplies x . (input)
- **x** (*MSKrealt**) – The x vector. (input)
- **y** (*MSKrealt**) – The y vector. (input/output)

Return (*MSKrescodee*) – The function response code.

Groups *Linear algebra*

MSK_basiscond

```
MSKrescodee (MSKAPI MSK_basiscond) (  
    MSKtask_t task,  
    MSKrealt * nrmbasis,  
    MSKrealt * nrminvbasis)
```

If a basic solution is available and it defines a nonsingular basis, then this function computes the 1-norm estimate of the basis matrix and a 1-norm estimate for the inverse of the basis matrix. The 1-norm estimates are computed using the method outlined in [\[Ste98\]](#), pp. 388-391.

By definition the 1-norm condition number of a matrix B is defined as

$$\kappa_1(B) := \|B\|_1 \|B^{-1}\|_1.$$

Moreover, the larger the condition number is the harder it is to solve linear equation systems involving B . Given estimates for $\|B\|_1$ and $\|B^{-1}\|_1$ it is also possible to estimate $\kappa_1(B)$.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **nrmbasis** (*MSKrealt by reference*) – An estimate for the 1-norm of the basis. (output)
- **nrminvbasis** (*MSKrealt by reference*) – An estimate for the 1-norm of the inverse of the basis. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solving systems with basis matrix*

MSK_bktostr

```
MSKrescodee (MSKAPI MSK_bktostr) (  
    MSKtask_t task,  
    MSKboundkeye bk,  
    char * str)
```

Obtains an identifier string corresponding to a bound key.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **bk** (*MSKboundkeye*) – Bound key. (input)
- **str** (*MSKstring_t*) – String corresponding to the bound key code **bk**. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names*

MSK_callbackcodetostr

```
MSKrescodee (MSKAPI MSK_callbackcodetostr) (  
    MSKcallbackcodee code,  
    char * callbackcodestr)
```

Obtains the string representation of a callback code.

Parameters

- **code** (*MSKcallbackcodee*) – A callback code. (input)
- **callbackcodestr** (*MSKstring_t*) – String corresponding to the callback code. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names*

MSK_callocdbgen

```
void * (MSKAPI MSK_callocdbgen) (  
    MSKenv_t env,  
    const size_t number,  
    const size_t size,  
    const char * file,  
    const unsigned line)
```

Debug version of *MSK_callocenv*.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **number** (*size_t*) – Number of elements. (input)
- **size** (*size_t*) – Size of each individual element. (input)
- **file** (*MSKstring_t*) – File from which the function is called. (input)
- **line** (*unsigned*) – Line in the file from which the function is called. (input)

Return (*void**) – A pointer to the memory allocated through the environment.

Groups *System, memory and debugging*

MSK_callocdbgtask

```
void * (MSKAPI MSK_allocdbgtask) (
    MSKtask_t task,
    const size_t number,
    const size_t size,
    const char * file,
    const unsigned line)
```

Debug version of *MSK_allocctask*.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- number (*size_t*) – Number of elements. (input)
- size (*size_t*) – Size of each individual element. (input)
- file (*MSKstring_t*) – File from which the function is called. (input)
- line (*unsigned*) – Line in the file from which the function is called. (input)

Return (*void**) – A pointer to the memory allocated through the task.

Groups *System, memory and debugging*

MSK_allocenv

```
void * (MSKAPI MSK_allocenv) (
    MSKenv_t env,
    const size_t number,
    const size_t size)
```

Equivalent to `calloc` i.e. allocate space for an array of length **number** where each element is of size **size**.

Parameters

- env (*MSKenv_t*) – The MOSEK environment. (input)
- number (*size_t*) – Number of elements. (input)
- size (*size_t*) – Size of each individual element. (input)

Return (*void**) – A pointer to the memory allocated through the environment.

Groups *System, memory and debugging*

MSK_allocctask

```
void * (MSKAPI MSK_allocctask) (
    MSKtask_t task,
    const size_t number,
    const size_t size)
```

Equivalent to `calloc` i.e. allocate space for an array of length **number** where each element is of size **size**.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- number (*size_t*) – Number of elements. (input)
- size (*size_t*) – Size of each individual element. (input)

Return (*void**) – A pointer to the memory allocated through the task.

Groups *System, memory and debugging*

MSK_checkinall

```
MSKrescodee (MSKAPI MSK_checkinall) (
    MSKenv_t env)
```

Check in all unused license features to the license token server.

Parameters *env* (*MSKenv_t*) – The MOSEK environment. (input)

Return (*MSKrescodee*) – The function response code.

Groups *License system*

MSK_checkinlicense

```
MSKrescodee (MSKAPI MSK_checkinlicense) (  
    MSKenv_t env,  
    MSKfeaturee feature)
```

Check in a license feature to the license server. By default all licenses consumed by functions using a single environment are kept checked out for the lifetime of the **MOSEK** environment. This function checks in a given license feature back to the license server immediately.

If the given license feature is not checked out at all, or it is in use by a call to *MSK_optimize*, calling this function has no effect.

Please note that returning a license to the license server incurs a small overhead, so frequent calls to this function should be avoided.

Parameters

- *env* (*MSKenv_t*) – The MOSEK environment. (input)
- *feature* (*MSKfeaturee*) – Feature to check in to the license system. (input)

Return (*MSKrescodee*) – The function response code.

Groups *License system*

MSK_checkmemenv

```
MSKrescodee (MSKAPI MSK_checkmemenv) (  
    MSKenv_t env,  
    const char * file,  
    MSKint32t line)
```

Checks the memory allocated by the environment.

Parameters

- *env* (*MSKenv_t*) – The MOSEK environment. (input)
- *file* (*MSKstring_t*) – File from which the function is called. (input)
- *line* (*MSKint32t*) – Line in the file from which the function is called. (input)

Return (*MSKrescodee*) – The function response code.

Groups *System, memory and debugging*

MSK_checkmemtask

```
MSKrescodee (MSKAPI MSK_checkmemtask) (  
    MSKtask_t task,  
    const char * file,  
    MSKint32t line)
```

Checks the memory allocated by the task.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *file* (*MSKstring_t*) – File from which the function is called. (input)
- *line* (*MSKint32t*) – Line in the file from which the function is called. (input)

Return (*MSKrescodee*) – The function response code.

Groups *System, memory and debugging*

MSK_checkoutlicense

```
MSKrescodee (MSKAPI MSK_checkoutlicense) (  
    MSKenv_t env,  
    MSKfeaturee feature)
```

Checks out a license feature from the license server. Normally the required license features will be automatically checked out the first time they are needed by the function *MSK_optimize*. This function can be used to check out one or more features ahead of time.

The feature will remain checked out until the environment is deleted or the function *MSK_checkinlicense* is called.

If a given feature is already checked out when this function is called, the call has no effect.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **feature** (*MSKfeaturee*) – Feature to check out from the license system. (input)

Return (*MSKrescodee*) – The function response code.

Groups *License system*

MSK_checkversion

```
MSKrescodee (MSKAPI MSK_checkversion) (  
    MSKenv_t env,  
    MSKint32t major,  
    MSKint32t minor,  
    MSKint32t revision)
```

Compares the version of the **MOSEK** DLL with a specified version. Returns *MSK_RES_OK* if the versions match and one of *MSK_RES_ERR_NEWER_DLL*, *MSK_RES_ERR_OLDER_DLL* otherwise.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **major** (*MSKint32t*) – Major version number. (input)
- **minor** (*MSKint32t*) – Minor version number. (input)
- **revision** (*MSKint32t*) – Revision number. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Versions*

MSK_chgconbound

```
MSKrescodee (MSKAPI MSK_chgconbound) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKint32t lower,  
    MSKint32t finite,  
    MSKrealt value)
```

Changes a bound for one constraint.

If **lower** is non-zero, then the lower bound is changed as follows:

$$\text{new lower bound} = \begin{cases} -\infty, & \text{finite} = 0, \\ \text{value} & \text{otherwise.} \end{cases}$$

Otherwise if **lower** is zero, then

$$\text{new upper bound} = \begin{cases} \infty, & \text{finite} = 0, \\ \text{value} & \text{otherwise.} \end{cases}$$

Please note that this function automatically updates the bound key for the bound, in particular, if the lower and upper bounds are identical, the bound key is changed to **fixed**.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index of the constraint for which the bounds should be changed. (input)
- **lower** (*MSKint32t*) – If non-zero, then the lower bound is changed, otherwise the upper bound is changed. (input)
- **finite** (*MSKint32t*) – If non-zero, then **value** is assumed to be finite. (input)
- **value** (*MSKrealt*) – New value for the bound. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - bounds, Problem data - constraints, Problem data - linear part*

MSK_chgvarbound

```
MSKrescodee (MSKAPI MSK_chgvarbound) (  
    MSKtask_t task,  
    MSKint32t j,  
    MSKint32t lower,  
    MSKint32t finite,  
    MSKrealt value)
```

Changes a bound for one variable.

If **lower** is non-zero, then the lower bound is changed as follows:

$$\text{new lower bound} = \begin{cases} -\infty, & \text{finite} = 0, \\ \text{value} & \text{otherwise.} \end{cases}$$

Otherwise if **lower** is zero, then

$$\text{new upper bound} = \begin{cases} \infty, & \text{finite} = 0, \\ \text{value} & \text{otherwise.} \end{cases}$$

Please note that this function automatically updates the bound key for the bound, in particular, if the lower and upper bounds are identical, the bound key is changed to **fixed**.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **j** (*MSKint32t*) – Index of the variable for which the bounds should be changed. (input)
- **lower** (*MSKint32t*) – If non-zero, then the lower bound is changed, otherwise the upper bound is changed. (input)
- **finite** (*MSKint32t*) – If non-zero, then **value** is assumed to be finite. (input)
- **value** (*MSKrealt*) – New value for the bound. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - bounds, Problem data - variables, Problem data - linear part*

MSK_clonetask

```
MSKrescodee (MSKAPI MSK_clonetask) (  
    MSKtask_t task,  
    MSKtask_t * clonedtask)
```

Creates a clone of an existing task copying all problem data and parameter settings to a new task. Callback functions are not copied.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **clonedtask** (*MSKtask_t by reference*) – The cloned task. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management*

MSK_commitchanges

```
MSKrescodee (MSKAPI MSK_commitchanges) (  
    MSKtask_t task)
```

Commits all cached problem changes to the task. It is usually not necessary to call this function explicitly since changes will be committed automatically when required.

Parameters *task* (*MSKtask_t*) – An optimization task. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management*

MSK_computesparscholesky

```
MSKrescodee (MSKAPI MSK_computesparscholesky) (  
    MSKenv_t env,  
    MSKint32t multithread,  
    MSKint32t ordermethod,  
    MSKrealt tolsingular,  
    MSKint32t n,  
    const MSKint32t * anzc,  
    const MSKint64t * aptrc,  
    const MSKint32t * asubc,  
    const MSKrealt * avalc,  
    MSKint32t ** perm,  
    MSKrealt ** diag,  
    MSKint32t ** lnzc,  
    MSKint64t ** lptrc,  
    MSKint64t * lensubnval,  
    MSKint32t ** lsubc,  
    MSKrealt ** lvalc)
```

The function computes a Cholesky factorization of a sparse positive semidefinite matrix. Sparsity is exploited during the computations to reduce the amount of space and work required. Both the input and output matrices are represented using the sparse format.

To be precise, given a symmetric matrix $A \in \mathbb{R}^{n \times n}$ the function computes a nonsingular lower triangular matrix L , a diagonal matrix D and a permutation matrix P such that

$$LL^T - D = PAP^T.$$

If *ordermethod* is zero then reordering heuristics are not employed and P is the identity.

If a pivot during the computation of the Cholesky factorization is less than

$$-\rho \cdot \max((PAP^T)_{jj}, 1.0)$$

then the matrix is declared negative semidefinite. On the hand if a pivot is smaller than

$$\rho \cdot \max((PAP^T)_{jj}, 1.0),$$

then D_{jj} is increased from zero to

$$\rho \cdot \max((PAP^T)_{jj}, 1.0).$$

Therefore, if A is sufficiently positive definite then D will be the zero matrix. Here ρ is set equal to value of *tolsingular*.

The function allocates memory for the output arrays. It must be freed by the user with *MSK_freeenv*.

Parameters

- `env` (*MSKenv_t*) – The MOSEK environment. (input)
- `multithread` (*MSKint32t*) – If nonzero then the function may exploit multiple threads. (input)
- `ordermethod` (*MSKint32t*) – If nonzero, then a sparsity preserving ordering will be employed. (input)
- `tolsingular` (*MSKrealt*) – A positive parameter controlling when a pivot is declared zero. (input)
- `n` (*MSKint32t*) – Specifies the order of A . (input)
- `anzc` (*MSKint32t**) – `anzc[j]` is the number of nonzeros in the j -th column of A . (input)
- `aptrc` (*MSKint64t**) – `aptrc[j]` is a pointer to the first element in column j of A . (input)
- `asubc` (*MSKint32t**) – Row indexes for each column stored in increasing order. (input)
- `avalc` (*MSKrealt**) – The value corresponding to row indexed stored in `asubc`. (input)
- `perm` (*MSKint32t* by reference*) – Permutation array used to specify the permutation matrix P computed by the function. (output)
- `diag` (*MSKrealt* by reference*) – The diagonal elements of matrix D . (output)
- `lnzc` (*MSKint32t* by reference*) – `lnzc[j]` is the number of non zero elements in column j of L . (output)
- `lptrc` (*MSKint64t* by reference*) – `lptrc[j]` is a pointer to the first row index and value in column j of L . (output)
- `lensubnval` (*MSKint64t by reference*) – Number of elements in `lsubc` and `lvalc`. (output)
- `lsubc` (*MSKint32t* by reference*) – Row indexes for each column stored in increasing order. (output)
- `lvalc` (*MSKrealt* by reference*) – The values corresponding to row indexed stored in `lsubc`. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Linear algebra*

MSK_conetypetostr

```
MSKrescodee (MSKAPI MSK_conetypetostr) (  
    MSKtask_t task,  
    MSKconetypee ct,  
    char * str)
```

Obtains the cone string identifier corresponding to a cone type.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `ct` (*MSKconetypee*) – Specifies the type of the cone. (input)
- `str` (*MSKstring_t*) – String corresponding to the cone type code `ct`. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names*

MSK_deleteenv

```
MSKrescodee (MSKAPI MSK_deleteenv) (  
    MSKenv_t * env)
```

Deletes a **MOSEK** environment and all the data associated with it.

Before calling this function it is a good idea to call the function *MSK_unlinkfuncfromenvstream* for each stream that has had a function linked to it.

Parameters *env* (*MSKenv_t by reference*) – The MOSEK environment. (input/output)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management*

MSK_deletesolution

```
MSKrescodee (MSKAPI MSK_deletesolution) (
    MSKtask_t task,
    MSKsoltypee whichsol)
```

Undefine a solution and free the memory it uses.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *whichsol* (*MSKsoltypee*) – Selects a solution. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management, Solution information*

MSK_deletetask

```
MSKrescodee (MSKAPI MSK_deletetask) (
    MSKtask_t * task)
```

Deletes a task.

Parameters *task* (*MSKtask_t by reference*) – An optimization task. (input/output)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management*

MSK_dot

```
MSKrescodee (MSKAPI MSK_dot) (
    MSKenv_t env,
    MSKint32t n,
    const MSKrealt * x,
    const MSKrealt * y,
    MSKrealt * xty)
```

Computes the inner product of two vectors x, y of length $n \geq 0$, i.e

$$x \cdot y = \sum_{i=1}^n x_i y_i.$$

Note that if $n = 0$, then the result of the operation is 0.

Parameters

- *env* (*MSKenv_t*) – The MOSEK environment. (input)
- *n* (*MSKint32t*) – Length of the vectors. (input)
- *x* (*MSKrealt**) – The x vector. (input)
- *y* (*MSKrealt**) – The y vector. (input)
- *xty* (*MSKrealt by reference*) – The result of the inner product between x and y . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Linear algebra*

MSK_dualsensitivity

```
MSKrescodee (MSKAPI MSK_dualsensitivity) (
    MSKtask_t task,
    MSKint32t numj,
    const MSKint32t * subj,
    MSKrealt * leftpricej,
    MSKrealt * rightpricej,
    MSKrealt * leftrangej,
    MSKrealt * rightrangej)
```

Calculates sensitivity information for objective coefficients. The indexes of the coefficients to analyze are

$$\{\text{subj}[i] \mid i = 0, \dots, \text{numj} - 1\}$$

The type of sensitivity analysis to perform (basis or optimal partition) is controlled by the parameter *MSK_IPAR_SENSITIVITY_TYPE*.

For an example, please see Section *Example: Sensitivity Analysis*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **numj** (*MSKint32t*) – Number of coefficients to be analyzed. Length of **subj**. (input)
- **subj** (*MSKint32t**) – Indexes of objective coefficients to analyze. (input)
- **leftpricej** (*MSKrealt**) – **leftpricej[j]** is the left shadow price for the coefficient with index **subj[j]**. (output)
- **rightpricej** (*MSKrealt**) – **rightpricej[j]** is the right shadow price for the coefficient with index **subj[j]**. (output)
- **leftrangej** (*MSKrealt**) – **leftrangej[j]** is the left range β_1 for the coefficient with index **subj[j]**. (output)
- **rightrangej** (*MSKrealt**) – **rightrangej[j]** is the right range β_2 for the coefficient with index **subj[j]**. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Sensitivity analysis*

MSK_echoenv

```
MSKrescodee (MSKAPIVA MSK_echoenv) (
    MSKenv_t env,
    MSKstreamtypee whichstream,
    const char * format,
    ...)
```

Prints a formatted message to the environment stream.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **whichstream** (*MSKstreamtypee*) – Index of the stream. (input)
- **format** (*MSKstring_t*) – Is a valid C format string which matches the arguments in ... (input)
- **varnumarg** (...) – A variable argument list. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging*

MSK_echointro

```
MSKrescodee (MSKAPI MSK_echointro) (  
    MSKenv_t env,  
    MSKint32t longver)
```

Prints an intro to message stream.

Parameters

- `env` (*MSKenv_t*) – The MOSEK environment. (input)
- `longver` (*MSKint32t*) – If non-zero, then the intro is slightly longer. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging*

MSK_echotask

```
MSKrescodee (MSKAPIVA MSK_echotask) (  
    MSKtask_t task,  
    MSKstreamtypee whichstream,  
    const char * format,  
    ...)
```

Prints a formatted string to a task stream.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichstream` (*MSKstreamtypee*) – Index of the stream. (input)
- `format` (*MSKstring_t*) – Is a valid C format string which matches the arguments in ... (input)
- `varnumarg` (...) – Additional arguments (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

MSK_freedbgenv

```
void (MSKAPI MSK_freedbgenv) (  
    MSKenv_t env,  
    void * buffer,  
    const char * file,  
    const unsigned line)
```

Frees space allocated by **MOSEK**. Debug version of *MSK_freeenv*.

Parameters

- `env` (*MSKenv_t*) – The MOSEK environment. (input)
- `buffer` (void*) – A pointer. (input/output)
- `file` (*MSKstring_t*) – File from which the function is called. (input)
- `line` (unsigned) – Line in the file from which the function is called. (input)

Return (void)

Groups *System, memory and debugging*

MSK_freedbgtask

```
void (MSKAPI MSK_freedbgtask) (  
    MSKtask_t task,  
    void * buffer,  
    const char * file,  
    const unsigned line)
```

Frees space allocated by **MOSEK**. Debug version of *MSK_freetask*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **buffer** (void*) – A pointer. (input/output)
- **file** (*MSKstring_t*) – File from which the function is called. (input)
- **line** (unsigned) – Line in the file from which the function is called. (input)

Return (void)

Groups *System, memory and debugging*

MSK_freeenv

```
void (MSKAPI MSK_freeenv) (  
    MSKenv_t env,  
    void * buffer)
```

Frees space allocated by a **MOSEK** function. Must not be applied to the **MOSEK** environment and task.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **buffer** (void*) – A pointer. (input/output)

Return (void)

Groups *System, memory and debugging*

MSK_freetask

```
void (MSKAPI MSK_freetask) (  
    MSKtask_t task,  
    void * buffer)
```

Frees space allocated by a **MOSEK** function. Must not be applied to the **MOSEK** environment and task.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **buffer** (void*) – A pointer. (input/output)

Return (void)

Groups *System, memory and debugging*

MSK_gemm

```
MSKrescodee (MSKAPI MSK_gemm) (  
    MSKenv_t env,  
    MSKtransposee transa,  
    MSKtransposee transb,  
    MSKint32t m,  
    MSKint32t n,  
    MSKint32t k,  
    MSKrealt alpha,  
    const MSKrealt * a,  
    const MSKrealt * b,  
    MSKrealt beta,  
    MSKrealt * c)
```

Performs a matrix multiplication plus addition of dense matrices. Given A , B and C of compatible dimensions, this function computes

$$C := \alpha op(A)op(B) + \beta C$$

where α, β are two scalar values. The function $op(X)$ denotes X if `transX` is `MSK_TRANSPOSE_NO`, or X^T if set to `MSK_TRANSPOSE_YES`. The matrix C has m rows and n columns, and the other matrices must have compatible dimensions.

The result of this operation is stored in C .

Parameters

- `env` (`MSKenv_t`) – The MOSEK environment. (input)
- `transa` (`MSKtransposee`) – Indicates whether the matrix A must be transposed. (input)
- `transb` (`MSKtransposee`) – Indicates whether the matrix B must be transposed. (input)
- `m` (`MSKint32t`) – Indicates the number of rows of matrix C . (input)
- `n` (`MSKint32t`) – Indicates the number of columns of matrix C . (input)
- `k` (`MSKint32t`) – Specifies the common dimension along which $op(A)$ and $op(B)$ are multiplied. For example, if neither A nor B are transposed, then this is the number of columns in A and also the number of rows in B . (input)
- `alpha` (`MSKrealt`) – A scalar value multiplying the result of the matrix multiplication. (input)
- `a` (`MSKrealt*`) – The pointer to the array storing matrix A in a column-major format. (input)
- `b` (`MSKrealt*`) – The pointer to the array storing matrix B in a column-major format. (input)
- `beta` (`MSKrealt`) – A scalar value that multiplies C . (input)
- `c` (`MSKrealt*`) – The pointer to the array storing matrix C in a column-major format. (input/output)

Return (`MSKrescodee`) – The function response code.

Groups *Linear algebra*

MSK_gemv

```
MSKrescodee (MSKAPI MSK_gemv) (
    MSKenv_t env,
    MSKtransposee transa,
    MSKint32t m,
    MSKint32t n,
    MSKrealt alpha,
    const MSKrealt * a,
    const MSKrealt * x,
    MSKrealt beta,
    MSKrealt * y)
```

Computes the multiplication of a scaled dense matrix times a dense vector, plus a scaled dense vector. Precisely, if `trans` is `MSK_TRANSPOSE_NO` then the update is

$$y := \alpha Ax + \beta y,$$

and if `trans` is `MSK_TRANSPOSE_YES` then

$$y := \alpha A^T x + \beta y,$$

where α, β are scalar values and A is a matrix with m rows and n columns.

Note that the result is stored overwriting y .

Parameters

- `env` (*MSKenv_t*) – The MOSEK environment. (input)
- `transa` (*MSKtransposee*) – Indicates whether the matrix A must be transposed. (input)
- `m` (*MSKint32t*) – Specifies the number of rows of the matrix A . (input)
- `n` (*MSKint32t*) – Specifies the number of columns of the matrix A . (input)
- `alpha` (*MSKrealt*) – A scalar value multiplying the matrix A . (input)
- `a` (*MSKrealt**) – A pointer to the array storing matrix A in a column-major format. (input)
- `x` (*MSKrealt**) – A pointer to the array storing the vector x . (input)
- `beta` (*MSKrealt*) – A scalar value multiplying the vector y . (input)
- `y` (*MSKrealt**) – A pointer to the array storing the vector y . (input/output)

Return (*MSKrescodee*) – The function response code.

Groups *Linear algebra*

MSK_generateconenames

```
MSKrescodee (MSKAPI MSK_generateconenames) (  
    MSKtask_t task,  
    MSKint32t num,  
    const MSKint32t * subk,  
    const char * fmt,  
    MSKint32t ndims,  
    const MSKint32t * dims,  
    const MSKint64t * sp)
```

Generates systematic names for cone.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of cone indexes. (input)
- `subk` (*MSKint32t**) – Indexes of the cone. (input)
- `fmt` (*MSKstring_t*) – The cone name formatting string. (input)
- `ndims` (*MSKint32t*) – Number of dimensions in the shape. (input)
- `dims` (*MSKint32t**) – Dimensions in the shape. (input)
- `sp` (*MSKint64t**) – Items that should be named. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - cones*

MSK_generateconnames

```
MSKrescodee (MSKAPI MSK_generateconnames) (  
    MSKtask_t task,  
    MSKint32t num,  
    const MSKint32t * subi,  
    const char * fmt,  
    MSKint32t ndims,  
    const MSKint32t * dims,  
    const MSKint64t * sp)
```

Generates systematic names for constraints.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of constraint indexes. (input)
- `subi` (*MSKint32t**) – Indexes of the constraints. (input)

- `fmt` (*MSKstring_t*) – The constraint name formatting string. (input)
- `ndims` (*MSKint32t*) – Number of dimensions in the shape. (input)
- `dims` (*MSKint32t**) – Dimensions in the shape. (input)
- `sp` (*MSKint64t**) – Items that should be named. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - constraints, Problem data - linear part*

MSK_generatevarnames

```
MSKrescodee (MSKAPI MSK_generatevarnames) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * subj,
    const char * fmt,
    MSKint32t ndims,
    const MSKint32t * dims,
    const MSKint64t * sp)
```

Generates systematic names for variables.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of variable indexes. (input)
- `subj` (*MSKint32t**) – Indexes of the variables. (input)
- `fmt` (*MSKstring_t*) – The variable name formatting string. (input)
- `ndims` (*MSKint32t*) – Number of dimensions in the shape. (input)
- `dims` (*MSKint32t**) – Dimensions in the shape. (input)
- `sp` (*MSKint64t**) – Items that should be named. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - variables, Problem data - linear part*

MSK_getacol

```
MSKrescodee (MSKAPI MSK_getacol) (
    MSKtask_t task,
    MSKint32t j,
    MSKint32t * nzj,
    MSKint32t * subj,
    MSKrealt * valj)
```

Obtains one column of A in a sparse format.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `j` (*MSKint32t*) – Index of the column. (input)
- `nzj` (*MSKint32t by reference*) – Number of non-zeros in the column obtained. (output)
- `subj` (*MSKint32t**) – Row indices of the non-zeros in the column obtained. (output)
- `valj` (*MSKrealt**) – Numerical values in the column obtained. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getacolnumnz

```
MSKrescodee (MSKAPI MSK_getacolnumnz) (
    MSKtask_t task,
    MSKint32t i,
    MSKint32t * nzj)
```

Obtains the number of non-zero elements in one column of A .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index of the column. (input)
- **nzj** (*MSKint32t by reference*) – Number of non-zeros in the j -th column of A . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getacolslice

```
MSKrescodee (MSKAPI MSK_getacolslice) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    MSKint32t maxnumnz,
    MSKint32t * surp,
    MSKint32t * ptrb,
    MSKint32t * ptre,
    MSKint32t * sub,
    MSKrealt * val)
```

Obtains a sequence of columns from A in sparse format.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **first** (*MSKint32t*) – Index of the first column in the sequence. (input)
- **last** (*MSKint32t*) – Index of the last column in the sequence **plus one**. (input)
- **maxnumnz** (*MSKint32t*) – Denotes the length of the arrays **sub** and **val**. (input)
- **surp** (*MSKint32t by reference*) – Surplus of subscript and coefficient arrays. The required entries are stored sequentially in **sub** and **val** starting from position **surp** away from the end of the arrays. Upon return **surp** will be decremented by the total number of non-zeros written. (input/output)
- **ptrb** (*MSKint32t**) – **ptrb[t]** is an index pointing to the first element in the t -th column obtained. (output)
- **ptre** (*MSKint32t**) – **ptre[t]** is an index pointing to the last element plus one in the t -th column obtained. (output)
- **sub** (*MSKint32t**) – Contains the row subscripts. (output)
- **val** (*MSKrealt**) – Contains the coefficient values. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getacolslice64

```
MSKrescodee (MSKAPI MSK_getacolslice64) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    MSKint64t maxnumnz,
    MSKint64t * surp,
```

(continues on next page)

```

MSKint64t * ptrb,
MSKint64t * ptre,
MSKint32t * sub,
MSKrealt * val)

```

Obtains a sequence of columns from A in sparse format.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **first** (*MSKint32t*) – Index of the first column in the sequence. (input)
- **last** (*MSKint32t*) – Index of the last column in the sequence **plus one**. (input)
- **maxnumnz** (*MSKint64t*) – Denotes the length of the arrays **sub** and **val**. (input)
- **surp** (*MSKint64t by reference*) – Surplus of subscript and coefficient arrays. The required entries are stored sequentially in **sub** and **val** starting from position **surp** away from the end of the arrays. Upon return **surp** will be decremented by the total number of non-zeros written. (input/output)
- **ptrb** (*MSKint64t**) – **ptrb[t]** is an index pointing to the first element in the t -th column obtained. (output)
- **ptre** (*MSKint64t**) – **ptre[t]** is an index pointing to the last element plus one in the t -th column obtained. (output)
- **sub** (*MSKint32t**) – Contains the row subscripts. (output)
- **val** (*MSKrealt**) – Contains the coefficient values. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getacolslicenumnz

```

MSKrescodee (MSKAPI MSK_getacolslicenumnz) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    MSKint32t * numnz)

```

Obtains the number of non-zeros in a slice of columns of A .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **first** (*MSKint32t*) – Index of the first column in the sequence. (input)
- **last** (*MSKint32t*) – Index of the last column **plus one** in the sequence. (input)
- **numnz** (*MSKint32t by reference*) – Number of non-zeros in the slice. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getacolslicenumnz64

```

MSKrescodee (MSKAPI MSK_getacolslicenumnz64) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    MSKint64t * numnz)

```

Obtains the number of non-zeros in a slice of columns of A .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **first** (*MSKint32t*) – Index of the first column in the sequence. (input)

- `last` (*MSKint32t*) – Index of the last column **plus one** in the sequence. (input)
 - `numnz` (*MSKint64t by reference*) – Number of non-zeros in the slice. (output)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Problem data - linear part, Inspecting the task*

MSK_getacolslicetrip

```
MSKrescodee (MSKAPI MSK_getacolslicetrip) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    MSKint64t maxnumnz,
    MSKint64t * surp,
    MSKint32t * subi,
    MSKint32t * subj,
    MSKrealt * val)
```

Obtains a sequence of columns from A in sparse triplet format. The function returns the content of all columns whose index j satisfies $\text{first} \leq j < \text{last}$. The triplets corresponding to nonzero entries are stored in the arrays `subi`, `subj` and `val`.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `first` (*MSKint32t*) – Index of the first column in the sequence. (input)
- `last` (*MSKint32t*) – Index of the last column in the sequence **plus one**. (input)
- `maxnumnz` (*MSKint64t*) – Denotes the length of the arrays `subi`, `subj`, and `val`. (input)
- `surp` (*MSKint64t by reference*) – Surplus of subscript and coefficient arrays. The required entries are stored sequentially in `subi`, `subj` and `val` starting from position `surp` away from the end of the arrays. On return `surp` will be decremented by the total number of non-zeros written. (input/output)
- `subi` (*MSKint32t**) – Constraint subscripts. (output)
- `subj` (*MSKint32t**) – Column subscripts. (output)
- `val` (*MSKrealt**) – Values. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getaij

```
MSKrescodee (MSKAPI MSK_getaij) (
    MSKtask_t task,
    MSKint32t i,
    MSKint32t j,
    MSKrealt * aij)
```

Obtains a single coefficient in A .

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `i` (*MSKint32t*) – Row index of the coefficient to be returned. (input)
- `j` (*MSKint32t*) – Column index of the coefficient to be returned. (input)
- `aij` (*MSKrealt by reference*) – The required coefficient $a_{i,j}$. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getapiecenumnz

```

MSKrescodee (MSKAPI MSK_getapieceumnz) (
    MSKtask_t task,
    MSKint32t firsti,
    MSKint32t lasti,
    MSKint32t firstj,
    MSKint32t lastj,
    MSKint32t * numnz)

```

Obtains the number non-zeros in a rectangular piece of A , i.e. the number of elements in the set

$$\{(i, j) : a_{i,j} \neq 0, \text{firsti} \leq i \leq \text{lasti} - 1, \text{firstj} \leq j \leq \text{lastj} - 1\}$$

This function is not an efficient way to obtain the number of non-zeros in one row or column. In that case use the function *MSK_getarownumnz* or *MSK_getacolnumnz*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **firsti** (*MSKint32t*) – Index of the first row in the rectangular piece. (input)
- **lasti** (*MSKint32t*) – Index of the last row plus one in the rectangular piece. (input)
- **firstj** (*MSKint32t*) – Index of the first column in the rectangular piece. (input)
- **lastj** (*MSKint32t*) – Index of the last column plus one in the rectangular piece. (input)
- **numnz** (*MSKint32t by reference*) – Number of non-zero A elements in the rectangular piece. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getarow

```

MSKrescodee (MSKAPI MSK_getarow) (
    MSKtask_t task,
    MSKint32t i,
    MSKint32t * nzi,
    MSKint32t * subi,
    MSKrealt * vali)

```

Obtains one row of A in a sparse format.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index of the row. (input)
- **nzi** (*MSKint32t by reference*) – Number of non-zeros in the row obtained. (output)
- **subi** (*MSKint32t**) – Column indices of the non-zeros in the row obtained. (output)
- **vali** (*MSKrealt**) – Numerical values of the row obtained. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getarownumnz

```

MSKrescodee (MSKAPI MSK_getarownumnz) (
    MSKtask_t task,
    MSKint32t i,
    MSKint32t * nzi)

```

Obtains the number of non-zero elements in one row of A .

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `i` (*MSKint32t*) – Index of the row. (input)
- `nzi` (*MSKint32t by reference*) – Number of non-zeros in the i -th row of A . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getarowslice

```
MSKrescodee (MSKAPI MSK_getarowslice) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    MSKint32t maxnumnz,
    MSKint32t * surp,
    MSKint32t * ptrb,
    MSKint32t * ptre,
    MSKint32t * sub,
    MSKrealt * val)
```

Obtains a sequence of rows from A in sparse format.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `first` (*MSKint32t*) – Index of the first row in the sequence. (input)
- `last` (*MSKint32t*) – Index of the last row in the sequence **plus one**. (input)
- `maxnumnz` (*MSKint32t*) – Denotes the length of the arrays `sub` and `val`. (input)
- `surp` (*MSKint32t by reference*) – Surplus of subscript and coefficient arrays. The required entries are stored sequentially in `sub` and `val` starting from position `surp` away from the end of the arrays. Upon return `surp` will be decremented by the total number of non-zeros written. (input/output)
- `ptrb` (*MSKint32t**) – `ptrb[t]` is an index pointing to the first element in the t -th row obtained. (output)
- `ptre` (*MSKint32t**) – `ptre[t]` is an index pointing to the last element plus one in the t -th row obtained. (output)
- `sub` (*MSKint32t**) – Contains the column subscripts. (output)
- `val` (*MSKrealt**) – Contains the coefficient values. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getarowslice64

```
MSKrescodee (MSKAPI MSK_getarowslice64) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    MSKint64t maxnumnz,
    MSKint64t * surp,
    MSKint64t * ptrb,
    MSKint64t * ptre,
    MSKint32t * sub,
    MSKrealt * val)
```

Obtains a sequence of rows from A in sparse format.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `first` (*MSKint32t*) – Index of the first row in the sequence. (input)
- `last` (*MSKint32t*) – Index of the last row in the sequence **plus one**. (input)
- `maxnumnz` (*MSKint64t*) – Denotes the length of the arrays `sub` and `val`. (input)
- `surp` (*MSKint64t by reference*) – Surplus of subscript and coefficient arrays. The required entries are stored sequentially in `sub` and `val` starting from position `surp` away from the end of the arrays. Upon return `surp` will be decremented by the total number of non-zeros written. (input/output)
- `ptrb` (*MSKint64t**) – `ptrb[t]` is an index pointing to the first element in the t -th row obtained. (output)
- `ptre` (*MSKint64t**) – `ptre[t]` is an index pointing to the last element plus one in the t -th row obtained. (output)
- `sub` (*MSKint32t**) – Contains the column subscripts. (output)
- `val` (*MSKreal_t**) – Contains the coefficient values. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getarowslicenumnz

```
MSKrescodee (MSKAPI MSK_getarowslicenumnz) (  
    MSKtask_t task,  
    MSKint32t first,  
    MSKint32t last,  
    MSKint32t * numnz)
```

Obtains the number of non-zeros in a slice of rows of A .

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `first` (*MSKint32t*) – Index of the first row in the sequence. (input)
- `last` (*MSKint32t*) – Index of the last row **plus one** in the sequence. (input)
- `numnz` (*MSKint32t by reference*) – Number of non-zeros in the slice. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getarowslicenumnz64

```
MSKrescodee (MSKAPI MSK_getarowslicenumnz64) (  
    MSKtask_t task,  
    MSKint32t first,  
    MSKint32t last,  
    MSKint64t * numnz)
```

Obtains the number of non-zeros in a slice of rows of A .

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `first` (*MSKint32t*) – Index of the first row in the sequence. (input)
- `last` (*MSKint32t*) – Index of the last row **plus one** in the sequence. (input)
- `numnz` (*MSKint64t by reference*) – Number of non-zeros in the slice. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getarowslicetrip

```

MSKrescodee (MSKAPI MSK_getarowslicetrip) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    MSKint64t maxnumnz,
    MSKint64t * surp,
    MSKint32t * subi,
    MSKint32t * subj,
    MSKrealt * val)

```

Obtains a sequence of rows from A in sparse triplet format. The function returns the content of all rows whose index i satisfies $\text{first} \leq i < \text{last}$. The triplets corresponding to nonzero entries are stored in the arrays `subi`, `subj` and `val`.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `first` (*MSKint32t*) – Index of the first row in the sequence. (input)
- `last` (*MSKint32t*) – Index of the last row in the sequence **plus one**. (input)
- `maxnumnz` (*MSKint64t*) – Denotes the length of the arrays `subi`, `subj`, and `val`. (input)
- `surp` (*MSKint64t by reference*) – Surplus of subscript and coefficient arrays. The required entries are stored sequentially in `subi`, `subj` and `val` starting from position `surp` away from the end of the arrays. On return `surp` will be decremented by the total number of non-zeros written. (input/output)
- `subi` (*MSKint32t**) – Constraint subscripts. (output)
- `subj` (*MSKint32t**) – Column subscripts. (output)
- `val` (*MSKrealt**) – Values. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getatruncatetol

```

MSKrescodee (MSKAPI MSK_getatruncatetol) (
    MSKtask_t task,
    MSKrealt * tolzero)

```

Obtains the tolerance value set with *MSK_putatruncatetol*.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `tolzero` (*MSKrealt**) – All elements $|a_{i,j}|$ less than this tolerance is truncated to zero. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters, Problem data - linear part*

MSK_getbarablocktriplet

```

MSKrescodee (MSKAPI MSK_getbarablocktriplet) (
    MSKtask_t task,
    MSKint64t maxnum,
    MSKint64t * num,
    MSKint32t * subi,
    MSKint32t * subj,
    MSKint32t * subk,
    MSKint32t * subl,
    MSKrealt * valijkl)

```

Obtains \overline{A} in block triplet form.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnum** (*MSKint64t*) – **subi**, **subj**, **subk**, **subl** and **valijkl** must be **maxnum** long. (input)
- **num** (*MSKint64t by reference*) – Number of elements in the block triplet form. (output)
- **subi** (*MSKint32t**) – Constraint index. (output)
- **subj** (*MSKint32t**) – Symmetric matrix variable index. (output)
- **subk** (*MSKint32t**) – Block row index. (output)
- **subl** (*MSKint32t**) – Block column index. (output)
- **valijkl** (*MSKrealt**) – The numerical value associated with each block triplet. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getbaraidx

```
MSKrescodee (MSKAPI MSK_getbaraidx) (  
    MSKtask_t task,  
    MSKint64t idx,  
    MSKint64t maxnum,  
    MSKint32t * i,  
    MSKint32t * j,  
    MSKint64t * num,  
    MSKint64t * sub,  
    MSKrealt * weights)
```

Obtains information about an element in \bar{A} . Since \bar{A} is a sparse matrix of symmetric matrices, only the nonzero elements in \bar{A} are stored in order to save space. Now \bar{A} is stored vectorized i.e. as one long vector. This function makes it possible to obtain information such as the row index and the column index of a particular element of the vectorized form of \bar{A} .

Please observe if one element of \bar{A} is inputted multiple times then it may be stored several times in vectorized form. In that case the element with the highest index is the one that is used.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **idx** (*MSKint64t*) – Position of the element in the vectorized form. (input)
- **maxnum** (*MSKint64t*) – **sub** and **weights** must be at least **maxnum** long. (input)
- **i** (*MSKint32t by reference*) – Row index of the element at position **idx**. (output)
- **j** (*MSKint32t by reference*) – Column index of the element at position **idx**. (output)
- **num** (*MSKint64t by reference*) – Number of terms in weighted sum that forms the element. (output)
- **sub** (*MSKint64t**) – A list indexes of the elements from symmetric matrix storage that appear in the weighted sum. (output)
- **weights** (*MSKrealt**) – The weights associated with each term in the weighted sum. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getbaraidxij

```
MSKrescodee (MSKAPI MSK_getbaraidxij) (  
    MSKtask_t task,  
    MSKint64t idx,  
    MSKint32t * i,  
    MSKint32t * j)
```

Obtains information about an element in \bar{A} . Since \bar{A} is a sparse matrix of symmetric matrices, only the nonzero elements in \bar{A} are stored in order to save space. Now \bar{A} is stored vectorized i.e. as one long vector. This function makes it possible to obtain information such as the row index and the column index of a particular element of the vectorized form of \bar{A} .

Please note that if one element of \bar{A} is inputted multiple times then it may be stored several times in vectorized form. In that case the element with the highest index is the one that is used.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **idx** (*MSKint64t*) – Position of the element in the vectorized form. (input)
- **i** (*MSKint32t by reference*) – Row index of the element at position idx. (output)
- **j** (*MSKint32t by reference*) – Column index of the element at position idx. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getbaraidxinfo

```
MSKrescodee (MSKAPI MSK_getbaraidxinfo) (
    MSKtask_t task,
    MSKint64t idx,
    MSKint64t * num)
```

Each nonzero element in \bar{A}_{ij} is formed as a weighted sum of symmetric matrices. Using this function the number of terms in the weighted sum can be obtained. See description of *MSK_appendsparsesymmat* for details about the weighted sum.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **idx** (*MSKint64t*) – The internal position of the element for which information should be obtained. (input)
- **num** (*MSKint64t by reference*) – Number of terms in the weighted sum that form the specified element in \bar{A} . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getbarasparsity

```
MSKrescodee (MSKAPI MSK_getbarasparsity) (
    MSKtask_t task,
    MSKint64t maxnumnz,
    MSKint64t * numnz,
    MSKint64t * idxij)
```

The matrix \bar{A} is assumed to be a sparse matrix of symmetric matrices. This implies that many of the elements in \bar{A} are likely to be zero matrices. Therefore, in order to save space, only nonzero elements in \bar{A} are stored on vectorized form. This function is used to obtain the sparsity pattern of \bar{A} and the position of each nonzero element in the vectorized form of \bar{A} . From the index detailed information about each nonzero $\bar{A}_{i,j}$ can be obtained using *MSK_getbaraidxinfo* and *MSK_getbaraidx*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumnz** (*MSKint64t*) – The array idxij must be at least maxnumnz long. (input)
- **numnz** (*MSKint64t by reference*) – Number of nonzero elements in \bar{A} . (output)

- `idxij` (*MSKint64t**) – Position of each nonzero element in the vectorized form of \bar{A} . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getbarcblocktriplet

```
MSKrescodee (MSKAPI MSK_getbarcblocktriplet) (
    MSKtask_t task,
    MSKint64t maxnum,
    MSKint64t * num,
    MSKint32t * subj,
    MSKint32t * subk,
    MSKint32t * subl,
    MSKrealt * valjkl)
```

Obtains \bar{C} in block triplet form.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `maxnum` (*MSKint64t*) – `subj`, `subk`, `subl` and `valjkl` must be `maxnum` long. (input)
- `num` (*MSKint64t by reference*) – Number of elements in the block triplet form. (output)
- `subj` (*MSKint32t**) – Symmetric matrix variable index. (output)
- `subk` (*MSKint32t**) – Block row index. (output)
- `subl` (*MSKint32t**) – Block column index. (output)
- `valjkl` (*MSKrealt**) – The numerical value associated with each block triplet. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getbarcidx

```
MSKrescodee (MSKAPI MSK_getbarcidx) (
    MSKtask_t task,
    MSKint64t idx,
    MSKint64t maxnum,
    MSKint32t * j,
    MSKint64t * num,
    MSKint64t * sub,
    MSKrealt * weights)
```

Obtains information about an element in \bar{C} .

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `idx` (*MSKint64t*) – Index of the element for which information should be obtained. (input)
- `maxnum` (*MSKint64t*) – `sub` and `weights` must be at least `maxnum` long. (input)
- `j` (*MSKint32t by reference*) – Row index in \bar{C} . (output)
- `num` (*MSKint64t by reference*) – Number of terms in the weighted sum. (output)
- `sub` (*MSKint64t**) – Elements appearing the weighted sum. (output)
- `weights` (*MSKrealt**) – Weights of terms in the weighted sum. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getbarcidxinfo

```
MSKrescodee (MSKAPI MSK_getbarcidxinfo) (  
    MSKtask_t task,  
    MSKint64t idx,  
    MSKint64t * num)
```

Obtains the number of terms in the weighted sum that forms a particular element in \overline{C} .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **idx** (*MSKint64t*) – Index of the element for which information should be obtained. The value is an index of a symmetric sparse variable. (input)
- **num** (*MSKint64t by reference*) – Number of terms that appear in the weighted sum that forms the requested element. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getbarcidxj

```
MSKrescodee (MSKAPI MSK_getbarcidxj) (  
    MSKtask_t task,  
    MSKint64t idx,  
    MSKint32t * j)
```

Obtains the row index of an element in \overline{C} .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **idx** (*MSKint64t*) – Index of the element for which information should be obtained. (input)
- **j** (*MSKint32t by reference*) – Row index in \overline{C} . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getbarcsparsity

```
MSKrescodee (MSKAPI MSK_getbarcsparsity) (  
    MSKtask_t task,  
    MSKint64t maxnumnz,  
    MSKint64t * numnz,  
    MSKint64t * idxj)
```

Internally only the nonzero elements of \overline{C} are stored in a vector. This function is used to obtain the nonzero elements of \overline{C} and their indexes in the internal vector representation (in **idxj**). From the index detailed information about each nonzero \overline{C}_j can be obtained using *MSK_getbarcidxinfo* and *MSK_getbarcidx*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumnz** (*MSKint64t*) – **idxj** must be at least **maxnumnz** long. (input)
- **numnz** (*MSKint64t by reference*) – Number of nonzero elements in \overline{C} . (output)
- **idxj** (*MSKint64t**) – Internal positions of the nonzero elements in \overline{C} . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getbarsj

```
MSKrescodee (MSKAPI MSK_getbarsj) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKint32t j,  
    MSKrealt * barsj)
```

Obtains the dual solution for a semidefinite variable. Only the lower triangular part of \bar{S}_j is returned because the matrix by construction is symmetric. The format is that the columns are stored sequentially in the natural order.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **j** (*MSKint32t*) – Index of the semidefinite variable. (input)
- **barsj** (*MSKrealt**) – Value of \bar{S}_j . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - semidefinite*

MSK_getbarsslice

```
MSKrescodee (MSKAPI MSK_getbarsslice) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKint32t first,  
    MSKint32t last,  
    MSKint64t slicesize,  
    MSKrealt * barsslice)
```

Obtains the dual solution for a sequence of semidefinite variables. The format is that matrices are stored sequentially, and in each matrix the columns are stored as in *MSK_getbarsj*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – Index of the first semidefinite variable in the slice. (input)
- **last** (*MSKint32t*) – Index of the last semidefinite variable in the slice plus one. (input)
- **slicesize** (*MSKint64t*) – Denotes the length of the array **barsslice**. (input)
- **barsslice** (*MSKrealt**) – Dual solution values of symmetric matrix variables in the slice, stored sequentially. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - semidefinite*

MSK_getbarvarname

```
MSKrescodee (MSKAPI MSK_getbarvarname) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKint32t sizename,  
    char * name)
```

Obtains the name of a semidefinite variable.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)

- `i` (*MSKint32t*) – Index of the variable. (input)
- `size` (*MSKint32t*) – Length of the name buffer. (input)
- `name` (*MSKstring_t*) – The requested name is copied to this buffer. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Inspecting the task*

MSK_getbarvarnameindex

```
MSKrescodee (MSKAPI MSK_getbarvarnameindex) (
    MSKtask_t task,
    const char * somename,
    MSKint32t * asgn,
    MSKint32t * index)
```

Obtains the index of semidefinite variable from its name.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `somename` (*MSKstring_t*) – The name of the variable. (input)
- `asgn` (*MSKint32t by reference*) – Non-zero if the name `somename` is assigned to some semidefinite variable. (output)
- `index` (*MSKint32t by reference*) – The index of a semidefinite variable with the name `somename` (if one exists). (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Inspecting the task*

MSK_getbarvarnamelen

```
MSKrescodee (MSKAPI MSK_getbarvarnamelen) (
    MSKtask_t task,
    MSKint32t i,
    MSKint32t * len)
```

Obtains the length of the name of a semidefinite variable.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `i` (*MSKint32t*) – Index of the variable. (input)
- `len` (*MSKint32t by reference*) – Returns the length of the indicated name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Inspecting the task*

MSK_getbarxj

```
MSKrescodee (MSKAPI MSK_getbarxj) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t j,
    MSKrealt * barxj)
```

Obtains the primal solution for a semidefinite variable. Only the lower triangular part of \bar{X}_j is returned because the matrix by construction is symmetric. The format is that the columns are stored sequentially in the natural order.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)

- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `j` (*MSKint32t*) – Index of the semidefinite variable. (input)
- `barxj` (*MSKrealt**) – Value of \bar{X}_j . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - semidefinite*

MSK_getbarxslice

```
MSKrescodee (MSKAPI MSK_getbarxslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    MSKint64t slicesize,
    MSKrealt * barxslice)
```

Obtains the primal solution for a sequence of semidefinite variables. The format is that matrices are stored sequentially, and in each matrix the columns are stored as in *MSK_getbarxj*.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `first` (*MSKint32t*) – Index of the first semidefinite variable in the slice. (input)
- `last` (*MSKint32t*) – Index of the last semidefinite variable in the slice plus one. (input)
- `slicesize` (*MSKint64t*) – Denotes the length of the array `barxslice`. (input)
- `barxslice` (*MSKrealt**) – Solution values of symmetric matrix variables in the slice, stored sequentially. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - semidefinite*

MSK_getbuildinfo

```
MSKrescodee (MSKAPI MSK_getbuildinfo) (
    char * buildstate,
    char * builddate)
```

Obtains build information.

Parameters

- `buildstate` (*MSKstring_t*) – State of binaries, i.e. a debug, release candidate or final release. (output)
- `builddate` (*MSKstring_t*) – Date when the binaries were built. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Versions*

MSK_getc

```
MSKrescodee (MSKAPI MSK_getc) (
    MSKtask_t task,
    MSKrealt * c)
```

Obtains all objective coefficients *c*.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)

- *c* (*MSKrealt**) – Linear terms of the objective as a dense vector. The length is the number of variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task, Problem data - variables*

MSK_getcallbackfunc

```
MSKrescodee (MSKAPI MSK_getcallbackfunc) (
    MSKtask_t task,
    MSKcallbackfunc * func,
    MSKuserhandle_t * handle)
```

Obtains the current user-defined callback function and associated user handle.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *func* (*MSKcallbackfunc by reference*) – Get the user-defined progress callback function *MSKcallbackfunc* associated with *task*. If *func* is identical to NULL, then no callback function is associated with the *task*. (output)
- *handle* (*MSKuserhandle_t by reference*) – The user-defined pointer associated with the user-defined callback function. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Callback*

MSK_getcfix

```
MSKrescodee (MSKAPI MSK_getcfix) (
    MSKtask_t task,
    MSKrealt * cfix)
```

Obtains the fixed term in the objective.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *cfix* (*MSKrealt by reference*) – Fixed term in the objective. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task*

MSK_getcj

```
MSKrescodee (MSKAPI MSK_getcj) (
    MSKtask_t task,
    MSKint32t j,
    MSKrealt * cj)
```

Obtains one coefficient of *c*.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *j* (*MSKint32t*) – Index of the variable for which the *c* coefficient should be obtained. (input)
- *cj* (*MSKrealt by reference*) – The value of *c_j*. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task, Problem data - variables*

MSK_getclist

```
MSKrescodee (MSKAPI MSK_getclist) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * subj,
    MSKrealt * c)
```

Obtains a sequence of elements in *c*.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *num* (*MSKint32t*) – Number of variables for which the *c* values should be obtained. (input)
- *subj* (*MSKint32t**) – A list of variable indexes. (input)
- *c* (*MSKrealt**) – Linear terms of the requested list of the objective as a dense vector. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - linear part*

MSK_getcodedesc

```
MSKrescodee (MSKAPI MSK_getcodedesc) (
    MSKrescodee code,
    char * symname,
    char * str)
```

Obtains a short description of the meaning of the response code given by *code*.

Parameters

- *code* (*MSKrescodee*) – A valid **MOSEK** response code. (input)
- *symname* (*MSKstring_t*) – Symbolic name corresponding to *code*. (output)
- *str* (*MSKstring_t*) – Obtains a short description of a response code. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Responses, errors and warnings*

MSK_getconbound

```
MSKrescodee (MSKAPI MSK_getconbound) (
    MSKtask_t task,
    MSKint32t i,
    MSKboundkeye * bk,
    MSKrealt * bl,
    MSKrealt * bu)
```

Obtains bound information for one constraint.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *i* (*MSKint32t*) – Index of the constraint for which the bound information should be obtained. (input)
- *bk* (*MSKboundkeye by reference*) – Bound keys. (output)
- *bl* (*MSKrealt by reference*) – Values for lower bounds. (output)
- *bu* (*MSKrealt by reference*) – Values for upper bounds. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task, Problem data - bounds, Problem data - constraints*

MSK_getconboundslice

```
MSKrescodee (MSKAPI MSK_getconboundslice) (  
    MSKtask_t task,  
    MSKint32t first,  
    MSKint32t last,  
    MSKboundkeye * bk,  
    MSKrealt * bl,  
    MSKrealt * bu)
```

Obtains bounds information for a slice of the constraints.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **bk** (*MSKboundkeye**) – Bound keys. (output)
- **bl** (*MSKrealt**) – Values for lower bounds. (output)
- **bu** (*MSKrealt**) – Values for upper bounds. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task, Problem data - bounds, Problem data - constraints*

MSK_getcone

```
MSKrescodee (MSKAPI MSK_getcone) (  
    MSKtask_t task,  
    MSKint32t k,  
    MSKconetypee * ct,  
    MSKrealt * coneapar,  
    MSKint32t * nummem,  
    MSKint32t * submem)
```

Obtains a cone.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **k** (*MSKint32t*) – Index of the cone. (input)
- **ct** (*MSKconetypee by reference*) – Specifies the type of the cone. (output)
- **coneapar** (*MSKrealt by reference*) – For the power cone it denotes the exponent alpha. For other cone types it is unused and can be set to 0. (output)
- **nummem** (*MSKint32t by reference*) – Number of member variables in the cone. (output)
- **submem** (*MSKint32t**) – Variable subscripts of the members in the cone. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - cones*

MSK_getconeinfo

```
MSKrescodee (MSKAPI MSK_getconeinfo) (  
    MSKtask_t task,  
    MSKint32t k,  
    MSKconetypee * ct,  
    MSKrealt * coneapar,  
    MSKint32t * nummem)
```

Obtains information about a cone.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **k** (*MSKint32t*) – Index of the cone. (input)
- **ct** (*MSKconetypee by reference*) – Specifies the type of the cone. (output)
- **conepar** (*MSKrealt by reference*) – For the power cone it denotes the exponent alpha. For other cone types it is unused and can be set to 0. (output)
- **nummem** (*MSKint32t by reference*) – Number of member variables in the cone. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - cones*

MSK_getconename

```
MSKrescodee (MSKAPI MSK_getconename) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKint32t sizename,  
    char * name)
```

Obtains the name of a cone.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index of the cone. (input)
- **sizename** (*MSKint32t*) – Maximum length of a name that can be stored in **name**. (input)
- **name** (*MSKstring_t*) – The required name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - cones, Inspecting the task*

MSK_getconenameindex

```
MSKrescodee (MSKAPI MSK_getconenameindex) (  
    MSKtask_t task,  
    const char * somename,  
    MSKint32t * asgn,  
    MSKint32t * index)
```

Checks whether the name **somename** has been assigned to any cone. If it has been assigned to a cone, then the index of the cone is reported.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **somename** (*MSKstring_t*) – The name which should be checked. (input)
- **asgn** (*MSKint32t by reference*) – Is non-zero if the name **somename** is assigned to some cone. (output)
- **index** (*MSKint32t by reference*) – If the name **somename** is assigned to some cone, then **index** is the index of the cone. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - cones, Inspecting the task*

MSK_getconenamelen

```
MSKrescodee (MSKAPI MSK_getconenamelen) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKint32t * len)
```


Obtains the length of the name of a cone.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index of the cone. (input)
- **len** (*MSKint32t by reference*) – Returns the length of the indicated name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - cones, Inspecting the task*

MSK_getconname

```
MSKrescodee (MSKAPI MSK_getconname) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKint32t sizename,  
    char * name)
```

Obtains the name of a constraint.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index of the constraint. (input)
- **sizename** (*MSKint32t*) – Maximum length of name that can be stored in **name**. (input)
- **name** (*MSKstring_t*) – The required name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - linear part, Problem data - constraints, Inspecting the task*

MSK_getconnameindex

```
MSKrescodee (MSKAPI MSK_getconnameindex) (  
    MSKtask_t task,  
    const char * somename,  
    MSKint32t * asgn,  
    MSKint32t * index)
```

Checks whether the name **somename** has been assigned to any constraint. If so, the index of the constraint is reported.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **somename** (*MSKstring_t*) – The name which should be checked. (input)
- **asgn** (*MSKint32t by reference*) – Is non-zero if the name **somename** is assigned to some constraint. (output)
- **index** (*MSKint32t by reference*) – If the name **somename** is assigned to a constraint, then **index** is the index of the constraint. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - linear part, Problem data - constraints, Inspecting the task*

MSK_getconnamelen

```
MSKrescodee (MSKAPI MSK_getconnamelen) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKint32t * len)
```

Obtains the length of the name of a constraint.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index of the constraint. (input)
- **len** (*MSKint32t by reference*) – Returns the length of the indicated name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - linear part, Problem data - constraints, Inspecting the task*

MSK_getcslice

```
MSKrescodee (MSKAPI MSK_getcslice) (  
    MSKtask_t task,  
    MSKint32t first,  
    MSKint32t last,  
    MSKrealt * c)
```

Obtains a sequence of elements in *c*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **c** (*MSKrealt**) – Linear terms of the requested slice of the objective as a dense vector. The length is **last-first**. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - linear part*

MSK_getdimbarvarj

```
MSKrescodee (MSKAPI MSK_getdimbarvarj) (  
    MSKtask_t task,  
    MSKint32t j,  
    MSKint32t * dimbarvarj)
```

Obtains the dimension of a symmetric matrix variable.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **j** (*MSKint32t*) – Index of the semidefinite variable whose dimension is requested. (input)
- **dimbarvarj** (*MSKint32t by reference*) – The dimension of the *j*-th semidefinite variable. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - semidefinite*

MSK_getdouinf

```
MSKrescodee (MSKAPI MSK_getdouinf) (  
    MSKtask_t task,  
    MSKdinfiteme whichdinf,  
    MSKrealt * dvalue)
```

Obtains a double information item from the task information database.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichdinf` (*MSKdinfiteme*) – Specifies a double information item. (input)
- `dvalue` (*MSKrealt by reference*) – The value of the required double information item. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Information items and statistics*

MSK_getdouparam

```
MSKrescodee (MSKAPI MSK_getdouparam) (
    MSKtask_t task,
    MSKdparame param,
    MSKrealt * parvalue)
```

Obtains the value of a double parameter.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `param` (*MSKdparame*) – Which parameter. (input)
- `parvalue` (*MSKrealt by reference*) – Parameter value. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_getdualobj

```
MSKrescodee (MSKAPI MSK_getdualobj) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * dualobj)
```

Computes the dual objective value associated with the solution. Note that if the solution is a primal infeasibility certificate, then the fixed term in the objective value is not included.

Moreover, since there is no dual solution associated with an integer solution, an error will be reported if the dual objective value is requested for the integer solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `dualobj` (*MSKrealt by reference*) – Objective value corresponding to the dual solution. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information, Solution - dual*

MSK_getdualsolutionnorms

```
MSKrescodee (MSKAPI MSK_getdualsolutionnorms) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * nrmx,
    MSKrealt * nrmslc,
    MSKrealt * nrmsuc,
    MSKrealt * nrmslx,
    MSKrealt * nrmsux,
    MSKrealt * nrmsnx,
    MSKrealt * nrmbars)
```

Compute norms of the dual solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `nrmy` (*MSKrealt by reference*) – The norm of the y vector. (output)
- `nrmslc` (*MSKrealt by reference*) – The norm of the s_l^c vector. (output)
- `nrmsuc` (*MSKrealt by reference*) – The norm of the s_u^c vector. (output)
- `nrmslx` (*MSKrealt by reference*) – The norm of the s_l^x vector. (output)
- `nrmsux` (*MSKrealt by reference*) – The norm of the s_u^x vector. (output)
- `nrmsnx` (*MSKrealt by reference*) – The norm of the s_n^x vector. (output)
- `nrmbars` (*MSKrealt by reference*) – The norm of the \bar{S} vector. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getdviolbarvar

```
MSKrescodee (MSKAPI MSK_getdviolbarvar) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t num,
    const MSKint32t * sub,
    MSKrealt * viol)
```

Let $(\bar{S}_j)^*$ be the value of variable \bar{S}_j for the specified solution. Then the dual violation of the solution associated with variable \bar{S}_j is given by

$$\max(-\lambda_{\min}(\bar{S}_j), 0.0).$$

Both when the solution is a certificate of primal infeasibility and when it is dual feasible solution the violation should be small.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `num` (*MSKint32t*) – Length of `sub` and `viol`. (input)
- `sub` (*MSKint32t**) – An array of indexes of \bar{X} variables. (input)
- `viol` (*MSKrealt**) – `viol[k]` is the violation of the solution for the constraint $\bar{S}_{\text{sub}[k]} \in \mathcal{S}_+$. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getdviolcon

```
MSKrescodee (MSKAPI MSK_getdviolcon) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t num,
    const MSKint32t * sub,
    MSKrealt * viol)
```

The violation of the dual solution associated with the i -th constraint is computed as follows

$$\max(\rho((s_l^c)_i^*, (b_l^c)_i), \rho((s_u^c)_i^*, -(b_u^c)_i), | -y_i + (s_l^c)_i^* - (s_u^c)_i^* |)$$

where

$$\rho(x, l) = \begin{cases} -x, & l > -\infty, \\ |x|, & \text{otherwise.} \end{cases}$$

Both when the solution is a certificate of primal infeasibility or it is a dual feasible solution the violation should be small.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **num** (*MSKint32t*) – Length of **sub** and **viol**. (input)
- **sub** (*MSKint32t**) – An array of indexes of constraints. (input)
- **viol** (*MSKrealt**) – **viol**[k] is the violation of dual solution associated with the constraint **sub**[k]. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getdviolcones

```
MSKrescodee (MSKAPI MSK_getdviolcones) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t num,
    const MSKint32t * sub,
    MSKrealt * viol)
```

Let $(s_n^x)^*$ be the value of variable (s_n^x) for the specified solution. For simplicity let us assume that s_n^x is a member of a quadratic cone, then the violation is computed as follows

$$\begin{cases} \max(0, (\|s_n^x\|_{2:n}^* - (s_n^x)_1^*)/\sqrt{2}, & (s_n^x)^* \geq -\|(s_n^x)_{2:n}^*\|, \\ \|(s_n^x)^*\|, & \text{otherwise.} \end{cases}$$

Both when the solution is a certificate of primal infeasibility or when it is a dual feasible solution the violation should be small.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **num** (*MSKint32t*) – Length of **sub** and **viol**. (input)
- **sub** (*MSKint32t**) – An array of indexes of conic constraints. (input)
- **viol** (*MSKrealt**) – **viol**[k] is the violation of the dual solution associated with the conic constraint **sub**[k]. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getdviolvar

```
MSKrescodee (MSKAPI MSK_getdviolvar) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t num,
    const MSKint32t * sub,
    MSKrealt * viol)
```

The violation of the dual solution associated with the j -th variable is computed as follows

$$\max \left(\rho((s_l^x)^*, (b_l^x)_j), \rho((s_u^x)^*, -(b_u^x)_j), \left| \sum_{i=0}^{numcon-1} a_{ij}y_i + (s_l^x)_j^* - (s_u^x)_j^* - \tau c_j \right| \right)$$

where

$$\rho(x, l) = \begin{cases} -x, & l > -\infty, \\ |x|, & \text{otherwise} \end{cases}$$

and $\tau = 0$ if the solution is a certificate of primal infeasibility and $\tau = 1$ otherwise. The formula for computing the violation is only shown for the linear case but is generalized appropriately for the more general problems. Both when the solution is a certificate of primal infeasibility or when it is a dual feasible solution the violation should be small.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `num` (*MSKint32t*) – Length of `sub` and `viol`. (input)
- `sub` (*MSKint32t**) – An array of indexes of x variables. (input)
- `viol` (*MSKrealt**) – `viol[k]` is the violation of dual solution associated with the variable `sub[k]`. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getenv

```
MSKrescodee (MSKAPI MSK_getenv) (  
    MSKtask_t task,  
    MSKenv_t * env)
```

Obtains the environment used to create the task.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `env` (*MSKenv_t by reference*) – The MOSEK environment. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management*

MSK_getinfeasiblesubproblem

```
MSKrescodee (MSKAPI MSK_getinfeasiblesubproblem) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKtask_t * inftask)
```

Given the solution is a certificate of primal or dual infeasibility then a primal or dual infeasible subproblem is obtained respectively. The subproblem tends to be much smaller than the original problem and hence it is easier to locate the infeasibility inspecting the subproblem than the original problem.

For the procedure to be useful it is important to assign meaningful names to constraints, variables etc. in the original task because those names will be duplicated in the subproblem.

The function is only applicable to linear and conic quadratic optimization problems.

For more information see [Sec. 8.3](#) and [Sec. 14.2](#).

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Which solution to use when determining the infeasible subproblem. (input)
- `inftask` (*MSKtask_t by reference*) – A new task containing the infeasible subproblem. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Infeasibility diagnostic*

MSK_getinfindex

```
MSKrescodee (MSKAPI MSK_getinfindex) (  
    MSKtask_t task,  
    MSKinftypee inftype,  
    const char * infname,  
    MSKint32t * infindex)
```

Obtains the index of a named information item.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **inftype** (*MSKinftypee*) – Type of the information item. (input)
- **iname** (*MSKstring_t*) – Name of the information item. (input)
- **inindex** (*MSKint32t by reference*) – The item index. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Information items and statistics*

MSK_getinfmax

```
MSKrescodee (MSKAPI MSK_getinfmax) (  
    MSKtask_t task,  
    MSKinftypee inftype,  
    MSKint32t * inmax)
```

Obtains the maximum index of an information item of a given type **inftype** plus 1.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **inftype** (*MSKinftypee*) – Type of the information item. (input)
- **inmax** (*MSKint32t**) – The maximum index (plus 1) requested. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Information items and statistics*

MSK_getinfname

```
MSKrescodee (MSKAPI MSK_getinfname) (  
    MSKtask_t task,  
    MSKinftypee inftype,  
    MSKint32t whichinf,  
    char * inname)
```

Obtains the name of an information item.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **inftype** (*MSKinftypee*) – Type of the information item. (input)
- **whichinf** (*MSKint32t*) – An information item. (input)
- **iname** (*MSKstring_t*) – Name of the information item. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Information items and statistics, Names*

MSK_getintinf

```
MSKrescodee (MSKAPI MSK_getintinf) (  
    MSKtask_t task,  
    MSKiinfiteme whichiinf,  
    MSKint32t * ivalue)
```

Obtains an integer information item from the task information database.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichiinf** (*MSKiinfiteme*) – Specifies an integer information item. (input)

- `ivalue` (*MSKint32t by reference*) – The value of the required integer information item. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Information items and statistics*

MSK_getintparam

```
MSKrescodee (MSKAPI MSK_getintparam) (
    MSKtask_t task,
    MSKiparame param,
    MSKint32t * parvalue)
```

Obtains the value of an integer parameter.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `param` (*MSKiparame*) – Which parameter. (input)
- `parvalue` (*MSKint32t by reference*) – Parameter value. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_getlasterror

```
MSKrescodee (MSKAPI MSK_getlasterror) (
    MSKtask_t task,
    MSKrescodee * lastrescode,
    MSKint32t sizelastmsg,
    MSKint32t * lastmsglen,
    char * lastmsg)
```

Obtains the last response code and corresponding message reported in **MOSEK**.

If there is no previous error, warning or termination code for this task, `lastrescode` returns *MSK_RES_OK* and `lastmsg` returns an empty string, otherwise the last response code different from *MSK_RES_OK* and the corresponding message are returned.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `lastrescode` (*MSKrescodee by reference*) – Returns the last error code reported in the task. (output)
- `sizelastmsg` (*MSKint32t*) – The length of the `lastmsg` buffer. (input)
- `lastmsglen` (*MSKint32t by reference*) – Returns the length of the last error message reported in the task. (output)
- `lastmsg` (*MSKstring_t*) – Returns the last error message reported in the task. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Responses, errors and warnings*

MSK_getlasterror64

```
MSKrescodee (MSKAPI MSK_getlasterror64) (
    MSKtask_t task,
    MSKrescodee * lastrescode,
    MSKint64t sizelastmsg,
    MSKint64t * lastmsglen,
    char * lastmsg)
```


Obtains the last response code and corresponding message reported in **MOSEK**.

If there is no previous error, warning or termination code for this task, `lastrescode` returns `MSK_RES_OK` and `lastmsg` returns an empty string, otherwise the last response code different from `MSK_RES_OK` and the corresponding message are returned.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `lastrescode` (*MSKrescodee by reference*) – Returns the last error code reported in the task. (output)
- `sizelastmsg` (*MSKint64t*) – The length of the `lastmsg` buffer. (input)
- `lastmsglen` (*MSKint64t by reference*) – Returns the length of the last error message reported in the task. (output)
- `lastmsg` (*MSKstring_t*) – Returns the last error message reported in the task. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Responses, errors and warnings*

`MSK_getlenbarvarj`

```
MSKrescodee (MSKAPI MSK_getlenbarvarj) (
    MSKtask_t task,
    MSKint32t j,
    MSKint64t * lenbarvarj)
```

Obtains the length of the j -th semidefinite variable i.e. the number of elements in the lower triangular part.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `j` (*MSKint32t*) – Index of the semidefinite variable whose length if requested. (input)
- `lenbarvarj` (*MSKint64t by reference*) – Number of scalar elements in the lower triangular part of the semidefinite variable. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - semidefinite*

`MSK_getlintinf`

```
MSKrescodee (MSKAPI MSK_getlintinf) (
    MSKtask_t task,
    MSKliinfiteme whichliinf,
    MSKint64t * ivalue)
```

Obtains a long integer information item from the task information database.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichliinf` (*MSKliinfiteme*) – Specifies a long information item. (input)
- `ivalue` (*MSKint64t by reference*) – The value of the required long integer information item. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Information items and statistics*

`MSK_getmaxnamelen`

```
MSKrescodee (MSKAPI MSK_getmaxnamelen) (
    MSKtask_t task,
    MSKint32t * maxlen)
```

Obtains the maximum length (not including terminating zero character) of any objective, constraint, variable or cone name.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxlen** (*MSKint32t by reference*) – The maximum length of any name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Names*

MSK_getmaxnumanz

```
MSKrescodee (MSKAPI MSK_getmaxnumanz) (
    MSKtask_t task,
    MSKint32t * maxnumanz)
```

Obtains number of preallocated non-zeros in A . When this number of non-zeros is reached **MOSEK** will automatically allocate more space for A .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumanz** (*MSKint32t by reference*) – Number of preallocated non-zero linear matrix elements. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - linear part*

MSK_getmaxnumanz64

```
MSKrescodee (MSKAPI MSK_getmaxnumanz64) (
    MSKtask_t task,
    MSKint64t * maxnumanz)
```

Obtains number of preallocated non-zeros in A . When this number of non-zeros is reached **MOSEK** will automatically allocate more space for A .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumanz** (*MSKint64t by reference*) – Number of preallocated non-zero linear matrix elements. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - linear part*

MSK_getmaxnumberbarvar

```
MSKrescodee (MSKAPI MSK_getmaxnumberbarvar) (
    MSKtask_t task,
    MSKint32t * maxnumberbarvar)
```

Obtains maximum number of symmetric matrix variables for which space is currently preallocated.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumberbarvar** (*MSKint32t by reference*) – Maximum number of symmetric matrix variables for which space is currently preallocated. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - semidefinite*

MSK_getmaxnumcon

```
MSKrescodee (MSKAPI MSK_getmaxnumcon) (  
    MSKtask_t task,  
    MSKint32t * maxnumcon)
```

Obtains the number of preallocated constraints in the optimization task. When this number of constraints is reached **MOSEK** will automatically allocate more space for constraints.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumcon** (*MSKint32t by reference*) – Number of preallocated constraints in the optimization task. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - linear part, Problem data - constraints*

MSK_getmaxnumcone

```
MSKrescodee (MSKAPI MSK_getmaxnumcone) (  
    MSKtask_t task,  
    MSKint32t * maxnumcone)
```

Obtains the number of preallocated cones in the optimization task. When this number of cones is reached **MOSEK** will automatically allocate space for more cones.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumcone** (*MSKint32t by reference*) – Number of preallocated conic constraints in the optimization task. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - cones*

MSK_getmaxnumqnz

```
MSKrescodee (MSKAPI MSK_getmaxnumqnz) (  
    MSKtask_t task,  
    MSKint32t * maxnumqnz)
```

Obtains the number of preallocated non-zeros for Q (both objective and constraints). When this number of non-zeros is reached **MOSEK** will automatically allocate more space for Q .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumqnz** (*MSKint32t by reference*) – Number of non-zero elements preallocated in quadratic coefficient matrices. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - quadratic part*

MSK_getmaxnumqnz64

```
MSKrescodee (MSKAPI MSK_getmaxnumqnz64) (  
    MSKtask_t task,  
    MSKint64t * maxnumqnz)
```

Obtains the number of preallocated non-zeros for Q (both objective and constraints). When this number of non-zeros is reached **MOSEK** will automatically allocate more space for Q .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumqnz** (*MSKint64t by reference*) – Number of non-zero elements preallocated in quadratic coefficient matrices. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - quadratic part*

MSK_getmaxnumvar

```
MSKrescodee (MSKAPI MSK_getmaxnumvar) (
    MSKtask_t task,
    MSKint32t * maxnumvar)
```

Obtains the number of preallocated variables in the optimization task. When this number of variables is reached **MOSEK** will automatically allocate more space for variables.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumvar** (*MSKint32t by reference*) – Number of preallocated variables in the optimization task. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - linear part, Problem data - variables*

MSK_getmemusagetask

```
MSKrescodee (MSKAPI MSK_getmemusagetask) (
    MSKtask_t task,
    MSKint64t * meminuse,
    MSKint64t * maxmemuse)
```

Obtains information about the amount of memory used by a task.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **meminuse** (*MSKint64t by reference*) – Amount of memory currently used by the task. (output)
- **maxmemuse** (*MSKint64t by reference*) – Maximum amount of memory used by the task until now. (output)

Return (*MSKrescodee*) – The function response code.

Groups *System, memory and debugging*

MSK_getnadouinf

```
MSKrescodee (MSKAPI MSK_getnadouinf) (
    MSKtask_t task,
    const char * infitemname,
    MSKrealt * dvalue)
```

Obtains a named double information item from task information database.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **infitemname** (*MSKstring_t*) – The name of a double information item. (input)
- **dvalue** (*MSKrealt by reference*) – The value of the required double information item. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Information items and statistics*

MSK_getnadouparam

```
MSKrescodee (MSKAPI MSK_getnadouparam) (  
    MSKtask_t task,  
    const char * paramname,  
    MSKrealt * parvalue)
```

Obtains the value of a named double parameter.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- paramname (*MSKstring_t*) – Name of a parameter. (input)
- parvalue (*MSKrealt by reference*) – Parameter value. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_getnaintinf

```
MSKrescodee (MSKAPI MSK_getnaintinf) (  
    MSKtask_t task,  
    const char * infitemname,  
    MSKint32t * ivalue)
```

Obtains a named integer information item from the task information database.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- infitemname (*MSKstring_t*) – The name of an integer information item. (input)
- ivalue (*MSKint32t by reference*) – The value of the required integer information item. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Information items and statistics*

MSK_getnaintparam

```
MSKrescodee (MSKAPI MSK_getnaintparam) (  
    MSKtask_t task,  
    const char * paramname,  
    MSKint32t * parvalue)
```

Obtains the value of a named integer parameter.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- paramname (*MSKstring_t*) – Name of a parameter. (input)
- parvalue (*MSKint32t by reference*) – Parameter value. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_getnastrparam

```
MSKrescodee (MSKAPI MSK_getnastrparam) (
    MSKtask_t task,
    const char * paramname,
    MSKint32t sizeparamname,
    MSKint32t * len,
    char * parvalue)
```

Obtains the value of a named string parameter.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- paramname (*MSKstring_t*) – Name of a parameter. (input)
- sizeparamname (*MSKint32t*) – Size of the name buffer parvalue. (input)
- len (*MSKint32t by reference*) – Length of the string in parvalue. (output)
- parvalue (*MSKstring_t*) – Parameter value. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters, Names*

MSK_getnastrparamal

```
MSKrescodee (MSKAPI MSK_getnastrparamal) (
    MSKtask_t task,
    const char * paramname,
    MSKint32t numaddchr,
    MSKstring_t * value)
```

Obtains the value of a named string parameter.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- paramname (*MSKstring_t*) – Name of a parameter. (input)
- numaddchr (*MSKint32t*) – Number of additional characters for which room is left in value. (input)
- value (*MSKstring_t**) – Parameter value. **MOSEK** will allocate this char buffer of size equal to the actual length of the string parameter plus numaddchr. This memory must be freed by *MSK_freetask*. (input/output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_getnumanz

```
MSKrescodee (MSKAPI MSK_getnumanz) (
    MSKtask_t task,
    MSKint32t * numanz)
```

Obtains the number of non-zeros in A .

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- numanz (*MSKint32t by reference*) – Number of non-zero elements in the linear constraint matrix. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - linear part*

MSK_getnumanz64

```
MSKrescodee (MSKAPI MSK_getnumanz64) (
    MSKtask_t task,
    MSKint64t * numanz)
```

Obtains the number of non-zeros in A .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **numanz** (*MSKint64t by reference*) – Number of non-zero elements in the linear constraint matrix. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - linear part*

MSK_getnumbarablocktriplets

```
MSKrescodee (MSKAPI MSK_getnumbarablocktriplets) (
    MSKtask_t task,
    MSKint64t * num)
```

Obtains an upper bound on the number of elements in the block triplet form of \bar{A} .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint64t by reference*) – An upper bound on the number of elements in the block triplet form of \bar{A} . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getnumbaranz

```
MSKrescodee (MSKAPI MSK_getnumbaranz) (
    MSKtask_t task,
    MSKint64t * nz)
```

Get the number of nonzero elements in \bar{A} .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **nz** (*MSKint64t by reference*) – The number of nonzero block elements in \bar{A} i.e. the number of \bar{A}_{ij} elements that are nonzero. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getnumbarcbblocktriplets

```
MSKrescodee (MSKAPI MSK_getnumbarcbblocktriplets) (
    MSKtask_t task,
    MSKint64t * num)
```

Obtains an upper bound on the number of elements in the block triplet form of \bar{C} .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint64t by reference*) – An upper bound on the number of elements in the block triplet form of \bar{C} . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getnumbarcnz

```
MSKrescodee (MSKAPI MSK_getnumbarcnz) (  
    MSKtask_t task,  
    MSKint64t * nz)
```

Obtains the number of nonzero elements in \overline{C} .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **nz** (*MSKint64t by reference*) – The number of nonzeros in \overline{C} i.e. the number of elements \overline{C}_j that are nonzero. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getnumbarvar

```
MSKrescodee (MSKAPI MSK_getnumbarvar) (  
    MSKtask_t task,  
    MSKint32t * numbarvar)
```

Obtains the number of semidefinite variables.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **numbarvar** (*MSKint32t by reference*) – Number of semidefinite variables in the problem. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - semidefinite*

MSK_getnumcon

```
MSKrescodee (MSKAPI MSK_getnumcon) (  
    MSKtask_t task,  
    MSKint32t * numcon)
```

Obtains the number of constraints.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **numcon** (*MSKint32t by reference*) – Number of constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - constraints, Inspecting the task*

MSK_getnumcone

```
MSKrescodee (MSKAPI MSK_getnumcone) (  
    MSKtask_t task,  
    MSKint32t * numcone)
```

Obtains the number of cones.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **numcone** (*MSKint32t by reference*) – Number of conic constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - cones, Inspecting the task*

MSK_getnumconmem

```
MSKrescodee (MSKAPI MSK_getnumconmem) (  
    MSKtask_t task,  
    MSKint32t k,  
    MSKint32t * nummem)
```

Obtains the number of members in a cone.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **k** (*MSKint32t*) – Index of the cone. (input)
- **nummem** (*MSKint32t by reference*) – Number of member variables in the cone. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - cones, Inspecting the task*

MSK_getnumintvar

```
MSKrescodee (MSKAPI MSK_getnumintvar) (  
    MSKtask_t task,  
    MSKint32t * numintvar)
```

Obtains the number of integer-constrained variables.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **numintvar** (*MSKint32t by reference*) – Number of integer variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - variables*

MSK_getnumparam

```
MSKrescodee (MSKAPI MSK_getnumparam) (  
    MSKtask_t task,  
    MSKparametertypee partype,  
    MSKint32t * numparam)
```

Obtains the number of parameters of a given type.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **partype** (*MSKparametertypee*) – Parameter type. (input)
- **numparam** (*MSKint32t by reference*) – The number of parameters of type partype. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Parameters*

MSK_getnumqconknz

```
MSKrescodee (MSKAPI MSK_getnumqconknz) (  
    MSKtask_t task,  
    MSKint32t k,  
    MSKint32t * numqcnz)
```

Obtains the number of non-zero quadratic terms in a constraint.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **k** (*MSKint32t*) – Index of the constraint for which the number of non-zero quadratic terms should be obtained. (input)
- **numqcnz** (*MSKint32t by reference*) – Number of quadratic terms. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - constraints, Problem data - quadratic part*

MSK_getnumqconknz64

```
MSKrescodee (MSKAPI MSK_getnumqconknz64) (  
    MSKtask_t task,  
    MSKint32t k,  
    MSKint64t * numqcnz)
```

Obtains the number of non-zero quadratic terms in a constraint.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **k** (*MSKint32t*) – Index of the constraint for which the number quadratic terms should be obtained. (input)
- **numqcnz** (*MSKint64t by reference*) – Number of quadratic terms. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - constraints, Problem data - quadratic part*

MSK_getnumqobjnz

```
MSKrescodee (MSKAPI MSK_getnumqobjnz) (  
    MSKtask_t task,  
    MSKint32t * numqonz)
```

Obtains the number of non-zero quadratic terms in the objective.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **numqonz** (*MSKint32t by reference*) – Number of non-zero elements in the quadratic objective terms. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - quadratic part*

MSK_getnumqobjnz64

```
MSKrescodee (MSKAPI MSK_getnumqobjnz64) (  
    MSKtask_t task,  
    MSKint64t * numqonz)
```

Obtains the number of non-zero quadratic terms in the objective.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **numqonz** (*MSKint64t by reference*) – Number of non-zero elements in the quadratic objective terms. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - quadratic part*

MSK_getnumsymmat

```
MSKrescodee (MSKAPI MSK_getnumsymmat) (
    MSKtask_t task,
    MSKint64t * num)
```

Obtains the number of symmetric matrices stored in the vector E .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint64t by reference*) – The number of symmetric sparse matrices. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getnumvar

```
MSKrescodee (MSKAPI MSK_getnumvar) (
    MSKtask_t task,
    MSKint32t * numvar)
```

Obtains the number of variables.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **numvar** (*MSKint32t by reference*) – Number of variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - variables*

MSK_getobjname

```
MSKrescodee (MSKAPI MSK_getobjname) (
    MSKtask_t task,
    MSKint32t sizeobjname,
    char * objname)
```

Obtains the name assigned to the objective function.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **sizeobjname** (*MSKint32t*) – Length of **objname**. (input)
- **objname** (*MSKstring_t*) – Assigned the objective name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Names*

MSK_getobjnamelen

```
MSKrescodee (MSKAPI MSK_getobjnamelen) (
    MSKtask_t task,
    MSKint32t * len)
```

Obtains the length of the name assigned to the objective function.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **len** (*MSKint32t by reference*) – Assigned the length of the objective name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Names*

MSK_getobjsense

```
MSKrescodee (MSKAPI MSK_getobjsense) (  
    MSKtask_t task,  
    MSKobjsensee * sense)
```

Gets the objective sense of the task.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **sense** (*MSKobjsensee by reference*) – The returned objective sense. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_getparammax

```
MSKrescodee (MSKAPI MSK_getparammax) (  
    MSKtask_t task,  
    MSKparametertypee partype,  
    MSKint32t * parammax)
```

Obtains the maximum index of a parameter of type **partype** plus 1.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **partype** (*MSKparametertypee*) – Parameter type. (input)
- **parammax** (*MSKint32t by reference*) – The maximum index (plus 1) of the given parameter type. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_getparamname

```
MSKrescodee (MSKAPI MSK_getparamname) (  
    MSKtask_t task,  
    MSKparametertypee partype,  
    MSKint32t param,  
    char * parname)
```

Obtains the name for a parameter **param** of type **partype**.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **partype** (*MSKparametertypee*) – Parameter type. (input)
- **param** (*MSKint32t*) – Which parameter. (input)
- **parname** (*MSKstring_t*) – Parameter name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Parameters*

MSK_getprimalobj

```
MSKrescodee (MSKAPI MSK_getprimalobj) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKrealt * primalobj)
```

Computes the primal objective value for the desired solution. Note that if the solution is an infeasibility certificate, then the fixed term in the objective is not included.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `primalobj` (*MSKrealt by reference*) – Objective value corresponding to the primal solution. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information, Solution - primal*

MSK_getprimalsolutionnorms

```
MSKrescodee (MSKAPI MSK_getprimalsolutionnorms) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * nrmxc,
    MSKrealt * nrmxx,
    MSKrealt * nrmbarx)
```

Compute norms of the primal solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `nrmxc` (*MSKrealt by reference*) – The norm of the x^c vector. (output)
- `nrmxx` (*MSKrealt by reference*) – The norm of the x vector. (output)
- `nrmbarx` (*MSKrealt by reference*) – The norm of the \bar{X} vector. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getprodtype

```
MSKrescodee (MSKAPI MSK_getprodtype) (
    MSKtask_t task,
    MSKproblemtyp * probtype)
```

Obtains the problem type.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `probtype` (*MSKproblemtyp by reference*) – The problem type. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task*

MSK_getprosta

```
MSKrescodee (MSKAPI MSK_getprosta) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKprosta * prosta)
```

Obtains the problem status.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)

- **prosta** (*MSKprosta* by reference) – Problem status. (output)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Solution information*

MSK_getpviolbarvar

```
MSKrescodee (MSKAPI MSK_getpviolbarvar) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t num,
    const MSKint32t * sub,
    MSKrealt * viol)
```

Computes the primal solution violation for a set of semidefinite variables. Let $(\bar{X}_j)^*$ be the value of the variable \bar{X}_j for the specified solution. Then the primal violation of the solution associated with variable \bar{X}_j is given by

$$\max(-\lambda_{\min}(\bar{X}_j), 0.0).$$

Both when the solution is a certificate of dual infeasibility or when it is primal feasible the violation should be small.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **num** (*MSKint32t*) – Length of **sub** and **viol**. (input)
- **sub** (*MSKint32t**) – An array of indexes of \bar{X} variables. (input)
- **viol** (*MSKrealt**) – **viol[k]** is how much the solution violates the constraint $\bar{X}_{\text{sub}[k]} \in \mathcal{S}_+$. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getpviolcon

```
MSKrescodee (MSKAPI MSK_getpviolcon) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t num,
    const MSKint32t * sub,
    MSKrealt * viol)
```

Computes the primal solution violation for a set of constraints. The primal violation of the solution associated with the i -th constraint is given by

$$\max(\tau l_i^c - (x_i^c)^*, (x_i^c)^* - \tau u_i^c), \mid \sum_{j=0}^{\text{numvar}-1} a_{ij} x_j^* - x_i^c)$$

where $\tau = 0$ if the solution is a certificate of dual infeasibility and $\tau = 1$ otherwise. Both when the solution is a certificate of dual infeasibility and when it is primal feasible the violation should be small. The above formula applies for the linear case but is appropriately generalized in other cases.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **num** (*MSKint32t*) – Length of **sub** and **viol**. (input)
- **sub** (*MSKint32t**) – An array of indexes of constraints. (input)

- `viol (MSKrealt*)` – `viol[k]` is the violation associated with the solution for the constraint `sub[k]`. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getpviolcones

```
MSKrescodee (MSKAPI MSK_getpviolcones) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t num,
    const MSKint32t * sub,
    MSKrealt * viol)
```

Computes the primal solution violation for a set of conic constraints. Let x^* be the value of the variable x for the specified solution. For simplicity let us assume that x is a member of a quadratic cone, then the violation is computed as follows

$$\begin{cases} \max(0, \|x_{2:n}\| - x_1)/\sqrt{2}, & x_1 \geq -\|x_{2:n}\|, \\ \|x\|, & \text{otherwise.} \end{cases}$$

Both when the solution is a certificate of dual infeasibility or when it is primal feasible the violation should be small.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `whichsol (MSKsoltypee)` – Selects a solution. (input)
- `num (MSKint32t)` – Length of `sub` and `viol`. (input)
- `sub (MSKint32t*)` – An array of indexes of conic constraints. (input)
- `viol (MSKrealt*)` – `viol[k]` is the violation of the solution associated with the conic constraint number `sub[k]`. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getpviolvar

```
MSKrescodee (MSKAPI MSK_getpviolvar) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t num,
    const MSKint32t * sub,
    MSKrealt * viol)
```

Computes the primal solution violation associated to a set of variables. Let x_j^* be the value of x_j for the specified solution. Then the primal violation of the solution associated with variable x_j is given by

$$\max(\tau l_j^x - x_j^*, x_j^* - \tau u_j^x, 0).$$

where $\tau = 0$ if the solution is a certificate of dual infeasibility and $\tau = 1$ otherwise. Both when the solution is a certificate of dual infeasibility and when it is primal feasible the violation should be small.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `whichsol (MSKsoltypee)` – Selects a solution. (input)
- `num (MSKint32t)` – Length of `sub` and `viol`. (input)
- `sub (MSKint32t*)` – An array of indexes of x variables. (input)

- `viol (MSKrealt*)` – `viol[k]` is the violation associated with the solution for the variable $x_{\text{sub}[k]}$. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getqconk

```
MSKrescodee (MSKAPI MSK_getqconk) (
    MSKtask_t task,
    MSKint32t k,
    MSKint32t maxnumqcnz,
    MSKint32t * qcsurp,
    MSKint32t * numqcnz,
    MSKint32t * qcsubi,
    MSKint32t * qcsubj,
    MSKrealt * qcval)
```

Obtains all the quadratic terms in a constraint. The quadratic terms are stored sequentially in `qcsubi`, `qcsubj`, and `qcval`.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `k (MSKint32t)` – Which constraint. (input)
- `maxnumqcnz (MSKint32t)` – Length of the arrays `qcsubi`, `qcsubj`, and `qcval`. (input)
- `qcsurp (MSKint32t by reference)` – Surplus of subscript and coefficient arrays. The required entries are stored sequentially in `qcsubi`, `qcsubj` and `qcval` starting from position `qcsurp` away from the end of the arrays. On return `qcsurp` will be decremented by the total number of non-zeros written. (input/output)
- `numqcnz (MSKint32t by reference)` – Number of quadratic terms. (output)
- `qcsubi (MSKint32t*)` – Row subscripts for quadratic constraint matrix. (output)
- `qcsubj (MSKint32t*)` – Column subscripts for quadratic constraint matrix. (output)
- `qcval (MSKrealt*)` – Quadratic constraint coefficient values. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - quadratic part, Problem data - constraints*

MSK_getqconk64

```
MSKrescodee (MSKAPI MSK_getqconk64) (
    MSKtask_t task,
    MSKint32t k,
    MSKint64t maxnumqcnz,
    MSKint64t * qcsurp,
    MSKint64t * numqcnz,
    MSKint32t * qcsubi,
    MSKint32t * qcsubj,
    MSKrealt * qcval)
```

Obtains all the quadratic terms in a constraint. The quadratic terms are stored sequentially in `qcsubi`, `qcsubj`, and `qcval`.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `k (MSKint32t)` – Which constraint. (input)
- `maxnumqcnz (MSKint64t)` – Length of the arrays `qcsubi`, `qcsubj`, and `qcval`. (input)

- `qcsurp` (*MSKint64t by reference*) – Surplus of subscript and coefficient arrays. The required entries are stored sequentially in `qcsubi`, `qcsubj` and `qcval` starting from position `qcsurp` away from the end of the arrays. On return `qcsurp` will be decremented by the total number of non-zeros written. (input/output)
- `numqcnz` (*MSKint64t by reference*) – Number of quadratic terms. (output)
- `qcsubi` (*MSKint32t**) – Row subscripts for quadratic constraint matrix. (output)
- `qcsubj` (*MSKint32t**) – Column subscripts for quadratic constraint matrix. (output)
- `qcval` (*MSKrealt**) – Quadratic constraint coefficient values. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - quadratic part, Problem data - constraints*

MSK_getqobj

```
MSKrescodee (MSKAPI MSK_getqobj) (
    MSKtask_t task,
    MSKint32t maxnumqonz,
    MSKint32t * qosurp,
    MSKint32t * numqonz,
    MSKint32t * qosubi,
    MSKint32t * qosubj,
    MSKrealt * qoval)
```

Obtains the quadratic terms in the objective. The required quadratic terms are stored sequentially in `qosubi`, `qosubj`, and `qoval`.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `maxnumqonz` (*MSKint32t*) – The length of the arrays `qosubi`, `qosubj`, and `qoval`. (input)
- `qosurp` (*MSKint32t by reference*) – Surplus of subscript and coefficient arrays. The required entries are stored sequentially in `qosubi`, `qosubj` and `qoval` starting from position `qosurp` away from the end of the arrays. On return `qosurp` will be decremented by the total number of non-zeros written. (input/output)
- `numqonz` (*MSKint32t by reference*) – Number of non-zero elements in the quadratic objective terms. (output)
- `qosubi` (*MSKint32t**) – Row subscripts for quadratic objective coefficients. (output)
- `qosubj` (*MSKint32t**) – Column subscripts for quadratic objective coefficients. (output)
- `qoval` (*MSKrealt**) – Quadratic objective coefficient values. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - quadratic part*

MSK_getqobj64

```
MSKrescodee (MSKAPI MSK_getqobj64) (
    MSKtask_t task,
    MSKint64t maxnumqonz,
    MSKint64t * qosurp,
    MSKint64t * numqonz,
    MSKint32t * qosubi,
    MSKint32t * qosubj,
    MSKrealt * qoval)
```

Obtains the quadratic terms in the objective. The required quadratic terms are stored sequentially in `qosubi`, `qosubj`, and `qoval`.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumqonz** (*MSKint64t*) – The length of the arrays **qosubi**, **qosubj**, and **qoval**. (input)
- **qosurp** (*MSKint64t by reference*) – Surplus of subscript and coefficient arrays. The required entries are stored sequentially in **qosubi**, **qosubj** and **qoval** starting from position **qosurp** away from the end of the arrays. On return **qosurp** will be decremented by the total number of non-zeros written. (input/output)
- **numqonz** (*MSKint64t by reference*) – Number of non-zero elements in the quadratic objective terms. (output)
- **qosubi** (*MSKint32t**) – Row subscripts for quadratic objective coefficients. (output)
- **qosubj** (*MSKint32t**) – Column subscripts for quadratic objective coefficients. (output)
- **qoval** (*MSKrealt**) – Quadratic objective coefficient values. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - quadratic part*

MSK_getqobjij

```
MSKrescodee (MSKAPI MSK_getqobjij) (
    MSKtask_t task,
    MSKint32t i,
    MSKint32t j,
    MSKrealt * qoij)
```

Obtains one coefficient q_{ij}^o in the quadratic term of the objective.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Row index of the coefficient. (input)
- **j** (*MSKint32t*) – Column index of coefficient. (input)
- **qoij** (*MSKrealt by reference*) – The required coefficient. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - quadratic part*

MSK_getreducedcosts

```
MSKrescodee (MSKAPI MSK_getreducedcosts) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    MSKrealt * redcosts)
```

Computes the reduced costs for a slice of variables and returns them in the array **redcosts** i.e.

$$\text{redcosts}[j - \text{first}] = (s_l^x)_j - (s_u^x)_j, \quad j = \text{first}, \dots, \text{last} - 1 \quad (15.2)$$

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – The index of the first variable in the sequence. (input)
- **last** (*MSKint32t*) – The index of the last variable in the sequence plus 1. (input)
- **redcosts** (*MSKrealt**) – The reduced costs for the required slice of variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getresponseclass

```
MSKrescodee (MSKAPI MSK_getresponseclass) (  
    MSKrescodee r,  
    MSKrescodetypee * rc)
```

Obtain the class of a response code.

Parameters

- **r** (*MSKrescodee*) – A response code indicating the result of function call. (input)
- **rc** (*MSKrescodetypee by reference*) – The response class. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Responses, errors and warnings*

MSK_getskc

```
MSKrescodee (MSKAPI MSK_getskc) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKstakeye * skc)
```

Obtains the status keys for the constraints.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **skc** (*MSKstakeye**) – Status keys for the constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getskcslice

```
MSKrescodee (MSKAPI MSK_getskcslice) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKint32t first,  
    MSKint32t last,  
    MSKstakeye * skc)
```

Obtains the status keys for a slice of the constraints.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **skc** (*MSKstakeye**) – Status keys for the constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getskn

```
MSKrescodee (MSKAPI MSK_getskn) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKstakeye * skn)
```

Obtains the status keys for the conic constraints.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **skn** (*MSKstakeye**) – Status keys for the conic constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getskx

```
MSKrescodee (MSKAPI MSK_getskx) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKstakeye * skx)
```

Obtains the status keys for the scalar variables.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **skx** (*MSKstakeye**) – Status keys for the variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getskxslice

```
MSKrescodee (MSKAPI MSK_getskxslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    MSKstakeye * skx)
```

Obtains the status keys for a slice of the scalar variables.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **skx** (*MSKstakeye**) – Status keys for the variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getslc

```
MSKrescodee (MSKAPI MSK_getslc) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * slc)
```

Obtains the s_l^c vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **slc** (*MSKrealt**) – Dual variables corresponding to the lower bounds on the constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getslcslice

```
MSKrescodee (MSKAPI MSK_getslcslice) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKint32t first,  
    MSKint32t last,  
    MSKrealt * slc)
```

Obtains a slice of the s_l^c vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **slc** (*MSKrealt**) – Dual variables corresponding to the lower bounds on the constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getslx

```
MSKrescodee (MSKAPI MSK_getslx) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKrealt * slx)
```

Obtains the s_l^x vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **slx** (*MSKrealt**) – Dual variables corresponding to the lower bounds on the variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getslxslice

```
MSKrescodee (MSKAPI MSK_getslxslice) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKint32t first,  
    MSKint32t last,  
    MSKrealt * slx)
```

Obtains a slice of the s_l^x vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **slx** (*MSKrealt**) – Dual variables corresponding to the lower bounds on the variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getsnx

```
MSKrescodee (MSKAPI MSK_getsnx) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKrealt * snx)
```

Obtains the s_n^x vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **snx** (*MSKrealt**) – Dual variables corresponding to the conic constraints on the variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getsnxslice

```
MSKrescodee (MSKAPI MSK_getsnxslice) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKint32t first,  
    MSKint32t last,  
    MSKrealt * snx)
```

Obtains a slice of the s_n^x vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **snx** (*MSKrealt**) – Dual variables corresponding to the conic constraints on the variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getsolsta

```
MSKrescodee (MSKAPI MSK_getsolsta) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKsolstae * solsta)
```

Obtains the solution status.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **solsta** (*MSKsolstae by reference*) – Solution status. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getsolution

```
MSKrescodee (MSKAPI MSK_getsolution) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKprosta * prosta,
    MSKsolstae * solsta,
    MSKstakeye * skc,
    MSKstakeye * skx,
    MSKstakeye * skn,
    MSKrealt * xc,
    MSKrealt * xx,
    MSKrealt * y,
    MSKrealt * slc,
    MSKrealt * suc,
    MSKrealt * slx,
    MSKrealt * sux,
    MSKrealt * snx)
```

Obtains the complete solution.

Consider the case of linear programming. The primal problem is given by

$$\begin{aligned} & \text{minimize} && c^T x + c^f \\ & \text{subject to} && \begin{array}{ccc} l^c & \leq & Ax & \leq & u^c, \\ l^x & \leq & x & \leq & u^x. \end{array} \end{aligned}$$

and the corresponding dual problem is

$$\begin{aligned} & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c \\ & && + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ & \text{subject to} && \begin{array}{ccc} A^T y + s_l^x - s_u^x & = & c, \\ -y + s_l^c - s_u^c & = & 0, \\ s_l^c, s_u^c, s_l^x, s_u^x & \geq & 0. \end{array} \end{aligned}$$

A conic optimization problem has the same primal variables as in the linear case. Recall that the dual of a conic optimization problem is given by:

$$\begin{aligned} & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c \\ & && + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ & \text{subject to} && \begin{array}{ccc} A^T y + s_l^x - s_u^x + s_n^x & = & c, \\ -y + s_l^c - s_u^c & = & 0, \\ s_l^c, s_u^c, s_l^x, s_u^x & \geq & 0, \\ s_n^x & \in & \mathcal{K}^* \end{array} \end{aligned}$$

The mapping between variables and arguments to the function is as follows:

- **xx** : Corresponds to variable x (also denoted x^x).
- **xc** : Corresponds to $x^c := Ax$.
- **y** : Corresponds to variable y .
- **slc**: Corresponds to variable s_l^c .

- **suc**: Corresponds to variable s_u^c .
- **slx**: Corresponds to variable s_l^x .
- **sux**: Corresponds to variable s_u^x .
- **snx**: Corresponds to variable s_n^x .

The meaning of the values returned by this function depend on the *solution status* returned in the argument **solsta**. The most important possible values of **solsta** are:

- **MSK_SOL_STA_OPTIMAL** : An optimal solution satisfying the optimality criteria for continuous problems is returned.
- **MSK_SOL_STA_INTEGER_OPTIMAL** : An optimal solution satisfying the optimality criteria for integer problems is returned.
- **MSK_SOL_STA_PRIM_FEAS** : A solution satisfying the feasibility criteria.
- **MSK_SOL_STA_PRIM_INFEAS_CER** : A primal certificate of infeasibility is returned.
- **MSK_SOL_STA_DUAL_INFEAS_CER** : A dual certificate of infeasibility is returned.

In order to retrieve the primal and dual values of semidefinite variables see **MSK_getbarxj** and **MSK_getbarsj**.

Parameters

- **task** (**MSKtask_t**) – An optimization task. (input)
- **whichsol** (**MSKsoltypee**) – Selects a solution. (input)
- **prosta** (**MSKprosta_e by reference**) – Problem status. (output)
- **solsta** (**MSKsolsta_e by reference**) – Solution status. (output)
- **skc** (**MSKstakeye***) – Status keys for the constraints. (output)
- **skx** (**MSKstakeye***) – Status keys for the variables. (output)
- **skn** (**MSKstakeye***) – Status keys for the conic constraints. (output)
- **xc** (**MSKrealt***) – Primal constraint solution. (output)
- **xx** (**MSKrealt***) – Primal variable solution. (output)
- **y** (**MSKrealt***) – Vector of dual variables corresponding to the constraints. (output)
- **slc** (**MSKrealt***) – Dual variables corresponding to the lower bounds on the constraints. (output)
- **suc** (**MSKrealt***) – Dual variables corresponding to the upper bounds on the constraints. (output)
- **slx** (**MSKrealt***) – Dual variables corresponding to the lower bounds on the variables. (output)
- **sux** (**MSKrealt***) – Dual variables corresponding to the upper bounds on the variables. (output)
- **snx** (**MSKrealt***) – Dual variables corresponding to the conic constraints on the variables. (output)

Return (**MSKrescodee**) – The function response code.

Groups *Solution information, Solution - primal, Solution - dual*

MSK_getsolutioninfo

```
MSKrescodee (MSKAPI MSK_getsolutioninfo) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * pobj,
    MSKrealt * pviolcon,
    MSKrealt * pviolvar,
    MSKrealt * pviolbarvar,
    MSKrealt * pviolcone,
```

(continues on next page)


```

MSKrealt * pviolitg,
MSKrealt * dobj,
MSKrealt * dviolcon,
MSKrealt * dviolvar,
MSKrealt * dviolbarvar,
MSKrealt * dviolcone)

```

Obtains information about a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **pobj** (*MSKrealt by reference*) – The primal objective value as computed by *MSK_getprimalobj*. (output)
- **pviolcon** (*MSKrealt by reference*) – Maximal primal violation of the solution associated with the x^c variables where the violations are computed by *MSK_getpviolcon*. (output)
- **pviolvar** (*MSKrealt by reference*) – Maximal primal violation of the solution for the x variables where the violations are computed by *MSK_getpviolvar*. (output)
- **pviolbarvar** (*MSKrealt by reference*) – Maximal primal violation of solution for the \bar{X} variables where the violations are computed by *MSK_getpviolbarvar*. (output)
- **pviolcone** (*MSKrealt by reference*) – Maximal primal violation of solution for the conic constraints where the violations are computed by *MSK_getpviolcones*. (output)
- **pviolitg** (*MSKrealt by reference*) – Maximal violation in the integer constraints. The violation for an integer variable x_j is given by $\min(x_j - \lfloor x_j \rfloor, \lceil x_j \rceil - x_j)$. This number is always zero for the interior-point and basic solutions. (output)
- **dobj** (*MSKrealt by reference*) – Dual objective value as computed by *MSK_getdualobj*. (output)
- **dviolcon** (*MSKrealt by reference*) – Maximal violation of the dual solution associated with the x^c variable as computed by *MSK_getdviolcon*. (output)
- **dviolvar** (*MSKrealt by reference*) – Maximal violation of the dual solution associated with the x variable as computed by *MSK_getdviolvar*. (output)
- **dviolbarvar** (*MSKrealt by reference*) – Maximal violation of the dual solution associated with the \bar{S} variable as computed by *MSK_getdviolbarvar*. (output)
- **dviolcone** (*MSKrealt by reference*) – Maximal violation of the dual solution associated with the dual conic constraints as computed by *MSK_getdviolcones*. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_getsolutionslice

```

MSKrescodee (MSKAPI MSK_getsolutionslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKsoliteme solitem,
    MSKint32t first,
    MSKint32t last,
    MSKrealt * values)

```

Obtains a slice of one item from the solution. The format of the solution is exactly as in *MSK_getsolution*. The parameter *solitem* determines which of the solution vectors should be returned.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `solitem` (*MSKsoliteme*) – Which part of the solution is required. (input)
- `first` (*MSKint32t*) – First index in the sequence. (input)
- `last` (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- `values` (*MSKrealt**) – The values in the required sequence are stored sequentially in `values`. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - primal, Solution - dual, Solution information*

MSK_getsparsesymmat

```
MSKrescodee (MSKAPI MSK_getsparsesymmat) (  
    MSKtask_t task,  
    MSKint64t idx,  
    MSKint64t maxlen,  
    MSKint32t * subi,  
    MSKint32t * subj,  
    MSKrealt * valij)
```

Get a single symmetric matrix from the matrix store.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `idx` (*MSKint64t*) – Index of the matrix to retrieve. (input)
- `maxlen` (*MSKint64t*) – Length of the output arrays `subi`, `subj` and `valij`. (input)
- `subi` (*MSKint32t**) – Row subscripts of the matrix non-zero elements. (output)
- `subj` (*MSKint32t**) – Column subscripts of the matrix non-zero elements. (output)
- `valij` (*MSKrealt**) – Coefficients of the matrix non-zero elements. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_getstrparam

```
MSKrescodee (MSKAPI MSK_getstrparam) (  
    MSKtask_t task,  
    MSKsparame param,  
    MSKint32t maxlen,  
    MSKint32t * len,  
    char * parvalue)
```

Obtains the value of a string parameter.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `param` (*MSKsparame*) – Which parameter. (input)
- `maxlen` (*MSKint32t*) – Length of the `parvalue` buffer. (input)
- `len` (*MSKint32t by reference*) – The length of the parameter value. (output)
- `parvalue` (*MSKstring_t*) – Parameter value. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Parameters*

MSK_getstrparamal

```
MSKrescodee (MSKAPI MSK_getstrparamal) (
    MSKtask_t task,
    MSKsparame param,
    MSKint32t numaddchr,
    MSKstring_t * value)
```

Obtains the value of a string parameter.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- param (*MSKsparame*) – Which parameter. (input)
- numaddchr (*MSKint32t*) – Number of additional characters for which room is left in value. (input)
- value (*MSKstring_t by reference*) – Parameter value. **MOSEK** will allocate this char buffer of size equal to the actual length of the string parameter plus numaddchr. This memory must be freed by *MSK_freetask*. (input/output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_getstrparamlen

```
MSKrescodee (MSKAPI MSK_getstrparamlen) (
    MSKtask_t task,
    MSKsparame param,
    MSKint32t * len)
```

Obtains the length of a string parameter.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- param (*MSKsparame*) – Which parameter. (input)
- len (*MSKint32t by reference*) – The length of the parameter value. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Parameters*

MSK_getsuc

```
MSKrescodee (MSKAPI MSK_getsuc) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * suc)
```

Obtains the s_u^c vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- suc (*MSKrealt**) – Dual variables corresponding to the upper bounds on the constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getsucslice

```
MSKrescodee (MSKAPI MSK_getsucslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    MSKrealt * suc)
```

Obtains a slice of the s_u^c vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- first (*MSKint32t*) – First index in the sequence. (input)
- last (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- suc (*MSKrealt**) – Dual variables corresponding to the upper bounds on the constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getsux

```
MSKrescodee (MSKAPI MSK_getsux) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * sux)
```

Obtains the s_u^x vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- sux (*MSKrealt**) – Dual variables corresponding to the upper bounds on the variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getsuxslice

```
MSKrescodee (MSKAPI MSK_getsuxslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    MSKrealt * sux)
```

Obtains a slice of the s_u^x vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- first (*MSKint32t*) – First index in the sequence. (input)
- last (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- sux (*MSKrealt**) – Dual variables corresponding to the upper bounds on the variables. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getsymbcon

```
MSKrescodee (MSKAPI MSK_getsymbcon) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKint32t sizevalue,  
    char * name,  
    MSKint32t * value)
```

Obtains the name and corresponding value for the i th symbolic constant.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index. (input)
- **sizevalue** (*MSKint32t*) – The length of the buffer pointed to by the **value** argument. (input)
- **name** (*MSKstring_t*) – Name of the i th symbolic constant. (output)
- **value** (*MSKint32t by reference*) – The corresponding value. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names*

MSK_getsymbcondim

```
MSKrescodee (MSKAPI MSK_getsymbcondim) (  
    MSKenv_t env,  
    MSKint32t * num,  
    size_t * maxlen)
```

Obtains the number of symbolic constants defined by **MOSEK** and the maximum length of the name of any symbolic constant.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **num** (*MSKint32t by reference*) – Number of symbolic constants defined by **MOSEK**. (output)
- **maxlen** (*size_t by reference*) – Maximum length of the name of any symbolic constants. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_getsymmatinfo

```
MSKrescodee (MSKAPI MSK_getsymmatinfo) (  
    MSKtask_t task,  
    MSKint64t idx,  
    MSKint32t * dim,  
    MSKint64t * nz,  
    MSKsymmattypee * type)
```

MOSEK maintains a vector denoted by E of symmetric data matrices. This function makes it possible to obtain important information about a single matrix in E .

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **idx** (*MSKint64t*) – Index of the matrix for which information is requested. (input)
- **dim** (*MSKint32t by reference*) – Returns the dimension of the requested matrix. (output)

- `nz` (*MSKint64t by reference*) – Returns the number of non-zeros in the requested matrix. (output)
- `type` (*MSKsymmattypee by reference*) – Returns the type of the requested matrix. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Inspecting the task*

MSK_gettaskname

```
MSKrescodee (MSKAPI MSK_gettaskname) (
    MSKtask_t task,
    MSKint32t sizetaskname,
    char * taskname)
```

Obtains the name assigned to the task.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `sizetaskname` (*MSKint32t*) – Length of the `taskname` buffer. (input)
- `taskname` (*MSKstring_t*) – Returns the task name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Inspecting the task*

MSK_gettasknamelen

```
MSKrescodee (MSKAPI MSK_gettasknamelen) (
    MSKtask_t task,
    MSKint32t * len)
```

Obtains the length the task name.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `len` (*MSKint32t by reference*) – Returns the length of the task name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Inspecting the task*

MSK_getvarbound

```
MSKrescodee (MSKAPI MSK_getvarbound) (
    MSKtask_t task,
    MSKint32t i,
    MSKboundkeye * bk,
    MSKrealt * bl,
    MSKrealt * bu)
```

Obtains bound information for one variable.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `i` (*MSKint32t*) – Index of the variable for which the bound information should be obtained. (input)
- `bk` (*MSKboundkeye by reference*) – Bound keys. (output)
- `bl` (*MSKrealt by reference*) – Values for lower bounds. (output)
- `bu` (*MSKrealt by reference*) – Values for upper bounds. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task, Problem data - bounds, Problem data - variables*

MSK_getvarboundslice

```
MSKrescodee (MSKAPI MSK_getvarboundslice) (  
    MSKtask_t task,  
    MSKint32t first,  
    MSKint32t last,  
    MSKboundkeye * bk,  
    MSKrealt * bl,  
    MSKrealt * bu)
```

Obtains bounds information for a slice of the variables.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **bk** (*MSKboundkeye**) – Bound keys. (output)
- **bl** (*MSKrealt**) – Values for lower bounds. (output)
- **bu** (*MSKrealt**) – Values for upper bounds. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Inspecting the task, Problem data - bounds, Problem data - variables*

MSK_getvarname

```
MSKrescodee (MSKAPI MSK_getvarname) (  
    MSKtask_t task,  
    MSKint32t j,  
    MSKint32t sizename,  
    char * name)
```

Obtains the name of a variable.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **j** (*MSKint32t*) – Index of a variable. (input)
- **sizename** (*MSKint32t*) – The length of the buffer pointed to by the **name** argument. (input)
- **name** (*MSKstring_t*) – Returns the required name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - linear part, Problem data - variables, Inspecting the task*

MSK_getvarnameindex

```
MSKrescodee (MSKAPI MSK_getvarnameindex) (  
    MSKtask_t task,  
    const char * somename,  
    MSKint32t * asgn,  
    MSKint32t * index)
```

Checks whether the name **somename** has been assigned to any variable. If so, the index of the variable is reported.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **somename** (*MSKstring_t*) – The name which should be checked. (input)
- **asgn** (*MSKint32t by reference*) – Is non-zero if the name **somename** is assigned to a variable. (output)
- **index** (*MSKint32t by reference*) – If the name **somename** is assigned to a variable, then **index** is the index of the variable. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - linear part, Problem data - variables, Inspecting the task*

MSK_getvarnamelen

```
MSKrescodee (MSKAPI MSK_getvarnamelen) (
    MSKtask_t task,
    MSKint32t i,
    MSKint32t * len)
```

Obtains the length of the name of a variable.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index of a variable. (input)
- **len** (*MSKint32t by reference*) – Returns the length of the indicated name. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - linear part, Problem data - variables, Inspecting the task*

MSK_getvartype

```
MSKrescodee (MSKAPI MSK_getvartype) (
    MSKtask_t task,
    MSKint32t j,
    MSKvariabletypee * vartype)
```

Gets the variable type of one variable.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **j** (*MSKint32t*) – Index of the variable. (input)
- **vartype** (*MSKvariabletypee by reference*) – Variable type of the *j*-th variable. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - variables*

MSK_getvartypelist

```
MSKrescodee (MSKAPI MSK_getvartypelist) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * subj,
    MSKvariabletypee * vartype)
```

Obtains the variable type of one or more variables. Upon return **vartype[k]** is the variable type of variable **subj[k]**.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of variables for which the variable type should be obtained. (input)
- `subj` (*MSKint32t**) – A list of variable indexes. (input)
- `vartype` (*MSKvariabletypee**) – The variables types corresponding to the variables specified by `subj`. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Problem data - variables*

MSK_getversion

```
MSKrescodee (MSKAPI MSK_getversion) (
    MSKint32t * major,
    MSKint32t * minor,
    MSKint32t * revision)
```

Obtains MOSEK version information.

Parameters

- `major` (*MSKint32t by reference*) – Major version number. (output)
- `minor` (*MSKint32t by reference*) – Minor version number. (output)
- `revision` (*MSKint32t by reference*) – Revision number. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Versions*

MSK_getxc

```
MSKrescodee (MSKAPI MSK_getxc) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * xc)
```

Obtains the x^c vector for a solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `xc` (*MSKrealt**) – Primal constraint solution. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - primal*

MSK_getxcslice

```
MSKrescodee (MSKAPI MSK_getxcslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    MSKrealt * xc)
```

Obtains a slice of the x^c vector for a solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `first` (*MSKint32t*) – First index in the sequence. (input)
- `last` (*MSKint32t*) – Last index plus 1 in the sequence. (input)

- xc (*MSKrealt**) – Primal constraint solution. (output)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Solution - primal*

MSK_getxx

```
MSKrescodee (MSKAPI MSK_getxx) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * xx)
```

Obtains the x^x vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- xx (*MSKrealt**) – Primal variable solution. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - primal*

MSK_getxxslice

```
MSKrescodee (MSKAPI MSK_getxxslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    MSKrealt * xx)
```

Obtains a slice of the x^x vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- first (*MSKint32t*) – First index in the sequence. (input)
- last (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- xx (*MSKrealt**) – Primal variable solution. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - primal*

MSK_gety

```
MSKrescodee (MSKAPI MSK_gety) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * y)
```

Obtains the y vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- y (*MSKrealt**) – Vector of dual variables corresponding to the constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_getyslice

```
MSKrescodee (MSKAPI MSK_getyslice) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKint32t first,  
    MSKint32t last,  
    MSKrealt * y)
```

Obtains a slice of the y vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **y** (*MSKrealt**) – Vector of dual variables corresponding to the constraints. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_initbasissolve

```
MSKrescodee (MSKAPI MSK_initbasissolve) (  
    MSKtask_t task,  
    MSKint32t * basis)
```

Prepare a task for use with the *MSK_solvewithbasis* function.

This function should be called

- immediately before the first call to *MSK_solvewithbasis*, and
- immediately before any subsequent call to *MSK_solvewithbasis* if the task has been modified.

If the basis is singular i.e. not invertible, then the error *MSK_RES_ERR_BASIS_SINGULAR* is reported.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **basis** (*MSKint32t**) – The array of basis indexes to use. The array is interpreted as follows: If $\text{basis}[i] \leq \text{numcon} - 1$, then $x_{\text{basis}[i]}^c$ is in the basis at position i , otherwise $x_{\text{basis}[i] - \text{numcon}}$ is in the basis at position i . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solving systems with basis matrix*

MSK_inputdata

```
MSKrescodee (MSKAPI MSK_inputdata) (  
    MSKtask_t task,  
    MSKint32t maxnumcon,  
    MSKint32t maxnumvar,  
    MSKint32t numcon,  
    MSKint32t numvar,  
    const MSKrealt * c,  
    MSKrealt cfix,  
    const MSKint32t * aptrb,  
    const MSKint32t * aptre,  
    const MSKint32t * asub,  
    const MSKrealt * aval,
```

(continues on next page)

```

const MSKboundkeye * bkc,
const MSKrealt * blc,
const MSKrealt * buc,
const MSKboundkeye * bkc,
const MSKrealt * blx,
const MSKrealt * bux)

```

Input the linear part of an optimization problem.

The non-zeros of A are inputted column-wise in the format described in Section *Column or Row Ordered Sparse Matrix*.

For an explained code example see Section *Linear Optimization* and Section *Matrix Formats*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumcon** (*MSKint32t*) – Number of preallocated constraints in the optimization task. (input)
- **maxnumvar** (*MSKint32t*) – Number of preallocated variables in the optimization task. (input)
- **numcon** (*MSKint32t*) – Number of constraints. (input)
- **numvar** (*MSKint32t*) – Number of variables. (input)
- **c** (*MSKrealt**) – Linear terms of the objective as a dense vector. The length is the number of variables. (input)
- **cfix** (*MSKrealt*) – Fixed term in the objective. (input)
- **aptrb** (*MSKint32t**) – Row or column start pointers. (input)
- **aptre** (*MSKint32t**) – Row or column end pointers. (input)
- **asub** (*MSKint32t**) – Coefficient subscripts. (input)
- **aval** (*MSKrealt**) – Coefficient values. (input)
- **bkc** (*MSKboundkeye**) – Bound keys for the constraints. (input)
- **blc** (*MSKrealt**) – Lower bounds for the constraints. (input)
- **buc** (*MSKrealt**) – Upper bounds for the constraints. (input)
- **bkc** (*MSKboundkeye**) – Bound keys for the variables. (input)
- **blx** (*MSKrealt**) – Lower bounds for the variables. (input)
- **bux** (*MSKrealt**) – Upper bounds for the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - bounds, Problem data - constraints*

MSK_inputdata64

```

MSKrescodee (MSKAPI MSK_inputdata64) (
    MSKtask_t task,
    MSKint32t maxnumcon,
    MSKint32t maxnumvar,
    MSKint32t numcon,
    MSKint32t numvar,
    const MSKrealt * c,
    MSKrealt cfix,
    const MSKint64t * aptrb,
    const MSKint64t * aptre,
    const MSKint32t * asub,
    const MSKrealt * aval,
    const MSKboundkeye * bkc,
    const MSKrealt * blc,
    const MSKrealt * buc,
    const MSKboundkeye * bkc,
    const MSKrealt * blx,
    const MSKrealt * bux)

```

Input the linear part of an optimization problem.

The non-zeros of A are inputted column-wise in the format described in Section *Column or Row Ordered Sparse Matrix*.

For an explained code example see Section *Linear Optimization* and Section *Matrix Formats*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumcon** (*MSKint32t*) – Number of preallocated constraints in the optimization task. (input)
- **maxnumvar** (*MSKint32t*) – Number of preallocated variables in the optimization task. (input)
- **numcon** (*MSKint32t*) – Number of constraints. (input)
- **numvar** (*MSKint32t*) – Number of variables. (input)
- **c** (*MSKrealt**) – Linear terms of the objective as a dense vector. The length is the number of variables. (input)
- **cfix** (*MSKrealt*) – Fixed term in the objective. (input)
- **aptrb** (*MSKint64t**) – Row or column start pointers. (input)
- **aptre** (*MSKint64t**) – Row or column end pointers. (input)
- **asub** (*MSKint32t**) – Coefficient subscripts. (input)
- **aval** (*MSKrealt**) – Coefficient values. (input)
- **bkc** (*MSKboundkeye**) – Bound keys for the constraints. (input)
- **blc** (*MSKrealt**) – Lower bounds for the constraints. (input)
- **buc** (*MSKrealt**) – Upper bounds for the constraints. (input)
- **bkx** (*MSKboundkeye**) – Bound keys for the variables. (input)
- **blx** (*MSKrealt**) – Lower bounds for the variables. (input)
- **bux** (*MSKrealt**) – Upper bounds for the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - bounds, Problem data - constraints*

MSK_iparvaltosymnam

```
MSKrescodee (MSKAPI MSK_iparvaltosymnam) (
    MSKenv_t env,
    MSKiparam whichparam,
    MSKint32t whichvalue,
    char * symbolicname)
```

Obtains the symbolic name corresponding to a value that can be assigned to an integer parameter.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **whichparam** (*MSKiparam*) – Which parameter. (input)
- **whichvalue** (*MSKint32t*) – Which value. (input)
- **symbolicname** (*MSKstring_t*) – The symbolic name corresponding to whichvalue. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters, Names*

MSK_isdoupaname

```
MSKrescodee (MSKAPI MSK_isdoupaname) (
    MSKtask_t task,
    const char * parname,
    MSKdparam * param)
```

Checks whether `parname` is a valid double parameter name.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `parname` (*MSKstring_t*) – Parameter name. (input)
- `param` (*MSKdparame by reference*) – Returns the parameter corresponding to the name, if one exists. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters, Names*

MSK_isinfinity

```
MSKboolean (MSKAPI MSK_isinfinity) (  
    MSKrealt value)
```

Return true if `value` is considered infinity by **MOSEK**.

Parameters `value` (*MSKrealt*) – The value to be checked (input)

Return (*MSKboolean*) – True if the value represents infinity.

MSK_isintparname

```
MSKrescodee (MSKAPI MSK_isintparname) (  
    MSKtask_t task,  
    const char * parname,  
    MSKiparam * param)
```

Checks whether `parname` is a valid integer parameter name.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `parname` (*MSKstring_t*) – Parameter name. (input)
- `param` (*MSKiparam by reference*) – Returns the parameter corresponding to the name, if one exists. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters, Names*

MSK_isstrparname

```
MSKrescodee (MSKAPI MSK_isstrparname) (  
    MSKtask_t task,  
    const char * parname,  
    MSKsparam * param)
```

Checks whether `parname` is a valid string parameter name.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `parname` (*MSKstring_t*) – Parameter name. (input)
- `param` (*MSKsparam by reference*) – Returns the parameter corresponding to the name, if one exists. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters, Names*

MSK_licensecleanup

```
MSKrescodee (MSKAPI MSK_licensecleanup) (
void)
```

Stops all threads and deletes all handles used by the license system. If this function is called, it must be called as the last **MOSEK** API call. No other **MOSEK** API calls are valid after this.

Return (*MSKrescodee*) – The function response code.

Groups *License system*

MSK_linkfiletoenvstream

```
MSKrescodee (MSKAPI MSK_linkfiletoenvstream) (
    MSKenv_t env,
    MSKstreamtypee whichstream,
    const char * filename,
    MSKint32t append)
```

Sends all output from the stream defined by **whichstream** to the file given by **filename**.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **whichstream** (*MSKstreamtypee*) – Index of the stream. (input)
- **filename** (*MSKstring_t*) – A valid file name. (input)
- **append** (*MSKint32t*) – If this argument is 0 the file will be overwritten, otherwise it will be appended to. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging*

MSK_linkfiletotaskstream

```
MSKrescodee (MSKAPI MSK_linkfiletotaskstream) (
    MSKtask_t task,
    MSKstreamtypee whichstream,
    const char * filename,
    MSKint32t append)
```

Directs all output from a task stream **whichstream** to a file **filename**.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichstream** (*MSKstreamtypee*) – Index of the stream. (input)
- **filename** (*MSKstring_t*) – A valid file name. (input)
- **append** (*MSKint32t*) – If this argument is 0 the output file will be overwritten, otherwise it will be appended to. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging*

MSK_linkfunctoenvstream

```
MSKrescodee (MSKAPI MSK_linkfunctoenvstream) (
    MSKenv_t env,
    MSKstreamtypee whichstream,
    MSKuserhandle_t handle,
    MSKstreamfunc func)
```

Connects a user-defined function to a stream.

Parameters

- `env` (*MSKenv_t*) – The MOSEK environment. (input)
- `whichstream` (*MSKstreamtypee*) – Index of the stream. (input)
- `handle` (*MSKuserhandle_t*) – A user-defined handle which is passed to the user-defined function `func`. (input)
- `func` (*MSKstreamfunc*) – All output to the stream `whichstream` is passed to `func`. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging, Callback*

MSK_linkfunctotaskstream

```
MSKrescodee (MSKAPI MSK_linkfunctotaskstream) (
    MSKtask_t task,
    MSKstreamtypee whichstream,
    MSKuserhandle_t handle,
    MSKstreamfunc func)
```

Connects a user-defined function to a task stream.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichstream` (*MSKstreamtypee*) – Index of the stream. (input)
- `handle` (*MSKuserhandle_t*) – A user-defined handle which is passed to the user-defined function `func`. (input)
- `func` (*MSKstreamfunc*) – All output to the stream `whichstream` is passed to `func`. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging, Callback*

MSK_makeemptytask

```
MSKrescodee (MSKAPI MSK_makeemptytask) (
    MSKenv_t env,
    MSKtask_t * task)
```

Creates a new optimization task.

Parameters

- `env` (*MSKenv_t*) – The MOSEK environment. (input)
- `task` (*MSKtask_t by reference*) – An optimization task. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management*

MSK_makeenv

```
MSKrescodee (MSKAPI MSK_makeenv) (
    MSKenv_t * env,
    const char * dbgfile)
```

Creates a new **MOSEK** environment. The environment must be shared among all tasks in a program.

Parameters

- `env` (*MSKenv_t by reference*) – The MOSEK environment. (output)
- `dbgfile` (*MSKstring_t*) – A user-defined file debug file. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management*

MSK_makeenvalloc

```
MSKrescodee (MSKAPI MSK_makeenvalloc) (  
    MSKenv_t * env,  
    MSKuserhandle_t usrptr,  
    MSKmallocfunc usrmalloc,  
    MSKcallocfunc usrcalloc,  
    MSKreallocfunc usrrealloc,  
    MSKfreefunc usrfree,  
    const char * dbgfile)
```

Creates a new **MOSEK** environment with user-defined memory management functions. The environment must be shared among all tasks in a program.

Parameters

- `env` (*MSKenv_t by reference*) – The MOSEK environment. (output)
- `usrptr` (*MSKuserhandle_t*) – A pointer to a user-defined data structure. The pointer is fed into `usrmalloc` and `usrfree`. (input)
- `usrmalloc` (*MSKmallocfunc*) – A user-defined `malloc` function or a NULL pointer. (input)
- `usrcalloc` (*MSKcallocfunc*) – A user-defined `calloc` function or a NULL pointer. (input)
- `usrrealloc` (*MSKreallocfunc*) – A user-defined `realloc` function or a NULL pointer. (input)
- `usrfree` (*MSKfreefunc*) – A user-defined `free` function which is used to deallocate space allocated by `usrmalloc`. This function must be defined if `usrmalloc != null`. (input)
- `dbgfile` (*MSKstring_t*) – A user-defined file debug file. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management*

MSK_maketask

```
MSKrescodee (MSKAPI MSK_maketask) (  
    MSKenv_t env,  
    MSKint32t maxnumcon,  
    MSKint32t maxnumvar,  
    MSKtask_t * task)
```

Creates a new task.

Parameters

- `env` (*MSKenv_t*) – The MOSEK environment. (input)
- `maxnumcon` (*MSKint32t*) – An optional estimate on the maximum number of constraints in the task. Can be 0 if no such estimate is known. (input)
- `maxnumvar` (*MSKint32t*) – An optional estimate on the maximum number of variables in the task. Can be 0 if no such estimate is known. (input)
- `task` (*MSKtask_t by reference*) – An optimization task. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management*

MSK_onesolutionsummary

```
MSKrescodee (MSKAPI MSK_onesolutionsummary) (
    MSKtask_t task,
    MSKstreamtypee whichstream,
    MSKsoltypee whichsol)
```

Prints a short summary of a specified solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichstream** (*MSKstreamtypee*) – Index of the stream. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging, Solution information*

MSK_optimize

```
MSKrescodee (MSKAPI MSK_optimize) (
    MSKtask_t task)
```

Calls the optimizer. Depending on the problem type and the selected optimizer this will call one of the optimizers in **MOSEK**. By default the interior point optimizer will be selected for continuous problems. The optimizer may be selected manually by setting the parameter *MSK_IPAR_OPTIMIZER*.

Response codes come in three categories:

- **Errors**: Indicate that an error has occurred during the optimization, e.g the optimizer has run out of memory (*MSK_RES_ERR_SPACE*).
- **Warnings**: Less fatal than errors. E.g *MSK_RES_WRN_LARGE_CJ* indicating possibly problematic problem data.
- **Termination codes**: Relaying information about the conditions under which the optimizer terminated. E.g *MSK_RES_TRM_MAX_ITERATIONS* indicates that the optimizer finished because it reached the maximum number of iterations specified by the user.

Parameters **task** (*MSKtask_t*) – An optimization task. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Optimization*

MSK_optimizermt

```
MSKrescodee (MSKAPI MSK_optimizermt) (
    MSKtask_t task,
    const char * server,
    const char * port,
    MSKrescodee * trmcode)
```

Offload the optimization task to a solver server defined by **server:port**. The call will block until a result is available or the connection closes.

If the string parameter *MSK_SPAR_REMOTE_ACCESS_TOKEN* is not blank, it will be passed to the server as authentication.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **server** (*MSKstring_t*) – Name or IP address of the solver server. (input)
- **port** (*MSKstring_t*) – Network port of the solver server. (input)
- **trmcode** (*MSKrescodee by reference*) – Is either *MSK_RES_OK* or a termination response code. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Remote optimization*

MSK_optimizersummary

```
MSKrescodee (MSKAPI MSK_optimizersummary) (  
    MSKtask_t task,  
    MSKstreamtypee whichstream)
```

Prints a short summary with optimizer statistics from last optimization.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichstream** (*MSKstreamtypee*) – Index of the stream. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging*

MSK_optimizetrm

```
MSKrescodee (MSKAPI MSK_optimizetrm) (  
    MSKtask_t task,  
    MSKrescodee * trmcode)
```

Calls the optimizer. Depending on the problem type and the selected optimizer this will call one of the optimizers in **MOSEK**. By default the interior point optimizer will be selected for continuous problems. The optimizer may be selected manually by setting the parameter *MSK_IPAR_OPTIMIZER*.

This function is equivalent to *MSK_optimize* except for the handling of return values. This function returns errors on the left hand side. Warnings are not returned and termination codes are returned through the separate argument **trmcode**.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **trmcode** (*MSKrescodee by reference*) – Is either *MSK_RES_OK* or a termination response code. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Optimization*

MSK_potrf

```
MSKrescodee (MSKAPI MSK_potrf) (  
    MSKenv_t env,  
    MSKuploe uplo,  
    MSKint32t n,  
    MSKrealt * a)
```

Computes a Cholesky factorization of a real symmetric positive definite dense matrix.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **uplo** (*MSKuploe*) – Indicates whether the upper or lower triangular part of the matrix is stored. (input)
- **n** (*MSKint32t*) – Dimension of the symmetric matrix. (input)
- **a** (*MSKrealt**) – A symmetric matrix stored in column-major order. Only the lower or the upper triangular part is used, accordingly with the **uplo** parameter. It will contain the result on exit. (input/output)

Return (*MSKrescodee*) – The function response code.

Groups *Linear algebra*

MSK_primalrepair

```
MSKrescodee (MSKAPI MSK_primalrepair) (  
    MSKtask_t task,  
    const MSKrealt * wlc,  
    const MSKrealt * wuc,  
    const MSKrealt * wlx,  
    const MSKrealt * wux)
```

The function repairs a primal infeasible optimization problem by adjusting the bounds on the constraints and variables where the adjustment is computed as the minimal weighted sum of relaxations to the bounds on the constraints and variables. Observe the function only repairs the problem but does not solve it. If an optimal solution is required the problem should be optimized after the repair.

The function is applicable to linear and conic problems possibly with integer variables.

Observe that when computing the minimal weighted relaxation the termination tolerance specified by the parameters of the task is employed. For instance the parameter *MSK_IPAR_MIO_MODE* can be used to make **MOSEK** ignore the integer constraints during the repair which usually leads to a much faster repair. However, the drawback is of course that the repaired problem may not have an integer feasible solution.

Note the function modifies the task in place. If this is not desired, then apply the function to a cloned task.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **wlc** (*MSKrealt**) – $(w_l^c)_i$ is the weight associated with relaxing the lower bound on constraint i . If the weight is negative, then the lower bound is not relaxed. Moreover, if the argument is NULL, then all the weights are assumed to be 1. (input)
- **wuc** (*MSKrealt**) – $(w_u^c)_i$ is the weight associated with relaxing the upper bound on constraint i . If the weight is negative, then the upper bound is not relaxed. Moreover, if the argument is NULL, then all the weights are assumed to be 1. (input)
- **wlx** (*MSKrealt**) – $(w_l^x)_j$ is the weight associated with relaxing the lower bound on variable j . If the weight is negative, then the lower bound is not relaxed. Moreover, if the argument is NULL, then all the weights are assumed to be 1. (input)
- **wux** (*MSKrealt**) – $(w_u^x)_j$ is the weight associated with relaxing the upper bound on variable j . If the weight is negative, then the upper bound is not relaxed. Moreover, if the argument is NULL, then all the weights are assumed to be 1. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Infeasibility diagnostic*

MSK_primalsensitivity

```
MSKrescodee (MSKAPI MSK_primalsensitivity) (  
    MSKtask_t task,  
    MSKint32t numi,  
    const MSKint32t * subi,  
    const MSKmarke * marki,  
    MSKint32t numj,  
    const MSKint32t * subj,  
    const MSKmarke * markj,  
    MSKrealt * leftpricei,  
    MSKrealt * rightpricei,
```

(continues on next page)

```

MSKrealt * leftrangei,
MSKrealt * rightrangei,
MSKrealt * leftpricej,
MSKrealt * rightpricej,
MSKrealt * leftrangej,
MSKrealt * rightrangej)

```

Calculates sensitivity information for bounds on variables and constraints. For details on sensitivity analysis, the definitions of *shadow price* and *linearity interval* and an example see Section [Sensitivity Analysis](#).

The type of sensitivity analysis to be performed (basis or optimal partition) is controlled by the parameter `MSK_IPAR_SENSITIVITY_TYPE`.

Parameters

- `task` (`MSKtask_t`) – An optimization task. (input)
- `numi` (`MSKint32t`) – Number of bounds on constraints to be analyzed. Length of `subi` and `marki`. (input)
- `subi` (`MSKint32t*`) – Indexes of constraints to analyze. (input)
- `marki` (`MSKmarke*`) – The value of `marki[i]` indicates for which bound of constraint `subi[i]` sensitivity analysis is performed. If `marki[i] = MSK_MARK_UP` the upper bound of constraint `subi[i]` is analyzed, and if `marki[i] = MSK_MARK_LO` the lower bound is analyzed. If `subi[i]` is an equality constraint, either `MSK_MARK_LO` or `MSK_MARK_UP` can be used to select the constraint for sensitivity analysis. (input)
- `numj` (`MSKint32t`) – Number of bounds on variables to be analyzed. Length of `subj` and `markj`. (input)
- `subj` (`MSKint32t*`) – Indexes of variables to analyze. (input)
- `markj` (`MSKmarke*`) – The value of `markj[j]` indicates for which bound of variable `subj[j]` sensitivity analysis is performed. If `markj[j] = MSK_MARK_UP` the upper bound of variable `subj[j]` is analyzed, and if `markj[j] = MSK_MARK_LO` the lower bound is analyzed. If `subj[j]` is a fixed variable, either `MSK_MARK_LO` or `MSK_MARK_UP` can be used to select the bound for sensitivity analysis. (input)
- `leftpricei` (`MSKrealt*`) – `leftpricei[i]` is the left shadow price for the bound `marki[i]` of constraint `subi[i]`. (output)
- `rightpricei` (`MSKrealt*`) – `rightpricei[i]` is the right shadow price for the bound `marki[i]` of constraint `subi[i]`. (output)
- `leftrangei` (`MSKrealt*`) – `leftrangei[i]` is the left range β_1 for the bound `marki[i]` of constraint `subi[i]`. (output)
- `rightrangei` (`MSKrealt*`) – `rightrangei[i]` is the right range β_2 for the bound `marki[i]` of constraint `subi[i]`. (output)
- `leftpricej` (`MSKrealt*`) – `leftpricej[j]` is the left shadow price for the bound `markj[j]` of variable `subj[j]`. (output)
- `rightpricej` (`MSKrealt*`) – `rightpricej[j]` is the right shadow price for the bound `markj[j]` of variable `subj[j]`. (output)
- `leftrangej` (`MSKrealt*`) – `leftrangej[j]` is the left range β_1 for the bound `markj[j]` of variable `subj[j]`. (output)
- `rightrangej` (`MSKrealt*`) – `rightrangej[j]` is the right range β_2 for the bound `markj[j]` of variable `subj[j]`. (output)

Return (`MSKrescodee`) – The function response code.

Groups [Sensitivity analysis](#)

MSK_printparam

```
MSKrescodee (MSKAPI MSK_printparam) (
    MSKtask_t task)
```

Prints the current parameter settings to the message stream.

Parameters *task* (*MSKtask_t*) – An optimization task. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Logging*

MSK_probtypetostr

```
MSKrescodee (MSKAPI MSK_probtypetostr) (
    MSKtask_t task,
    MSKproblemtypee probtype,
    char * str)
```

Obtains a string containing the name of a given problem type.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *probtype* (*MSKproblemtypee*) – Problem type. (input)
- *str* (*MSKstring_t*) – String corresponding to the problem type key *probtype*. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Inspecting the task, Names*

MSK_prostatostr

```
MSKrescodee (MSKAPI MSK_prostatostr) (
    MSKtask_t task,
    MSKprostaeprosta,
    char * str)
```

Obtains a string containing the name of a given problem status.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *prosta* (*MSKprostaeprosta*) – Problem status. (input)
- *str* (*MSKstring_t*) – String corresponding to the status key *prosta*. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information, Names*

MSK_putacol

```
MSKrescodee (MSKAPI MSK_putacol) (
    MSKtask_t task,
    MSKint32t j,
    MSKint32t nzj,
    const MSKint32t * subj,
    const MSKrealt * valj)
```

Change one column of the linear constraint matrix *A*. Resets all the elements in column *j* to zero and then sets

$$a_{\text{subj}[k],j} = \text{valj}[k], \quad k = 0, \dots, \text{nzj} - 1.$$

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)

- j (*MSKint32t*) – Index of a column in A . (input)
- nzj (*MSKint32t*) – Number of non-zeros in column j of A . (input)
- $subj$ (*MSKint32t**) – Row indexes of non-zero values in column j of A . (input)
- $valj$ (*MSKrealt**) – New non-zero values of column j in A . (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putacollist

```
MSKrescodee (MSKAPI MSK_putacollist) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * sub,
    const MSKint32t * ptrb,
    const MSKint32t * ptre,
    const MSKint32t * asub,
    const MSKrealt * aval)
```

Change a set of columns in the linear constraint matrix A with data in sparse triplet format. The requested columns are set to zero and then updated with:

$$\text{for } i = 0, \dots, num - 1 \\ a_{asub[k], sub[i]} = aval[k], \quad k = ptrb[i], \dots, ptre[i] - 1.$$

Parameters

- $task$ (*MSKtask_t*) – An optimization task. (input)
- num (*MSKint32t*) – Number of columns of A to replace. (input)
- sub (*MSKint32t**) – Indexes of columns that should be replaced, no duplicates. (input)
- $ptrb$ (*MSKint32t**) – Array of pointers to the first element in each column. (input)
- $ptre$ (*MSKint32t**) – Array of pointers to the last element plus one in each column. (input)
- $asub$ (*MSKint32t**) – Row indexes of new elements. (input)
- $aval$ (*MSKrealt**) – Coefficient values. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putacollist64

```
MSKrescodee (MSKAPI MSK_putacollist64) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * sub,
    const MSKint64t * ptrb,
    const MSKint64t * ptre,
    const MSKint32t * asub,
    const MSKrealt * aval)
```

Change a set of columns in the linear constraint matrix A with data in sparse triplet format. The requested columns are set to zero and then updated with:

$$\text{for } i = 0, \dots, num - 1 \\ a_{asub[k], sub[i]} = aval[k], \quad k = ptrb[i], \dots, ptre[i] - 1.$$

Parameters

- $task$ (*MSKtask_t*) – An optimization task. (input)
- num (*MSKint32t*) – Number of columns of A to replace. (input)

- `sub` (*MSKint32t**) – Indexes of columns that should be replaced, no duplicates. (input)
- `ptrb` (*MSKint64t**) – Array of pointers to the first element in each column. (input)
- `ptre` (*MSKint64t**) – Array of pointers to the last element plus one in each column. (input)
- `asub` (*MSKint32t**) – Row indexes of new elements. (input)
- `aval` (*MSKrealt**) – Coefficient values. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putacolslice

```
MSKrescodee (MSKAPI MSK_putacolslice) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    const MSKint32t * ptrb,
    const MSKint32t * ptre,
    const MSKint32t * asub,
    const MSKrealt * aval)
```

Change a slice of columns in the linear constraint matrix A with data in sparse triplet format. The requested columns are set to zero and then updated with:

$$\begin{aligned} \text{for } i = \text{first}, \dots, \text{last} - 1 \\ a_{\text{asub}[k], i} = \text{aval}[k], \quad k = \text{ptrb}[i], \dots, \text{ptre}[i] - 1. \end{aligned}$$

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `first` (*MSKint32t*) – First column in the slice. (input)
- `last` (*MSKint32t*) – Last column plus one in the slice. (input)
- `ptrb` (*MSKint32t**) – Array of pointers to the first element in each column. (input)
- `ptre` (*MSKint32t**) – Array of pointers to the last element plus one in each column. (input)
- `asub` (*MSKint32t**) – Row indexes of new elements. (input)
- `aval` (*MSKrealt**) – Coefficient values. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putacolslice64

```
MSKrescodee (MSKAPI MSK_putacolslice64) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    const MSKint64t * ptrb,
    const MSKint64t * ptre,
    const MSKint32t * asub,
    const MSKrealt * aval)
```

Change a slice of columns in the linear constraint matrix A with data in sparse triplet format. The requested columns are set to zero and then updated with:

$$\begin{aligned} \text{for } i = \text{first}, \dots, \text{last} - 1 \\ a_{\text{asub}[k], i} = \text{aval}[k], \quad k = \text{ptrb}[i], \dots, \text{ptre}[i] - 1. \end{aligned}$$

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `first` (*MSKint32t*) – First column in the slice. (input)
- `last` (*MSKint32t*) – Last column plus one in the slice. (input)
- `ptrb` (*MSKint64t**) – Array of pointers to the first element in each column. (input)
- `ptre` (*MSKint64t**) – Array of pointers to the last element plus one in each column. (input)
- `asub` (*MSKint32t**) – Row indexes of new elements. (input)
- `aval` (*MSKrealt**) – Coefficient values. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putaij

```
MSKrescodee (MSKAPI MSK_putaij) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKint32t j,  
    MSKrealt aij)
```

Changes a coefficient in the linear coefficient matrix A using the method

$$a_{i,j} = \text{aij}.$$

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `i` (*MSKint32t*) – Constraint (row) index. (input)
- `j` (*MSKint32t*) – Variable (column) index. (input)
- `aij` (*MSKrealt*) – New coefficient for $a_{i,j}$. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putaijlist

```
MSKrescodee (MSKAPI MSK_putaijlist) (  
    MSKtask_t task,  
    MSKint32t num,  
    const MSKint32t * subi,  
    const MSKint32t * subj,  
    const MSKrealt * valij)
```

Changes one or more coefficients in A using the method

$$a_{\text{subi}[k], \text{subj}[k]} = \text{valij}[k], \quad k = 0, \dots, \text{num} - 1.$$

Duplicates are not allowed.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of coefficients that should be changed. (input)
- `subi` (*MSKint32t**) – Constraint (row) indices. (input)
- `subj` (*MSKint32t**) – Variable (column) indices. (input)
- `valij` (*MSKrealt**) – New coefficient values for $a_{i,j}$. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putaijlist64

```
MSKrescodee (MSKAPI MSK_putaijlist64) (  
    MSKtask_t task,  
    MSKint64t num,  
    const MSKint32t * subi,  
    const MSKint32t * subj,  
    const MSKrealt * valij)
```

Changes one or more coefficients in A using the method

$$a_{\text{subi}[k], \text{subj}[k]} = \text{valij}[k], \quad k = 0, \dots, \text{num} - 1.$$

Duplicates are not allowed.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint64t*) – Number of coefficients that should be changed. (input)
- `subi` (*MSKint32t**) – Constraint (row) indices. (input)
- `subj` (*MSKint32t**) – Variable (column) indices. (input)
- `valij` (*MSKrealt**) – New coefficient values for $a_{i,j}$. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putarow

```
MSKrescodee (MSKAPI MSK_putarow) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKint32t nzi,  
    const MSKint32t * subi,  
    const MSKrealt * vali)
```

Change one row of the linear constraint matrix A . Resets all the elements in row i to zero and then sets

$$a_{i, \text{subi}[k]} = \text{vali}[k], \quad k = 0, \dots, \text{nzi} - 1.$$

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `i` (*MSKint32t*) – Index of a row in A . (input)
- `nzi` (*MSKint32t*) – Number of non-zeros in row i of A . (input)
- `subi` (*MSKint32t**) – Column indexes of non-zero values in row i of A . (input)
- `vali` (*MSKrealt**) – New non-zero values of row i in A . (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putarowlist

```
MSKrescodee (MSKAPI MSK_putarowlist) (  
    MSKtask_t task,  
    MSKint32t num,  
    const MSKint32t * sub,  
    const MSKint32t * ptrb,  
    const MSKint32t * ptre,  
    const MSKint32t * asub,  
    const MSKrealt * aval)
```

Change a set of rows in the linear constraint matrix A with data in sparse triplet format. The requested rows are set to zero and then updated with:

```
for i = 0, ..., num - 1
    asub[i],asub[k] = aval[k],    k = ptrb[i], ..., ptre[i] - 1.
```

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- num (*MSKint32t*) – Number of rows of A to replace. (input)
- sub (*MSKint32t**) – Indexes of rows that should be replaced, no duplicates. (input)
- ptrb (*MSKint32t**) – Array of pointers to the first element in each row. (input)
- ptre (*MSKint32t**) – Array of pointers to the last element plus one in each row. (input)
- asub (*MSKint32t**) – Column indexes of new elements. (input)
- aval (*MSKrealt**) – Coefficient values. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putarowlist64

```
MSKrescodee (MSKAPI MSK_putarowlist64) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * sub,
    const MSKint64t * ptrb,
    const MSKint64t * ptre,
    const MSKint32t * asub,
    const MSKrealt * aval)
```

Change a set of rows in the linear constraint matrix A with data in sparse triplet format. The requested rows are set to zero and then updated with:

```
for i = 0, ..., num - 1
    asub[i],asub[k] = aval[k],    k = ptrb[i], ..., ptre[i] - 1.
```

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- num (*MSKint32t*) – Number of rows of A to replace. (input)
- sub (*MSKint32t**) – Indexes of rows that should be replaced, no duplicates. (input)
- ptrb (*MSKint64t**) – Array of pointers to the first element in each row. (input)
- ptre (*MSKint64t**) – Array of pointers to the last element plus one in each row. (input)
- asub (*MSKint32t**) – Column indexes of new elements. (input)
- aval (*MSKrealt**) – Coefficient values. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putarowslice

```
MSKrescodee (MSKAPI MSK_putarowslice) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    const MSKint32t * ptrb,
    const MSKint32t * ptre,
    const MSKint32t * asub,
    const MSKrealt * aval)
```

Change a slice of rows in the linear constraint matrix A with data in sparse triplet format. The requested columns are set to zero and then updated with:

```
for i = first,...,last - 1
    asub[i],asub[k] = aval[k], k = ptrb[i],...,ptre[i] - 1.
```

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- first (*MSKint32t*) – First row in the slice. (input)
- last (*MSKint32t*) – Last row plus one in the slice. (input)
- ptrb (*MSKint32t**) – Array of pointers to the first element in each row. (input)
- ptre (*MSKint32t**) – Array of pointers to the last element plus one in each row. (input)
- asub (*MSKint32t**) – Column indexes of new elements. (input)
- aval (*MSKrealt**) – Coefficient values. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putarowslice64

```
MSKrescodee (MSKAPI MSK_putarowslice64) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    const MSKint64t * ptrb,
    const MSKint64t * ptre,
    const MSKint32t * asub,
    const MSKrealt * aval)
```

Change a slice of rows in the linear constraint matrix A with data in sparse triplet format. The requested columns are set to zero and then updated with:

```
for i = first,...,last - 1
    asub[i],asub[k] = aval[k], k = ptrb[i],...,ptre[i] - 1.
```

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- first (*MSKint32t*) – First row in the slice. (input)
- last (*MSKint32t*) – Last row plus one in the slice. (input)
- ptrb (*MSKint64t**) – Array of pointers to the first element in each row. (input)
- ptre (*MSKint64t**) – Array of pointers to the last element plus one in each row. (input)
- asub (*MSKint32t**) – Column indexes of new elements. (input)
- aval (*MSKrealt**) – Coefficient values. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putatruncatetol

```
MSKrescodee (MSKAPI MSK_putatruncatetol) (
    MSKtask_t task,
    MSKrealt tolzero)
```

Truncates (sets to zero) all elements in A that satisfy

$$|a_{i,j}| \leq \text{tolzero}.$$

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **tolzero** (*MSKrealt*) – Truncation tolerance. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part*

MSK_putbarablocktriplet

```
MSKrescodee (MSKAPI MSK_putbarablocktriplet) (  
    MSKtask_t task,  
    MSKint64t num,  
    const MSKint32t * subi,  
    const MSKint32t * subj,  
    const MSKint32t * subk,  
    const MSKint32t * subl,  
    const MSKrealt * valijkl)
```

Inputs the \bar{A} matrix in block triplet form.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint64t*) – Number of elements in the block triplet form. (input)
- **subi** (*MSKint32t**) – Constraint index. (input)
- **subj** (*MSKint32t**) – Symmetric matrix variable index. (input)
- **subk** (*MSKint32t**) – Block row index. (input)
- **subl** (*MSKint32t**) – Block column index. (input)
- **valijkl** (*MSKrealt**) – The numerical value associated with each block triplet. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite*

MSK_putbaraij

```
MSKrescodee (MSKAPI MSK_putbaraij) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKint32t j,  
    MSKint64t num,  
    const MSKint64t * sub,  
    const MSKrealt * weights)
```

This function sets one element in the \bar{A} matrix.

Each element in the \bar{A} matrix is a weighted sum of symmetric matrices from the symmetric matrix storage E , so \bar{A}_{ij} is a symmetric matrix. By default all elements in \bar{A} are 0, so only non-zero elements need be added. Setting the same element again will overwrite the earlier entry.

The symmetric matrices from E are defined separately using the function *MSK_appendsparsesymmat*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Row index of \bar{A} . (input)
- **j** (*MSKint32t*) – Column index of \bar{A} . (input)
- **num** (*MSKint64t*) – The number of terms in the weighted sum that forms \bar{A}_{ij} . (input)
- **sub** (*MSKint64t**) – Indices in E of the matrices appearing in the weighted sum for \bar{A}_{ij} . (input)

- `weights (MSKrealt*)` – `weights[k]` is the coefficient of the `sub[k]`-th element of E in the weighted sum forming \bar{A}_{ij} . (input)
- Return** (`MSKrescodee`) – The function response code.
- Groups** *Problem data - semidefinite*

MSK_putbaraijlist

```
MSKrescodee (MSKAPI MSK_putbaraijlist) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * sub_i,
    const MSKint32t * sub_j,
    const MSKint64t * alphaptrb,
    const MSKint64t * alphaptre,
    const MSKint64t * matidx,
    const MSKrealt * weights)
```

This function sets a list of elements in the \bar{A} matrix.

Each element in the \bar{A} matrix is a weighted sum of symmetric matrices from the symmetric matrix storage E , so \bar{A}_{ij} is a symmetric matrix. By default all elements in \bar{A} are 0, so only non-zero elements need be added. Setting the same element again will overwrite the earlier entry.

The symmetric matrices from E are defined separately using the function *MSK_appendsparsesymmat*.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `num (MSKint32t)` – Number of \bar{A} entries to add. (input)
- `sub_i (MSKint32t*)` – Row index of \bar{A} . (input)
- `sub_j (MSKint32t*)` – Column index of \bar{A} . (input)
- `alphaptrb (MSKint64t*)` – Start entries for terms in the weighted sum that forms \bar{A}_{ij} . (input)
- `alphaptre (MSKint64t*)` – End entries for terms in the weighted sum that forms \bar{A}_{ij} . (input)
- `matidx (MSKint64t*)` – Indices in E of the matrices appearing in the weighted sum for \bar{A}_{ij} . (input)
- `weights (MSKrealt*)` – `weights[k]` is the coefficient of the `sub[k]`-th element of E in the weighted sum forming \bar{A}_{ij} . (input)

Return (`MSKrescodee`) – The function response code.

Groups *Problem data - semidefinite*

MSK_putbararowlist

```
MSKrescodee (MSKAPI MSK_putbararowlist) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * sub_i,
    const MSKint64t * ptrb,
    const MSKint64t * ptre,
    const MSKint32t * sub_j,
    const MSKint64t * nummat,
    const MSKint64t * matidx,
    const MSKrealt * weights)
```

This function replaces a list of rows in the \bar{A} matrix.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)

- num (*MSKint32t*) – Number of \overline{A} entries to add. (input)
- subi (*MSKint32t**) – Row indexes of \overline{A} . (input)
- ptrb (*MSKint64t**) – Start of rows in \overline{A} . (input)
- ptre (*MSKint64t**) – End of rows in \overline{A} . (input)
- subj (*MSKint32t**) – Column index of \overline{A} . (input)
- nummat (*MSKint64t**) – Number of entries in weighted sum of matrixes. (input)
- matidx (*MSKint64t**) – Matrix indexes for weighted sum of matrixes. (input)
- weights (*MSKrealt**) – Weights for weighted sum of matrixes. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite*

MSK_putbarcblocktriplet

```
MSKrescodee (MSKAPI MSK_putbarcblocktriplet) (
    MSKtask_t task,
    MSKint64t num,
    const MSKint32t * subj,
    const MSKint32t * subk,
    const MSKint32t * subl,
    const MSKrealt * valjkl)
```

Inputs the \overline{C} matrix in block triplet form.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- num (*MSKint64t*) – Number of elements in the block triplet form. (input)
- subj (*MSKint32t**) – Symmetric matrix variable index. (input)
- subk (*MSKint32t**) – Block row index. (input)
- subl (*MSKint32t**) – Block column index. (input)
- valjkl (*MSKrealt**) – The numerical value associated with each block triplet. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite*

MSK_putbarcj

```
MSKrescodee (MSKAPI MSK_putbarcj) (
    MSKtask_t task,
    MSKint32t j,
    MSKint64t num,
    const MSKint64t * sub,
    const MSKrealt * weights)
```

This function sets one entry in the \overline{C} vector.

Each element in the \overline{C} vector is a weighted sum of symmetric matrices from the symmetric matrix storage E , so \overline{C}_j is a symmetric matrix. By default all elements in \overline{C} are 0, so only non-zero elements need be added. Setting the same element again will overwrite the earlier entry.

The symmetric matrices from E are defined separately using the function *MSK_appendsparsesymmat*.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- j (*MSKint32t*) – Index of the element in \overline{C} that should be changed. (input)
- num (*MSKint64t*) – The number of elements in the weighted sum that forms \overline{C}_j . (input)

- `sub (MSKint64t*)` – Indices in E of matrices appearing in the weighted sum for \overline{C}_j (input)
- `weights (MSKrealt*)` – `weights[k]` is the coefficient of the `sub[k]`-th element of E in the weighted sum forming \overline{C}_j . (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite, Problem data - objective*

MSK_putbarsj

```
MSKrescodee (MSKAPI MSK_putbarsj) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t j,
    const MSKrealt * barsj)
```

Sets the dual solution for a semidefinite variable.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `whichsol (MSKsoltypee)` – Selects a solution. (input)
- `j (MSKint32t)` – Index of the semidefinite variable. (input)
- `barsj (MSKrealt*)` – Value of \overline{S}_j . Format as in *MSK_getbarsj*. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - semidefinite*

MSK_putbarvarname

```
MSKrescodee (MSKAPI MSK_putbarvarname) (
    MSKtask_t task,
    MSKint32t j,
    const char * name)
```

Sets the name of a semidefinite variable.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `j (MSKint32t)` – Index of the variable. (input)
- `name (MSKstring_t)` – The variable name. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - semidefinite*

MSK_putbarxj

```
MSKrescodee (MSKAPI MSK_putbarxj) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t j,
    const MSKrealt * barxj)
```

Sets the primal solution for a semidefinite variable.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `whichsol (MSKsoltypee)` – Selects a solution. (input)
- `j (MSKint32t)` – Index of the semidefinite variable. (input)
- `barxj (MSKrealt*)` – Value of \overline{X}_j . Format as in *MSK_getbarxj*. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - semidefinite*

MSK_putcallbackfunc

```
MSKrescodee (MSKAPI MSK_putcallbackfunc) (
    MSKtask_t task,
    MSKcallbackfunc func,
    MSKuserhandle_t handle)
```

Sets a user-defined progress callback function of type *MSKcallbackfunc*. The callback function is called frequently during the optimization process. See Section *Progress and data callback* for an example.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **func** (*MSKcallbackfunc*) – A user-defined function which will be called occasionally from within the **MOSEK** optimizers. If the argument is a NULL pointer, then a previously defined callback function is removed. The progress function has the type *MSKcallbackfunc*. (input)
- **handle** (*MSKuserhandle_t*) – A pointer to a user-defined data structure. Whenever the function **func** is called, then **handle** is passed to the function. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Callback*

MSK_putcfix

```
MSKrescodee (MSKAPI MSK_putcfix) (
    MSKtask_t task,
    MSKrealt cfix)
```

Replaces the fixed term in the objective by a new one.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **cfix** (*MSKrealt*) – Fixed term in the objective. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - objective*

MSK_putcj

```
MSKrescodee (MSKAPI MSK_putcj) (
    MSKtask_t task,
    MSKint32t j,
    MSKrealt cj)
```

Modifies one coefficient in the linear objective vector c , i.e.

$$c_j = cj.$$

If the absolute value exceeds *MSK_DPAR_DATA_TOL_C_HUGE* an error is generated. If the absolute value exceeds *MSK_DPAR_DATA_TOL_CJ_LARGE*, a warning is generated, but the coefficient is inputted as specified.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **j** (*MSKint32t*) – Index of the variable for which c should be changed. (input)
- **cj** (*MSKrealt*) – New value of c_j . (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - objective*

MSK_putclist

```
MSKrescodee (MSKAPI MSK_putclist) (  
    MSKtask_t task,  
    MSKint32t num,  
    const MSKint32t * subj,  
    const MSKrealt * val)
```

Modifies the coefficients in the linear term c in the objective using the principle

$$c_{\text{subj}[t]} = \text{val}[t], \quad t = 0, \dots, \text{num} - 1.$$

If a variable index is specified multiple times in `subj` only the last entry is used. Data checks are performed as in *MSK_putcj*.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of coefficients that should be changed. (input)
- `subj` (*MSKint32t**) – Indices of variables for which the coefficient in c should be changed. (input)
- `val` (*MSKrealt**) – New numerical values for coefficients in c that should be modified. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - variables, Problem data - objective*

MSK_putconbound

```
MSKrescodee (MSKAPI MSK_putconbound) (  
    MSKtask_t task,  
    MSKint32t i,  
    MSKboundkeye bkc,  
    MSKrealt blc,  
    MSKrealt buc)
```

Changes the bounds for one constraint.

If the bound value specified is numerically larger than *MSK_DPAR_DATA_TOL_BOUND_INF* it is considered infinite and the bound key is changed accordingly. If a bound value is numerically larger than *MSK_DPAR_DATA_TOL_BOUND_WRN*, a warning will be displayed, but the bound is inputted as specified.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `i` (*MSKint32t*) – Index of the constraint. (input)
- `bkc` (*MSKboundkeye*) – New bound key. (input)
- `blc` (*MSKrealt*) – New lower bound. (input)
- `buc` (*MSKrealt*) – New upper bound. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - constraints, Problem data - bounds*

MSK_putconboundlist

```
MSKrescodee (MSKAPI MSK_putconboundlist) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * sub,
    const MSKboundkeye * bkc,
    const MSKrealt * blc,
    const MSKrealt * buc)
```

Changes the bounds for a list of constraints. If multiple bound changes are specified for a constraint, then only the last change takes effect. Data checks are performed as in *MSK_putconbound*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint32t*) – Number of bounds that should be changed. (input)
- **sub** (*MSKint32t**) – List of constraint indexes. (input)
- **bkc** (*MSKboundkeye**) – Bound keys for the constraints. (input)
- **blc** (*MSKrealt**) – Lower bounds for the constraints. (input)
- **buc** (*MSKrealt**) – Upper bounds for the constraints. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - constraints, Problem data - bounds*

MSK_putconboundlistconst

```
MSKrescodee (MSKAPI MSK_putconboundlistconst) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * sub,
    MSKboundkeye bkc,
    MSKrealt blc,
    MSKrealt buc)
```

Changes the bounds for one or more constraints. Data checks are performed as in *MSK_putconbound*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint32t*) – Number of bounds that should be changed. (input)
- **sub** (*MSKint32t**) – List of constraint indexes. (input)
- **bkc** (*MSKboundkeye*) – New bound key for all constraints in the list. (input)
- **blc** (*MSKrealt*) – New lower bound for all constraints in the list. (input)
- **buc** (*MSKrealt*) – New upper bound for all constraints in the list. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - constraints, Problem data - bounds*

MSK_putconboundslice

```
MSKrescodee (MSKAPI MSK_putconboundslice) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    const MSKboundkeye * bkc,
    const MSKrealt * blc,
    const MSKrealt * buc)
```

Changes the bounds for a slice of the constraints. Data checks are performed as in *MSK_putconbound*.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `first` (*MSKint32t*) – First index in the sequence. (input)
- `last` (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- `bkc` (*MSKboundkeye**) – Bound keys for the constraints. (input)
- `blc` (*MSKrealt**) – Lower bounds for the constraints. (input)
- `buc` (*MSKrealt**) – Upper bounds for the constraints. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - constraints, Problem data - bounds*

MSK_putconboundsliceconst

```
MSKrescodee (MSKAPI MSK_putconboundsliceconst) (
    MSKtask_t task,
    MSKint32t first,
    MSKint32t last,
    MSKboundkeye bkc,
    MSKrealt blc,
    MSKrealt buc)
```

Changes the bounds for a slice of the constraints. Data checks are performed as in *MSK_putconbound*.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `first` (*MSKint32t*) – First index in the sequence. (input)
- `last` (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- `bkc` (*MSKboundkeye*) – New bound key for all constraints in the slice. (input)
- `blc` (*MSKrealt*) – New lower bound for all constraints in the slice. (input)
- `buc` (*MSKrealt*) – New upper bound for all constraints in the slice. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - constraints, Problem data - bounds*

MSK_putcone

```
MSKrescodee (MSKAPI MSK_putcone) (
    MSKtask_t task,
    MSKint32t k,
    MSKconetypee ct,
    MSKrealt coneapar,
    MSKint32t nummem,
    const MSKint32t * submem)
```

Replaces a conic constraint.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `k` (*MSKint32t*) – Index of the cone. (input)
- `ct` (*MSKconetypee*) – Specifies the type of the cone. (input)
- `coneapar` (*MSKrealt*) – For the power cone it denotes the exponent alpha. For other cone types it is unused and can be set to 0. (input)
- `nummem` (*MSKint32t*) – Number of member variables in the cone. (input)
- `submem` (*MSKint32t**) – Variable subscripts of the members in the cone. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - cones*

MSK_putconename

```
MSKrescodee (MSKAPI MSK_putconename) (
    MSKtask_t task,
    MSKint32t j,
    const char * name)
```

Sets the name of a cone.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **j** (*MSKint32t*) – Index of the cone. (input)
- **name** (*MSKstring_t*) – The name of the cone. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - cones*

MSK_putconname

```
MSKrescodee (MSKAPI MSK_putconname) (
    MSKtask_t task,
    MSKint32t i,
    const char * name)
```

Sets the name of a constraint.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index of the constraint. (input)
- **name** (*MSKstring_t*) – The name of the constraint. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - constraints, Problem data - linear part*

MSK_putconsolutioni

```
MSKrescodee (MSKAPI MSK_putconsolutioni) (
    MSKtask_t task,
    MSKint32t i,
    MSKsoltypee whichsol,
    MSKstakeye sk,
    MSKrealt x,
    MSKrealt sl,
    MSKrealt su)
```

Sets the primal and dual solution information for a single constraint.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **i** (*MSKint32t*) – Index of the constraint. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **sk** (*MSKstakeye*) – Status key of the constraint. (input)
- **x** (*MSKrealt*) – Primal solution value of the constraint. (input)
- **sl** (*MSKrealt*) – Solution value of the dual variable associated with the lower bound. (input)
- **su** (*MSKrealt*) – Solution value of the dual variable associated with the upper bound. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information, Solution - primal, Solution - dual*

MSK_putcslice

```
MSKrescodee (MSKAPI MSK_putcslice) (  
    MSKtask_t task,  
    MSKint32t first,  
    MSKint32t last,  
    const MSKrealt * slice)
```

Modifies a slice in the linear term c in the objective using the principle

$$c_j = \text{slice}[j - \text{first}], \quad j = \text{first}, \dots, \text{last} - 1$$

Data checks are performed as in *MSK_putcj*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **first** (*MSKint32t*) – First element in the slice of c . (input)
- **last** (*MSKint32t*) – Last element plus 1 of the slice in c to be changed. (input)
- **slice** (*MSKrealt**) – New numerical values for coefficients in c that should be modified. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - objective*

MSK_putdouparam

```
MSKrescodee (MSKAPI MSK_putdouparam) (  
    MSKtask_t task,  
    MSKdparam param,  
    MSKrealt parvalue)
```

Sets the value of a double parameter.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **param** (*MSKdparam*) – Which parameter. (input)
- **parvalue** (*MSKrealt*) – Parameter value. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_putexitfunc

```
MSKrescodee (MSKAPI MSK_putexitfunc) (  
    MSKenv_t env,  
    MSKexitfunc exitfunc,  
    MSKuserhandle_t handle)
```

In case **MOSEK** experiences a fatal error, then a user-defined exit function can be called. The exit function should terminate **MOSEK**. In general it is not necessary to define an exit function.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **exitfunc** (*MSKexitfunc*) – A user-defined exit function. (input)
- **handle** (*MSKuserhandle_t*) – A pointer to a user-defined data structure which is passed to **exitfunc** when called. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging, Callback*

MSK_putintparam

```
MSKrescodee (MSKAPI MSK_putintparam) (  
    MSKtask_t task,  
    MSKiparam param,  
    MSKint32t parvalue)
```

Sets the value of an integer parameter.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- param (*MSKiparam*) – Which parameter. (input)
- parvalue (*MSKint32t*) – Parameter value. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_putlicensecode

```
MSKrescodee (MSKAPI MSK_putlicensecode) (  
    MSKenv_t env,  
    const MSKint32t * code)
```

Input a runtime license code.

Parameters

- env (*MSKenv_t*) – The MOSEK environment. (input)
- code (*MSKint32t**) – A runtime license code. (input)

Return (*MSKrescodee*) – The function response code.

Groups *License system*

MSK_putlicensedebug

```
MSKrescodee (MSKAPI MSK_putlicensedebug) (  
    MSKenv_t env,  
    MSKint32t licdebug)
```

Enables debug information for the license system. If *licdebug* is non-zero, then **MOSEK** will print debug info regarding the license checkout.

Parameters

- env (*MSKenv_t*) – The MOSEK environment. (input)
- licdebug (*MSKint32t*) – Whether license checkout debug info should be printed. (input)

Return (*MSKrescodee*) – The function response code.

Groups *License system*

MSK_putlicensepath

```
MSKrescodee (MSKAPI MSK_putlicensepath) (  
    MSKenv_t env,  
    const char * licensepath)
```

Set the path to the license file.

Parameters

- env (*MSKenv_t*) – The MOSEK environment. (input)

- `licensepath` (*MSKstring_t*) – A path specifying where to search for the license. (input)

Return (*MSKrescodee*) – The function response code.

Groups *License system*

MSK_putlicensewait

```
MSKrescodee (MSKAPI MSK_putlicensewait) (
    MSKenv_t env,
    MSKint32t licwait)
```

Control whether **MOSEK** should wait for an available license if no license is available. If `licwait` is non-zero, then **MOSEK** will wait for `licwait`-1 milliseconds between each check for an available license.

Parameters

- `env` (*MSKenv_t*) – The MOSEK environment. (input)
- `licwait` (*MSKint32t*) – Whether **MOSEK** should wait for a license if no license is available. (input)

Return (*MSKrescodee*) – The function response code.

Groups *License system*

MSK_putmaxnumanz

```
MSKrescodee (MSKAPI MSK_putmaxnumanz) (
    MSKtask_t task,
    MSKint64t maxnumanz)
```

Sets the number of preallocated non-zero entries in A .

MOSEK stores only the non-zero elements in the linear coefficient matrix A and it cannot predict how much storage is required to store A . Using this function it is possible to specify the number of non-zeros to preallocate for storing A .

If the number of non-zeros in the problem is known, it is a good idea to set `maxnumanz` slightly larger than this number, otherwise a rough estimate can be used. In general, if A is inputted in many small chunks, setting this value may speed up the data input phase.

It is not mandatory to call this function, since **MOSEK** will reallocate internal structures whenever it is necessary.

The function call has no effect if both `maxnumcon` and `maxnumvar` are zero.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `maxnumanz` (*MSKint64t*) – Number of preallocated non-zeros in A . (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management, Problem data - semidefinite*

MSK_putmaxnumberbarvar

```
MSKrescodee (MSKAPI MSK_putmaxnumberbarvar) (
    MSKtask_t task,
    MSKint32t maxnumberbarvar)
```

Sets the number of preallocated symmetric matrix variables in the optimization task. When this number of variables is reached **MOSEK** will automatically allocate more space for variables.

It is not mandatory to call this function. It only gives a hint about the amount of data to preallocate for efficiency reasons.

Please note that `maxnumberbarvar` must be larger than the current number of symmetric matrix variables in the task.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumbarvar** (*MSKint32t*) – Number of preallocated symmetric matrix variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management, Problem data - semidefinite*

MSK_putmaxnumcon

```
MSKrescodee (MSKAPI MSK_putmaxnumcon) (  
    MSKtask_t task,  
    MSKint32t maxnumcon)
```

Sets the number of preallocated constraints in the optimization task. When this number of constraints is reached **MOSEK** will automatically allocate more space for constraints.

It is never mandatory to call this function, since **MOSEK** will reallocate any internal structures whenever it is required.

Please note that **maxnumcon** must be larger than the current number of constraints in the task.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumcon** (*MSKint32t*) – Number of preallocated constraints in the optimization task. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management, Problem data - constraints*

MSK_putmaxnumcone

```
MSKrescodee (MSKAPI MSK_putmaxnumcone) (  
    MSKtask_t task,  
    MSKint32t maxnumcone)
```

Sets the number of preallocated conic constraints in the optimization task. When this number of conic constraints is reached **MOSEK** will automatically allocate more space for conic constraints.

It is not mandatory to call this function, since **MOSEK** will reallocate any internal structures whenever it is required.

Please note that **maxnumcon** must be larger than the current number of conic constraints in the task.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumcone** (*MSKint32t*) – Number of preallocated conic constraints in the optimization task. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management, Problem data - cones*

MSK_putmaxnumqnz

```
MSKrescodee (MSKAPI MSK_putmaxnumqnz) (  
    MSKtask_t task,  
    MSKint64t maxnumqnz)
```

Sets the number of preallocated non-zero entries in quadratic terms.

MOSEK stores only the non-zero elements in Q . Therefore, **MOSEK** cannot predict how much storage is required to store Q . Using this function it is possible to specify the number non-zeros to preallocate for storing Q (both objective and constraints).

It may be advantageous to reserve more non-zeros for Q than actually needed since it may improve the internal efficiency of **MOSEK**, however, it is never worthwhile to specify more than the double of the anticipated number of non-zeros in Q .

It is not mandatory to call this function, since **MOSEK** will reallocate internal structures whenever it is necessary.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `maxnumqnz` (*MSKint64t*) – Number of non-zero elements preallocated in quadratic coefficient matrices. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management, Problem data - quadratic part*

MSK_putmaxnumvar

```
MSKrescodee (MSKAPI MSK_putmaxnumvar) (
    MSKtask_t task,
    MSKint32t maxnumvar)
```

Sets the number of preallocated variables in the optimization task. When this number of variables is reached **MOSEK** will automatically allocate more space for variables.

It is not mandatory to call this function. It only gives a hint about the amount of data to preallocate for efficiency reasons.

Please note that `maxnumvar` must be larger than the current number of variables in the task.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `maxnumvar` (*MSKint32t*) – Number of preallocated variables in the optimization task. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management, Problem data - variables*

MSK_putnadoupam

```
MSKrescodee (MSKAPI MSK_putnadoupam) (
    MSKtask_t task,
    const char * paramname,
    MSKrealt parvalue)
```

Sets the value of a named double parameter.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `paramname` (*MSKstring_t*) – Name of a parameter. (input)
- `parvalue` (*MSKrealt*) – Parameter value. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_putnaintparam

```
MSKrescodee (MSKAPI MSK_putnaintparam) (
    MSKtask_t task,
    const char * paramname,
    MSKint32t parvalue)
```

Sets the value of a named integer parameter.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **paramname** (*MSKstring_t*) – Name of a parameter. (input)
- **parvalue** (*MSKint32t*) – Parameter value. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_putnastrparam

```
MSKrescodee (MSKAPI MSK_putnastrparam) (  
    MSKtask_t task,  
    const char * paramname,  
    const char * parvalue)
```

Sets the value of a named string parameter.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **paramname** (*MSKstring_t*) – Name of a parameter. (input)
- **parvalue** (*MSKstring_t*) – Parameter value. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_putobjname

```
MSKrescodee (MSKAPI MSK_putobjname) (  
    MSKtask_t task,  
    const char * objname)
```

Assigns a new name to the objective.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **objname** (*MSKstring_t*) – Name of the objective. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Names, Problem data - objective*

MSK_putobjsense

```
MSKrescodee (MSKAPI MSK_putobjsense) (  
    MSKtask_t task,  
    MSKobjsensee sense)
```

Sets the objective sense of the task.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **sense** (*MSKobjsensee*) – The objective sense of the task. The values *MSK_OBJECTIVE_SENSE_MAXIMIZE* and *MSK_OBJECTIVE_SENSE_MINIMIZE* mean that the problem is maximized or minimized respectively. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - objective*

MSK_putparam

```
MSKrescodee (MSKAPI MSK_putparam) (
    MSKtask_t task,
    const char * parname,
    const char * parvalue)
```

Checks if `parname` is valid parameter name. If it is, the parameter is assigned the value specified by `parvalue`.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `parname` (*MSKstring_t*) – Parameter name. (input)
- `parvalue` (*MSKstring_t*) – Parameter value. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_putqcon

```
MSKrescodee (MSKAPI MSK_putqcon) (
    MSKtask_t task,
    MSKint32t numqcnz,
    const MSKint32t * qcsubk,
    const MSKint32t * qcsubi,
    const MSKint32t * qcsubj,
    const MSKrealt * qcval)
```

Replace all quadratic entries in the constraints. The list of constraints has the form

$$l_k^c \leq \frac{1}{2} \sum_{i=0}^{numvar-1} \sum_{j=0}^{numvar-1} q_{ij}^k x_i x_j + \sum_{j=0}^{numvar-1} a_{kj} x_j \leq u_k^c, \quad k = 0, \dots, m-1.$$

This function sets all the quadratic terms to zero and then performs the update:

$$q_{qcsubi[t], qcsubj[t]}^{qcsubk[t]} = q_{qcsubj[t], qcsubi[t]}^{qcsubk[t]} = q_{qcsubj[t], qcsubi[t]}^{qcsubk[t]} + qcval[t],$$

for $t = 0, \dots, numqcnz - 1$.

Please note that:

- For large problems it is essential for the efficiency that the function *MSK_putmaxnumqcnz* is employed to pre-allocate space.
- Only the lower triangular parts should be specified because the Q matrices are symmetric. Specifying entries where $i < j$ will result in an error.
- Only non-zero elements should be specified.
- The order in which the non-zero elements are specified is insignificant.
- Duplicate elements are added together as shown above. Hence, it is usually not recommended to specify the same entry multiple times.

For a code example see Section *Quadratic Optimization*

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `numqcnz` (*MSKint32t*) – Number of quadratic terms. (input)
- `qcsubk` (*MSKint32t**) – Constraint subscripts for quadratic coefficients. (input)
- `qcsubi` (*MSKint32t**) – Row subscripts for quadratic constraint matrix. (input)
- `qcsubj` (*MSKint32t**) – Column subscripts for quadratic constraint matrix. (input)
- `qcval` (*MSKrealt**) – Quadratic constraint coefficient values. (input)

Return (*MSKrescodee*) – The function response code.

MSK_putqconk

```
MSKrescodee (MSKAPI MSK_putqconk) (
    MSKtask_t task,
    MSKint32t k,
    MSKint32t numqcnz,
    const MSKint32t * qcsubi,
    const MSKint32t * qcsubj,
    const MSKrealt * qcval)
```

Replaces all the quadratic entries in one constraint. This function performs the same operations as *MSK_putqcon* but only with respect to constraint number *k* and it does not modify the other constraints. See the description of *MSK_putqcon* for definitions and important remarks.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *k* (*MSKint32t*) – The constraint in which the new *Q* elements are inserted. (input)
- *numqcnz* (*MSKint32t*) – Number of quadratic terms. (input)
- *qcsubi* (*MSKint32t**) – Row subscripts for quadratic constraint matrix. (input)
- *qcsubj* (*MSKint32t**) – Column subscripts for quadratic constraint matrix. (input)
- *qcval* (*MSKrealt**) – Quadratic constraint coefficient values. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - quadratic part*

MSK_putqobj

```
MSKrescodee (MSKAPI MSK_putqobj) (
    MSKtask_t task,
    MSKint32t numqonz,
    const MSKint32t * qosubi,
    const MSKint32t * qosubj,
    const MSKrealt * qoval)
```

Replace all quadratic terms in the objective. If the objective has the form

$$\frac{1}{2} \sum_{i=0}^{numvar-1} \sum_{j=0}^{numvar-1} q_{ij}^o x_i x_j + \sum_{j=0}^{numvar-1} c_j x_j + c^f$$

then this function sets all the quadratic terms to zero and then performs the update:

$$q_{qosubi[t], qosubj[t]}^o = q_{qosubj[t], qosubi[t]}^o = q_{qosubj[t], qosubi[t]}^o + qoval[t],$$

for $t = 0, \dots, numqonz - 1$.

See the description of *MSK_putqcon* for important remarks and example.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *numqonz* (*MSKint32t*) – Number of non-zero elements in the quadratic objective terms. (input)
- *qosubi* (*MSKint32t**) – Row subscripts for quadratic objective coefficients. (input)
- *qosubj* (*MSKint32t**) – Column subscripts for quadratic objective coefficients. (input)

- `qoval (MSKreal_t*)` – Quadratic objective coefficient values. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Problem data - quadratic part, Problem data - objective*

MSK_putqobjij

```
MSKrescodee (MSKAPI MSK_putqobjij) (
    MSKtask_t task,
    MSKint32t i,
    MSKint32t j,
    MSKreal_t qoij)
```

Replaces one coefficient in the quadratic term in the objective. The function performs the assignment

$$q_{ij}^o = q_{ji}^o = qoij.$$

Only the elements in the lower triangular part are accepted. Setting q_{ij} with $j > i$ will cause an error.

Please note that replacing all quadratic elements one by one is more computationally expensive than replacing them all at once. Use *MSK_putqobj* instead whenever possible.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `i (MSKint32t)` – Row index for the coefficient to be replaced. (input)
- `j (MSKint32t)` – Column index for the coefficient to be replaced. (input)
- `qoij (MSKreal_t)` – The new value for q_{ij}^o . (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - quadratic part, Problem data - objective*

MSK_putresponsefunc

```
MSKrescodee (MSKAPI MSK_putresponsefunc) (
    MSKtask_t task,
    MSKresponsefunc responsefunc,
    MSKuserhandle_t handle)
```

Inputs a user-defined error callback which is called when an error or warning occurs.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `responsefunc (MSKresponsefunc)` – A user-defined response handling function. (input)
- `handle (MSKuserhandle_t)` – A user-defined data structure that is passed to the function `responsefunc` whenever it is called. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Callback, Logging*

MSK_putskc

```
MSKrescodee (MSKAPI MSK_putskc) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const MSKstakeye * skc)
```

Sets the status keys for the constraints.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
 - `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
 - `skc` (*MSKstakeye**) – Status keys for the constraints. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Solution information*

MSK_putskcslice

```
MSKrescodee (MSKAPI MSK_putskcslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    const MSKstakeye * skc)
```

Sets the status keys for a slice of the constraints.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `first` (*MSKint32t*) – First index in the sequence. (input)
- `last` (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- `skc` (*MSKstakeye**) – Status keys for the constraints. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_putskx

```
MSKrescodee (MSKAPI MSK_putskx) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const MSKstakeye * skx)
```

Sets the status keys for the scalar variables.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `skx` (*MSKstakeye**) – Status keys for the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_putskxslice

```
MSKrescodee (MSKAPI MSK_putskxslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    const MSKstakeye * skx)
```

Sets the status keys for a slice of the variables.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `first` (*MSKint32t*) – First index in the sequence. (input)

- last (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- skx (*MSKstakeye**) – Status keys for the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_putslc

```
MSKrescodee (MSKAPI MSK_putslc) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const MSKrealt * slc)
```

Sets the s_l^c vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- slc (*MSKrealt**) – Dual variables corresponding to the lower bounds on the constraints. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_putslcslice

```
MSKrescodee (MSKAPI MSK_putslcslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    const MSKrealt * slc)
```

Sets a slice of the s_l^c vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- first (*MSKint32t*) – First index in the sequence. (input)
- last (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- slc (*MSKrealt**) – Dual variables corresponding to the lower bounds on the constraints. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_putslx

```
MSKrescodee (MSKAPI MSK_putslx) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const MSKrealt * slx)
```

Sets the s_l^x vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- slx (*MSKrealt**) – Dual variables corresponding to the lower bounds on the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_putslxslice

```
MSKrescodee (MSKAPI MSK_putslxslice) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKint32t first,  
    MSKint32t last,  
    const MSKrealt * slx)
```

Sets a slice of the s_l^x vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **slx** (*MSKrealt**) – Dual variables corresponding to the lower bounds on the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_putsnx

```
MSKrescodee (MSKAPI MSK_putsnx) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    const MSKrealt * sux)
```

Sets the s_n^x vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **sux** (*MSKrealt**) – Dual variables corresponding to the upper bounds on the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_putsnxslice

```
MSKrescodee (MSKAPI MSK_putsnxslice) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKint32t first,  
    MSKint32t last,  
    const MSKrealt * snx)
```

Sets a slice of the s_n^x vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)

- `snx (MSKrealt*)` – Dual variables corresponding to the conic constraints on the variables. (input)

Return (`MSKrescodee`) – The function response code.

Groups *Solution - dual*

MSK_putsolution

```
MSKrescodee (MSKAPI MSK_putsolution) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const MSKstakeye * skc,
    const MSKstakeye * skx,
    const MSKstakeye * skn,
    const MSKrealt * xc,
    const MSKrealt * xx,
    const MSKrealt * y,
    const MSKrealt * slc,
    const MSKrealt * suc,
    const MSKrealt * slx,
    const MSKrealt * sux,
    const MSKrealt * snx)
```

Inserts a solution into the task.

Parameters

- `task (MSKtask_t)` – An optimization task. (input)
- `whichsol (MSKsoltypee)` – Selects a solution. (input)
- `skc (MSKstakeye*)` – Status keys for the constraints. (input)
- `skx (MSKstakeye*)` – Status keys for the variables. (input)
- `skn (MSKstakeye*)` – Status keys for the conic constraints. (input)
- `xc (MSKrealt*)` – Primal constraint solution. (input)
- `xx (MSKrealt*)` – Primal variable solution. (input)
- `y (MSKrealt*)` – Vector of dual variables corresponding to the constraints. (input)
- `slc (MSKrealt*)` – Dual variables corresponding to the lower bounds on the constraints. (input)
- `suc (MSKrealt*)` – Dual variables corresponding to the upper bounds on the constraints. (input)
- `slx (MSKrealt*)` – Dual variables corresponding to the lower bounds on the variables. (input)
- `sux (MSKrealt*)` – Dual variables corresponding to the upper bounds on the variables. (input)
- `snx (MSKrealt*)` – Dual variables corresponding to the conic constraints on the variables. (input)

Return (`MSKrescodee`) – The function response code.

Groups *Solution information, Solution - primal, Solution - dual*

MSK_putsolutionyi

```
MSKrescodee (MSKAPI MSK_putsolutionyi) (
    MSKtask_t task,
    MSKint32t i,
    MSKsoltypee whichsol,
    MSKrealt y)
```

Inputs the dual variable of a solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `i` (*MSKint32t*) – Index of the dual variable. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `y` (*MSKrealt*) – Solution value of the dual variable. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information, Solution - dual*

MSK_putstrparam

```
MSKrescodee (MSKAPI MSK_putstrparam) (
    MSKtask_t task,
    MSKsparame param,
    const char * parvalue)
```

Sets the value of a string parameter.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `param` (*MSKsparame*) – Which parameter. (input)
- `parvalue` (*MSKstring_t*) – Parameter value. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_putsuc

```
MSKrescodee (MSKAPI MSK_putsuc) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const MSKrealt * suc)
```

Sets the s_u^c vector for a solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `suc` (*MSKrealt**) – Dual variables corresponding to the upper bounds on the constraints. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_putsucslice

```
MSKrescodee (MSKAPI MSK_putsucslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    const MSKrealt * suc)
```

Sets a slice of the s_u^c vector for a solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `first` (*MSKint32t*) – First index in the sequence. (input)
- `last` (*MSKint32t*) – Last index plus 1 in the sequence. (input)

- `sux` (*MSKrealt**) – Dual variables corresponding to the upper bounds on the constraints. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_putsux

```
MSKrescodee (MSKAPI MSK_putsux) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const MSKrealt * sux)
```

Sets the s_u^x vector for a solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `sux` (*MSKrealt**) – Dual variables corresponding to the upper bounds on the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_putsuxslice

```
MSKrescodee (MSKAPI MSK_putsuxslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    const MSKrealt * sux)
```

Sets a slice of the s_u^x vector for a solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)
- `first` (*MSKint32t*) – First index in the sequence. (input)
- `last` (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- `sux` (*MSKrealt**) – Dual variables corresponding to the upper bounds on the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_puttaskname

```
MSKrescodee (MSKAPI MSK_puttaskname) (
    MSKtask_t task,
    const char * taskname)
```

Assigns a new name to the task.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `taskname` (*MSKstring_t*) – Name assigned to the task. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Environment and task management*

MSK_putvarbound

```
MSKrescodee (MSKAPI MSK_putvarbound) (  
    MSKtask_t task,  
    MSKint32t j,  
    MSKboundkeye bxx,  
    MSKrealt blx,  
    MSKrealt bux)
```

Changes the bounds for one variable.

If the bound value specified is numerically larger than *MSK_DPAR_DATA_TOL_BOUND_INF* it is considered infinite and the bound key is changed accordingly. If a bound value is numerically larger than *MSK_DPAR_DATA_TOL_BOUND_WRN*, a warning will be displayed, but the bound is inputted as specified.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- j (*MSKint32t*) – Index of the variable. (input)
- bxx (*MSKboundkeye*) – New bound key. (input)
- blx (*MSKrealt*) – New lower bound. (input)
- bux (*MSKrealt*) – New upper bound. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - variables, Problem data - bounds*

MSK_putvarboundlist

```
MSKrescodee (MSKAPI MSK_putvarboundlist) (  
    MSKtask_t task,  
    MSKint32t num,  
    const MSKint32t * sub,  
    const MSKboundkeye * bxx,  
    const MSKrealt * blx,  
    const MSKrealt * bux)
```

Changes the bounds for one or more variables. If multiple bound changes are specified for a variable, then only the last change takes effect. Data checks are performed as in *MSK_putvarbound*.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- num (*MSKint32t*) – Number of bounds that should be changed. (input)
- sub (*MSKint32t**) – List of variable indexes. (input)
- bxx (*MSKboundkeye**) – Bound keys for the variables. (input)
- blx (*MSKrealt**) – Lower bounds for the variables. (input)
- bux (*MSKrealt**) – Upper bounds for the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - variables, Problem data - bounds*

MSK_putvarboundlistconst

```
MSKrescodee (MSKAPI MSK_putvarboundlistconst) (  
    MSKtask_t task,  
    MSKint32t num,  
    const MSKint32t * sub,  
    MSKboundkeye bxx,  
    MSKrealt blx,  
    MSKrealt bux)
```

Changes the bounds for one or more variables. Data checks are performed as in *MSK_putvarbound*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint32t*) – Number of bounds that should be changed. (input)
- **sub** (*MSKint32t**) – List of variable indexes. (input)
- **bkx** (*MSKboundkeye*) – New bound key for all variables in the list. (input)
- **blx** (*MSKrealt*) – New lower bound for all variables in the list. (input)
- **bux** (*MSKrealt*) – New upper bound for all variables in the list. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - variables, Problem data - bounds*

MSK_putvarboundslice

```
MSKrescodee (MSKAPI MSK_putvarboundslice) (  
    MSKtask_t task,  
    MSKint32t first,  
    MSKint32t last,  
    const MSKboundkeye * bkx,  
    const MSKrealt * blx,  
    const MSKrealt * bux)
```

Changes the bounds for a slice of the variables. Data checks are performed as in *MSK_putvarbound*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **bkx** (*MSKboundkeye**) – Bound keys for the variables. (input)
- **blx** (*MSKrealt**) – Lower bounds for the variables. (input)
- **bux** (*MSKrealt**) – Upper bounds for the variables. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - variables, Problem data - bounds*

MSK_putvarboundsliceconst

```
MSKrescodee (MSKAPI MSK_putvarboundsliceconst) (  
    MSKtask_t task,  
    MSKint32t first,  
    MSKint32t last,  
    MSKboundkeye bkx,  
    MSKrealt blx,  
    MSKrealt bux)
```

Changes the bounds for a slice of the variables. Data checks are performed as in *MSK_putvarbound*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **bkx** (*MSKboundkeye*) – New bound key for all variables in the slice. (input)
- **blx** (*MSKrealt*) – New lower bound for all variables in the slice. (input)
- **bux** (*MSKrealt*) – New upper bound for all variables in the slice. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - linear part, Problem data - variables, Problem data - bounds*

MSK_putvarname

```
MSKrescodee (MSKAPI MSK_putvarname) (  
    MSKtask_t task,  
    MSKint32t j,  
    const char * name)
```

Sets the name of a variable.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **j** (*MSKint32t*) – Index of the variable. (input)
- **name** (*MSKstring_t*) – The variable name. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Names, Problem data - variables, Problem data - linear part*

MSK_putvarsolutionj

```
MSKrescodee (MSKAPI MSK_putvarsolutionj) (  
    MSKtask_t task,  
    MSKint32t j,  
    MSKsoltypee whichsol,  
    MSKstakeye sk,  
    MSKrealt x,  
    MSKrealt sl,  
    MSKrealt su,  
    MSKrealt sn)
```

Sets the primal and dual solution information for a single variable.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **j** (*MSKint32t*) – Index of the variable. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **sk** (*MSKstakeye*) – Status key of the variable. (input)
- **x** (*MSKrealt*) – Primal solution value of the variable. (input)
- **sl** (*MSKrealt*) – Solution value of the dual variable associated with the lower bound. (input)
- **su** (*MSKrealt*) – Solution value of the dual variable associated with the upper bound. (input)
- **sn** (*MSKrealt*) – Solution value of the dual variable associated with the conic constraint. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information, Solution - primal, Solution - dual*

MSK_putvartype

```
MSKrescodee (MSKAPI MSK_putvartype) (  
    MSKtask_t task,  
    MSKint32t j,  
    MSKvariabletypee vartype)
```

Sets the variable type of one variable.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **j** (*MSKint32t*) – Index of the variable. (input)

- **vartype** (*MSKvariabletypee*) – The new variable type. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Problem data - variables*

MSK_putvartypelist

```
MSKrescodee (MSKAPI MSK_putvartypelist) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * subj,
    const MSKvariabletypee * vartype)
```

Sets the variable type for one or more variables. If the same index is specified multiple times in subj only the last entry takes effect.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint32t*) – Number of variables for which the variable type should be set. (input)
- **subj** (*MSKint32t**) – A list of variable indexes for which the variable type should be changed. (input)
- **vartype** (*MSKvariabletypee**) – A list of variable types that should be assigned to the variables specified by subj. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - variables*

MSK_putxc

```
MSKrescodee (MSKAPI MSK_putxc) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKrealt * xc)
```

Sets the x^c vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **xc** (*MSKrealt**) – Primal constraint solution. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - primal*

MSK_putxcslice

```
MSKrescodee (MSKAPI MSK_putxcslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    const MSKrealt * xc)
```

Sets a slice of the x^c vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)

- last (*MSKint32t*) – Last index plus 1 in the sequence. (input)
 - xc (*MSKrealt**) – Primal constraint solution. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Solution - primal*

MSK_putxx

```
MSKrescodee (MSKAPI MSK_putxx) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const MSKrealt * xx)
```

Sets the x^x vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
 - whichsol (*MSKsoltypee*) – Selects a solution. (input)
 - xx (*MSKrealt**) – Primal variable solution. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Solution - primal*

MSK_putxxslice

```
MSKrescodee (MSKAPI MSK_putxxslice) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKint32t first,
    MSKint32t last,
    const MSKrealt * xx)
```

Sets a slice of the x^x vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
 - whichsol (*MSKsoltypee*) – Selects a solution. (input)
 - first (*MSKint32t*) – First index in the sequence. (input)
 - last (*MSKint32t*) – Last index plus 1 in the sequence. (input)
 - xx (*MSKrealt**) – Primal variable solution. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Solution - primal*

MSK_puty

```
MSKrescodee (MSKAPI MSK_puty) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const MSKrealt * y)
```

Sets the y vector for a solution.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
 - whichsol (*MSKsoltypee*) – Selects a solution. (input)
 - y (*MSKrealt**) – Vector of dual variables corresponding to the constraints. (input)
- Return** (*MSKrescodee*) – The function response code.

Groups *Solution - primal*

MSK_putyslice

```
MSKrescodee (MSKAPI MSK_putyslice) (  
    MSKtask_t task,  
    MSKsoltypee whichsol,  
    MSKint32t first,  
    MSKint32t last,  
    const MSKrealt * y)
```

Sets a slice of the y vector for a solution.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **first** (*MSKint32t*) – First index in the sequence. (input)
- **last** (*MSKint32t*) – Last index plus 1 in the sequence. (input)
- **y** (*MSKrealt**) – Vector of dual variables corresponding to the constraints. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Solution - dual*

MSK_readdata

```
MSKrescodee (MSKAPI MSK_readdata) (  
    MSKtask_t task,  
    const char * filename)
```

Reads an optimization problem and associated data from a file. The extension of the file name is used to deduce the file format.

For a list of supported file types and their extensions see *Supported File Formats*.

Data is read from the file **filename** if it is a nonempty string. Otherwise data is read from the file specified by *MSK_SPAR_DATA_FILE_NAME*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **filename** (*MSKstring_t*) – A valid file name. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

MSK_readdataautoformat

```
MSKrescodee (MSKAPI MSK_readdataautoformat) (  
    MSKtask_t task,  
    const char * filename)
```

Reads an optimization problem and associated data from a file.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **filename** (*MSKstring_t*) – A valid file name. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

MSK_readdataformat

```
MSKrescodee (MSKAPI MSK_readdataformat) (
    MSKtask_t task,
    const char * filename,
    int format,
    int compress)
```

Reads an optimization problem and associated data from a file.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **filename** (*MSKstring_t*) – A valid file name. (input)
- **format** (*MSKdataformat_e*) – File data format. (input)
- **compress** (*MSKcompress_type_e*) – File compression type. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

MSK_readjsonstring

```
MSKrescodee (MSKAPI MSK_readjsonstring) (
    MSKtask_t task,
    const char * data)
```

Load task data from a JSON string, replacing any data that already exists in the task object. All problem data, parameters and other settings are resorted, but if the string contains solutions, the solution status after loading a file is set to unknown, even if it is optimal or otherwise well-defined.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **data** (*MSKstring_t*) – Problem data in text format. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

MSK_readlpstring

```
MSKrescodee (MSKAPI MSK_readlpstring) (
    MSKtask_t task,
    const char * data)
```

Load task data from a string in LP format, replacing any data that already exists in the task object.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **data** (*MSKstring_t*) – Problem data in text format. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

MSK_readopfstring

```
MSKrescodee (MSKAPI MSK_readopfstring) (
    MSKtask_t task,
    const char * data)
```

Load task data from a string in OPF format, replacing any data that already exists in the task object.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
 - **data** (*MSKstring_t*) – Problem data in text format. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Input/Output*

MSK_readparamfile

```
MSKrescodee (MSKAPI MSK_readparamfile) (
    MSKtask_t task,
    const char * filename)
```

Reads **MOSEK** parameters from a file. Data is read from the file **filename** if it is a nonempty string. Otherwise data is read from the file specified by *MSK_SPAR_PARAM_READ_FILE_NAME*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
 - **filename** (*MSKstring_t*) – A valid file name. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Input/Output*

MSK_readptfstring

```
MSKrescodee (MSKAPI MSK_readptfstring) (
    MSKtask_t task,
    const char * data)
```

Load task data from a PTF string, replacing any data that already exists in the task object. All problem data, parameters and other settings are resorted, but if the string contains solutions, the solution status after loading a file is set to unknown, even if it is optimal or otherwise well-defined.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
 - **data** (*MSKstring_t*) – Problem data in text format. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Input/Output*

MSK_readsolution

```
MSKrescodee (MSKAPI MSK_readsolution) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const char * filename)
```

Reads a solution file and inserts it as a specified solution in the task. Data is read from the file **filename** if it is a nonempty string. Otherwise data is read from one of the files specified by *MSK_SPAR_BAS_SOL_FILE_NAME*, *MSK_SPAR_ITR_SOL_FILE_NAME* or *MSK_SPAR_INT_SOL_FILE_NAME* depending on which solution is chosen.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
 - **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
 - **filename** (*MSKstring_t*) – A valid file name. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Input/Output*

MSK_readsummary

```
MSKrescodee (MSKAPI MSK_readsummary) (
    MSKtask_t task,
    MSKstreamtypee whichstream)
```

Prints a short summary of last file that was read.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichstream** (*MSKstreamtypee*) – Index of the stream. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output, Inspecting the task*

MSK_readtask

```
MSKrescodee (MSKAPI MSK_readtask) (
    MSKtask_t task,
    const char * filename)
```

Load task data from a file, replacing any data that already exists in the task object. All problem data, parameters and other settings are resorted, but if the file contains solutions, the solution status after loading a file is set to unknown, even if it was optimal or otherwise well-defined when the file was dumped.

See section *The Task Format* for a description of the Task format.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **filename** (*MSKstring_t*) – A valid file name. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

MSK_removebarvars

```
MSKrescodee (MSKAPI MSK_removebarvars) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * subset)
```

The function removes a subset of the symmetric matrices from the optimization task. This implies that the remaining symmetric matrices are renumbered.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **num** (*MSKint32t*) – Number of symmetric matrices which should be removed. (input)
- **subset** (*MSKint32t**) – Indexes of symmetric matrices which should be removed. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - semidefinite*

MSK_removecones

```
MSKrescodee (MSKAPI MSK_removecones) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * subset)
```

Removes a number of conic constraints from the problem. This implies that the remaining conic constraints are renumbered. In general, it is much more efficient to remove a cone with a high index than a low index.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of cones which should be removed. (input)
- `subset` (*MSKint32t**) – Indexes of cones which should be removed. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - cones*

MSK_removecons

```
MSKrescodee (MSKAPI MSK_removecons) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * subset)
```

The function removes a subset of the constraints from the optimization task. This implies that the remaining constraints are renumbered.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of constraints which should be removed. (input)
- `subset` (*MSKint32t**) – Indexes of constraints which should be removed. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - constraints, Problem data - linear part*

MSK_removevars

```
MSKrescodee (MSKAPI MSK_removevars) (
    MSKtask_t task,
    MSKint32t num,
    const MSKint32t * subset)
```

The function removes a subset of the variables from the optimization task. This implies that the remaining variables are renumbered.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `num` (*MSKint32t*) – Number of variables which should be removed. (input)
- `subset` (*MSKint32t**) – Indexes of variables which should be removed. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - variables, Problem data - linear part*

MSK_resizetask

```
MSKrescodee (MSKAPI MSK_resizetask) (
    MSKtask_t task,
    MSKint32t maxnumcon,
    MSKint32t maxnumvar,
    MSKint32t maxnumcone,
    MSKint64t maxnumanz,
    MSKint64t maxnumqnz)
```

Sets the amount of preallocated space assigned for each type of data in an optimization task.

It is never mandatory to call this function, since it only gives a hint about the amount of data to preallocate for efficiency reasons.

Please note that the procedure is **destructive** in the sense that all existing data stored in the task is destroyed.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **maxnumcon** (*MSKint32t*) – New maximum number of constraints. (input)
- **maxnumvar** (*MSKint32t*) – New maximum number of variables. (input)
- **maxnumcone** (*MSKint32t*) – New maximum number of cones. (input)
- **maxnumanz** (*MSKint64t*) – New maximum number of non-zeros in A . (input)
- **maxnumqnz** (*MSKint64t*) – New maximum number of non-zeros in all Q matrices. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Environment and task management*

MSK_sensitivityreport

```
MSKrescodee (MSKAPI MSK_sensitivityreport) (
    MSKtask_t task,
    MSKstreamtypee whichstream)
```

Reads a sensitivity format file from a location given by *MSK_SPAR_SENSITIVITY_FILE_NAME* and writes the result to the stream **whichstream**. If *MSK_SPAR_SENSITIVITY_RES_FILE_NAME* is set to a non-empty string, then the sensitivity report is also written to a file of this name.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichstream** (*MSKstreamtypee*) – Index of the stream. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Sensitivity analysis*

MSK_setdefaults

```
MSKrescodee (MSKAPI MSK_setdefaults) (
    MSKtask_t task)
```

Resets all the parameters to their default values.

Parameters **task** (*MSKtask_t*) – An optimization task. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters*

MSK_setupthreads

```
MSKrescodee (MSKAPI MSK_setupthreads) (
    MSKenv_t env,
    MSKint32t numthreads)
```

Preallocates a thread pool for the interior-point and conic optimizers in the current process. This function should only be called once per process, before first optimization. Future settings of the parameter *MSK_IPAR_NUM_THREADS* will be irrelevant for the conic optimizer.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)

- numthreads (*MSKint32t*) – Number of threads. (input)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *System, memory and debugging*

MSK_sktostr

```
MSKrescodee (MSKAPI MSK_sktostr) (
    MSKtask_t task,
    MSKstakeye sk,
    char * str)
```

Obtains a status key abbreviation string, one of UN, BS, SB, LL, UL, EQ, **.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- sk (*MSKstakeye*) – A valid status key. (input)
- str (*MSKstring_t*) – Abbreviation string corresponding to the status key sk. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names*

MSK_solstatostr

```
MSKrescodee (MSKAPI MSK_solstatostr) (
    MSKtask_t task,
    MSKsolstae solsta,
    char * str)
```

Obtains an explanatory string corresponding to a solution status.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- solsta (*MSKsolstae*) – Solution status. (input)
- str (*MSKstring_t*) – String corresponding to the solution status solsta. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Names*

MSK_solutiondef

```
MSKrescodee (MSKAPI MSK_solutiondef) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    MSKboolean * isdef)
```

Checks whether a solution is defined.

Parameters

- task (*MSKtask_t*) – An optimization task. (input)
- whichsol (*MSKsoltypee*) – Selects a solution. (input)
- isdef (*MSKboolean by reference*) – Is non-zero if the requested solution is defined. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Solution information*

MSK_solutionsummary


```
MSKrescodee (MSKAPI MSK_solutionssummary) (
    MSKtask_t task,
    MSKstreamtypee whichstream)
```

Prints a short summary of the current solutions.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichstream** (*MSKstreamtypee*) – Index of the stream. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging, Solution information*

MSK_solvewithbasis

```
MSKrescodee (MSKAPI MSK_solvewithbasis) (
    MSKtask_t task,
    MSKint32t transp,
    MSKint32t * numnz,
    MSKint32t * sub,
    MSKrealt * val)
```

If a basic solution is available, then exactly *numcon* basis variables are defined. These *numcon* basis variables are denoted the basis. Associated with the basis is a basis matrix denoted B . This function solves either the linear equation system

$$B\bar{X} = b \quad (15.3)$$

or the system

$$B^T\bar{X} = b \quad (15.4)$$

for the unknowns \bar{X} , with b being a user-defined vector. In order to make sense of the solution \bar{X} it is important to know the ordering of the variables in the basis because the ordering specifies how B is constructed. When calling *MSK_initbasissolve* an ordering of the basis variables is obtained, which can be used to deduce how **MOSEK** has constructed B . Indeed if the k -th basis variable is variable x_j it implies that

$$B_{i,k} = A_{i,j}, \quad i = 0, \dots, \text{numcon} - 1.$$

Otherwise if the k -th basis variable is variable x_j^c it implies that

$$B_{i,k} = \begin{cases} -1, & i = j, \\ 0, & i \neq j. \end{cases}$$

The function *MSK_initbasissolve* must be called before a call to this function. Please note that this function exploits the sparsity in the vector b to speed up the computations.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **transp** (*MSKint32t*) – If this argument is zero, then (15.3) is solved, if non-zero then (15.4) is solved. (input)
- **numnz** (*MSKint32t by reference*) – As input it is the number of non-zeros in b . As output it is the number of non-zeros in \bar{X} . (input/output)
- **sub** (*MSKint32t**) – As input it contains the positions of non-zeros in b . As output it contains the positions of the non-zeros in \bar{X} . It must have room for *numcon* elements. (input/output)
- **val** (*MSKrealt**) – As input it is the vector b as a dense vector (although the positions of non-zeros are specified in **sub** it is required that $\text{val}[i] = 0$ when $b[i] = 0$). As output **val** is the vector \bar{X} as a dense vector. It must have length *numcon*. (input/output)

Return (*MSKrescodee*) – The function response code.

Groups *Solving systems with basis matrix*

MSK_sparsetriangularsolvedense

```
MSKrescodee (MSKAPI MSK_sparsetriangularsolvedense) (  
    MSKenv_t env,  
    MSKtransposee transposed,  
    MSKint32t n,  
    const MSKint32t * lnzc,  
    const MSKint64t * lptrc,  
    MSKint64t lensubnval,  
    const MSKint32t * lsubc,  
    const MSKrealt * lvalc,  
    MSKrealt * b)
```

The function solves a triangular system of the form

$$Lx = b$$

or

$$L^T x = b$$

where L is a sparse lower triangular nonsingular matrix. This implies in particular that diagonals in L are nonzero.

Parameters

- *env* (*MSKenv_t*) – The MOSEK environment. (input)
- *transposed* (*MSKtransposee*) – Controls whether to use with L or L^T . (input)
- *n* (*MSKint32t*) – Dimension of L . (input)
- *lnzc* (*MSKint32t**) – *lnzc[j]* is the number of nonzeros in column j . (input)
- *lptrc* (*MSKint64t**) – *lptrc[j]* is a pointer to the first row index and value in column j . (input)
- *lensubnval* (*MSKint64t*) – Number of elements in *lsubc* and *lvalc*. (input)
- *lsubc* (*MSKint32t**) – Row indexes for each column stored sequentially. Must be stored in increasing order for each column. (input)
- *lvalc* (*MSKrealt**) – The value corresponding to the row index stored in *lsubc*. (input)
- *b* (*MSKrealt**) – The right-hand side of linear equation system to be solved as a dense vector. (input/output)

Return (*MSKrescodee*) – The function response code.

Groups *Linear algebra*

MSK_strdupbgtask

```
char * (MSKAPI MSK_strdupbgtask) (  
    MSKtask_t task,  
    const char * str,  
    const char * file,  
    const unsigned line)
```

Make a copy of a string. The string created by this procedure must be freed by *MSK_freetask*.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *str* (*MSKstring_t*) – String that should be copied. (input)
- *file* (*MSKstring_t*) – File from which the function is called. (input)

- **line (unsigned)** – Line in the file from which the function is called. (input)
- Return** (*MSKstring_t*) – A copy of the given string.
- Groups** *System, memory and debugging*

MSK_strduptask

```
char * (MSKAPI MSK_strduptask) (
    MSKtask_t task,
    const char * str)
```

Make a copy of a string. The string created by this procedure must be freed by *MSK_freetask*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
 - **str** (*MSKstring_t*) – String that should be copied. (input)
- Return** (*MSKstring_t*) – A copy of the given string.
- Groups** *System, memory and debugging*

MSK_strtoconetype

```
MSKrescodee (MSKAPI MSK_strtoconetype) (
    MSKtask_t task,
    const char * str,
    MSKconetype * conetype)
```

Obtains cone type code corresponding to a cone type string.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
 - **str** (*MSKstring_t*) – String corresponding to the cone type code **conetype**. (input)
 - **conetype** (*MSKconetype by reference*) – The cone type corresponding to the string **str**. (output)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Names*

MSK_strtosk

```
MSKrescodee (MSKAPI MSK_strtosk) (
    MSKtask_t task,
    const char * str,
    MSKstakeye * sk)
```

Obtains the status key corresponding to an abbreviation string.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
 - **str** (*MSKstring_t*) – A status key abbreviation string. (input)
 - **sk** (*MSKstakeye by reference*) – Status key corresponding to the string. (output)
- Return** (*MSKrescodee*) – The function response code.
- Groups** *Names*

MSK_syeig

```

MSKrescodee (MSKAPI MSK_syeig) (
    MSKenv_t env,
    MSKuploe uplo,
    MSKint32t n,
    const MSKrealt * a,
    MSKrealt * w)

```

Computes all eigenvalues of a real symmetric matrix A . Given a matrix $A \in \mathbb{R}^{n \times n}$ it returns a vector $w \in \mathbb{R}^n$ containing the eigenvalues of A .

Parameters

- `env` (*MSKenv_t*) – The MOSEK environment. (input)
- `uplo` (*MSKuploe*) – Indicates whether the upper or lower triangular part is used. (input)
- `n` (*MSKint32t*) – Dimension of the symmetric input matrix. (input)
- `a` (*MSKrealt**) – A symmetric matrix A stored in column-major order. Only the part indicated by `uplo` is used. (input)
- `w` (*MSKrealt**) – Array of length at least `n` containing the eigenvalues of A . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Linear algebra*

MSK_syevd

```

MSKrescodee (MSKAPI MSK_syevd) (
    MSKenv_t env,
    MSKuploe uplo,
    MSKint32t n,
    MSKrealt * a,
    MSKrealt * w)

```

Computes all the eigenvalues and eigenvectors a real symmetric matrix. Given the input matrix $A \in \mathbb{R}^{n \times n}$, this function returns a vector $w \in \mathbb{R}^n$ containing the eigenvalues of A and it also computes the eigenvectors of A . Therefore, this function computes the eigenvalue decomposition of A as

$$A = UVU^T,$$

where $V = \text{diag}(w)$ and U contains the eigenvectors of A .

Note that the matrix U overwrites the input data A .

Parameters

- `env` (*MSKenv_t*) – The MOSEK environment. (input)
- `uplo` (*MSKuploe*) – Indicates whether the upper or lower triangular part is used. (input)
- `n` (*MSKint32t*) – Dimension of the symmetric input matrix. (input)
- `a` (*MSKrealt**) – A symmetric matrix A stored in column-major order. Only the part indicated by `uplo` is used. On exit it will be overwritten by the matrix U . (input/output)
- `w` (*MSKrealt**) – Array of length at least `n` containing the eigenvalues of A . (output)

Return (*MSKrescodee*) – The function response code.

Groups *Linear algebra*

MSK_symnamtovalue

```
MSKboolean (MSKAPI MSK_symnamtovalue) (
    const char * name,
    char * value)
```

Obtains the value corresponding to a symbolic name defined by **MOSEK**.

Parameters

- **name** (*MSKstring_t*) – Symbolic name. (input)
- **value** (*MSKstring_t*) – The corresponding value. (output)

Return (*MSKboolean*) – Indicates if the symbolic name has been converted.

Groups *Parameters*

MSK_syrk

```
MSKrescodee (MSKAPI MSK_syrk) (
    MSKenv_t env,
    MSKuploe uplo,
    MSKtransposee trans,
    MSKint32t n,
    MSKint32t k,
    MSKrealt alpha,
    const MSKrealt * a,
    MSKrealt beta,
    MSKrealt * c)
```

Performs a symmetric rank- k update for a symmetric matrix.

Given a symmetric matrix $C \in \mathbb{R}^{n \times n}$, two scalars α, β and a matrix A of rank $k \leq n$, it computes either

$$C := \alpha AA^T + \beta C,$$

when **trans** is set to *MSK_TRANSPOSE_NO* and $A \in \mathbb{R}^{n \times k}$, or

$$C := \alpha A^T A + \beta C,$$

when **trans** is set to *MSK_TRANSPOSE_YES* and $A \in \mathbb{R}^{k \times n}$.

Only the part of C indicated by **uplo** is used and only that part is updated with the result.

Parameters

- **env** (*MSKenv_t*) – The MOSEK environment. (input)
- **uplo** (*MSKuploe*) – Indicates whether the upper or lower triangular part of C is used. (input)
- **trans** (*MSKtransposee*) – Indicates whether the matrix A must be transposed. (input)
- **n** (*MSKint32t*) – Specifies the order of C . (input)
- **k** (*MSKint32t*) – Indicates the number of rows or columns of A , depending on whether or not it is transposed, and its rank. (input)
- **alpha** (*MSKrealt*) – A scalar value multiplying the result of the matrix multiplication. (input)
- **a** (*MSKrealt**) – The pointer to the array storing matrix A in a column-major format. (input)
- **beta** (*MSKrealt*) – A scalar value that multiplies C . (input)
- **c** (*MSKrealt**) – The pointer to the array storing matrix C in a column-major format. (input/output)

Return (*MSKrescodee*) – The function response code.

Groups *Linear algebra*

MSK_toconic

```
MSKrescodee (MSKAPI MSK_toconic) (  
    MSKtask_t task)
```

This function tries to reformulate a given Quadratically Constrained Quadratic Optimization problem (QCQP) as a Conic Quadratic Optimization problem (CQO). The first step of the reformulation is to convert the quadratic term of the objective function, if any, into a constraint. Then the following steps are repeated for each quadratic constraint:

- a conic constraint is added along with a suitable number of auxiliary variables and constraints;
- the original quadratic constraint is not removed, but all its coefficients are zeroed out.

Note that the reformulation preserves all the original variables.

The conversion is performed in-place, i.e. the task passed as argument is modified on exit. That also means that if the reformulation fails, i.e. the given QCQP is not representable as a CQO, then the task has an undefined state. In some cases, users may want to clone the task to ensure a clean copy is preserved.

Parameters *task* (*MSKtask_t*) – An optimization task. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Problem data - quadratic part*

MSK_unlinkfuncfromenvstream

```
MSKrescodee (MSKAPI MSK_unlinkfuncfromenvstream) (  
    MSKenv_t env,  
    MSKstreamtypee whichstream)
```

Disconnects a user-defined function from a stream.

Parameters

- *env* (*MSKenv_t*) – The MOSEK environment. (input)
- *whichstream* (*MSKstreamtypee*) – Index of the stream. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging, Callback*

MSK_unlinkfuncfromtaskstream

```
MSKrescodee (MSKAPI MSK_unlinkfuncfromtaskstream) (  
    MSKtask_t task,  
    MSKstreamtypee whichstream)
```

Disconnects a user-defined function from a task stream.

Parameters

- *task* (*MSKtask_t*) – An optimization task. (input)
- *whichstream* (*MSKstreamtypee*) – Index of the stream. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Logging, Callback*

MSK_updatesolutioninfo

```
MSKrescodee (MSKAPI MSK_updatesolutioninfo) (  
    MSKtask_t task,  
    MSKsoltypee whichsol)
```

Update the information items related to the solution.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `whichsol` (*MSKsoltypee*) – Selects a solution. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Information items and statistics*

MSK_utf8towchar

```
MSKrescodee (MSKAPI MSK_utf8towchar) (  
    const size_t outputlen,  
    size_t * len,  
    size_t * conv,  
    MSKwchart * output,  
    const char * input)
```

Converts an UTF8 string to a *MSKwchart* string.

Parameters

- `outputlen` (*size_t*) – The length of the output buffer. (input)
- `len` (*size_t**) – The length of the string contained in the output buffer. (output)
- `conv` (*size_t**) – Returns the number of characters converted, i.e. `input[conv]` is the first character which was not converted. If the whole string was converted, then `input[conv]=0`. (output)
- `output` (*MSKwchart**) – The input string converted to a *MSKwchart* string. (output)
- `input` (*MSKstring_t*) – The UTF8 input string. (input)

Return (*MSKrescodee*) – The function response code.

Groups *System, memory and debugging*

MSK_wchartoutf8

```
MSKrescodee (MSKAPI MSK_wchartoutf8) (  
    const size_t outputlen,  
    size_t * len,  
    size_t * conv,  
    char * output,  
    const MSKwchart * input)
```

Converts a *MSKwchart* string to an UTF8 string.

Parameters

- `outputlen` (*size_t*) – The length of the output buffer. (input)
- `len` (*size_t**) – The length of the string contained in the output buffer. (output)
- `conv` (*size_t**) – Returns the number of characters from converted, i.e. `input[conv]` is the first char which was not converted. If the whole string was converted, then `input[conv]=0`. (output)
- `output` (*MSKstring_t*) – The input string converted to a UTF8 string. (output)
- `input` (*MSKwchart**) – The *MSKwchart* input string. (input)

Return (*MSKrescodee*) – The function response code.

Groups *System, memory and debugging*

MSK_whichparam

```
MSKrescodee (MSKAPI MSK_whichparam) (
    MSKtask_t task,
    const char * parname,
    MSKparametertypee * partye,
    MSKint32t * param)
```

Checks if `parname` is a valid parameter name. If yes then `partye` and `param` denote the type and the index of the parameter, respectively.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `parname` (*MSKstring_t*) – Parameter name. (input)
- `partye` (*MSKparametertypee by reference*) – Parameter type. (output)
- `param` (*MSKint32t by reference*) – Which parameter. (output)

Return (*MSKrescodee*) – The function response code.

Groups *Parameters, Names*

MSK_writedata

```
MSKrescodee (MSKAPI MSK_writedata) (
    MSKtask_t task,
    const char * filename)
```

Writes problem data associated with the optimization task to a file in one of the supported formats. See Section *Supported File Formats* for the complete list.

The data file format is determined by the file name extension. To write in compressed format append the extension `.gz`. E.g to write a gzip compressed MPS file use the extension `mps.gz`.

Please note that MPS, LP and OPF files require all variables to have unique names. If a task contains no names, it is possible to write the file with automatically generated anonymous names by setting the *MSK_IPAR_WRITE_GENERIC_NAMES* parameter to *MSK_ON*.

Data is written to the file `filename` if it is a nonempty string. Otherwise data is written to the file specified by *MSK_SPAR_DATA_FILE_NAME*.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `filename` (*MSKstring_t*) – A valid file name. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

MSK_writejsonsol

```
MSKrescodee (MSKAPI MSK_writejsonsol) (
    MSKtask_t task,
    const char * filename)
```

Saves the current solutions and solver information items in a JSON file.

Parameters

- `task` (*MSKtask_t*) – An optimization task. (input)
- `filename` (*MSKstring_t*) – A valid file name. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

MSK_writeparamfile


```
MSKrescodee (MSKAPI MSK_writeparamfile) (
    MSKtask_t task,
    const char * filename)
```

Writes all the parameters to a parameter file.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **filename** (*MSKstring_t*) – A valid file name. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output, Parameters*

MSK_writesolution

```
MSKrescodee (MSKAPI MSK_writesolution) (
    MSKtask_t task,
    MSKsoltypee whichsol,
    const char * filename)
```

Saves the current basic, interior-point, or integer solution to a file.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **whichsol** (*MSKsoltypee*) – Selects a solution. (input)
- **filename** (*MSKstring_t*) – A valid file name. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

MSK_writetask

```
MSKrescodee (MSKAPI MSK_writetask) (
    MSKtask_t task,
    const char * filename)
```

Write a binary dump of the task data. This format saves all problem data, coefficients and parameter settings. See section *The Task Format* for a description of the Task format.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **filename** (*MSKstring_t*) – A valid file name. (input)

Return (*MSKrescodee*) – The function response code.

Groups *Input/Output*

15.4 Parameters grouped by topic

Analysis

- *MSK_DPAR_ANA_SOL_INFEAS_TOL*
- *MSK_IPAR_ANA_SOL_BASIS*
- *MSK_IPAR_ANA_SOL_PRINT_VIOLATED*
- *MSK_IPAR_LOG_ANA_PRO*

Basis identification

- *MSK_DPAR_SIM_LU_TOL_REL_PIV*
- *MSK_IPAR_BI_CLEAN_OPTIMIZER*
- *MSK_IPAR_BI_IGNORE_MAX_ITER*
- *MSK_IPAR_BI_IGNORE_NUM_ERROR*
- *MSK_IPAR_BI_MAX_ITERATIONS*
- *MSK_IPAR_INTPNT_BASIS*
- *MSK_IPAR_LOG_BI*
- *MSK_IPAR_LOG_BI_FREQ*

Conic interior-point method

- *MSK_DPAR_INTPNT_CO_TOL_DFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_INFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_MU_RED*
- *MSK_DPAR_INTPNT_CO_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_CO_TOL_PFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_REL_GAP*

Data check

- *MSK_DPAR_DATA_SYM_MAT_TOL*
- *MSK_DPAR_DATA_SYM_MAT_TOL_HUGE*
- *MSK_DPAR_DATA_SYM_MAT_TOL_LARGE*
- *MSK_DPAR_DATA_TOL_AIJ_HUGE*
- *MSK_DPAR_DATA_TOL_AIJ_LARGE*
- *MSK_DPAR_DATA_TOL_BOUND_INF*
- *MSK_DPAR_DATA_TOL_BOUND_WRN*
- *MSK_DPAR_DATA_TOL_C_HUGE*
- *MSK_DPAR_DATA_TOL_CJ_LARGE*
- *MSK_DPAR_DATA_TOL_QIJ*
- *MSK_DPAR_DATA_TOL_X*
- *MSK_DPAR_SEMIDEFINITE_TOL_APPROX*
- *MSK_IPAR_CHECK_CONVEXITY*
- *MSK_IPAR_LOG_CHECK_CONVEXITY*

Data input/output

- *MSK_IPAR_INFEAS_REPORT_AUTO*
- *MSK_IPAR_LOG_FILE*
- *MSK_IPAR_OPF_WRITE_HEADER*
- *MSK_IPAR_OPF_WRITE_HINTS*
- *MSK_IPAR_OPF_WRITE_LINE_LENGTH*
- *MSK_IPAR_OPF_WRITE_PARAMETERS*
- *MSK_IPAR_OPF_WRITE_PROBLEM*
- *MSK_IPAR_OPF_WRITE_SOL_BAS*
- *MSK_IPAR_OPF_WRITE_SOL_ITG*
- *MSK_IPAR_OPF_WRITE_SOL_ITR*
- *MSK_IPAR_OPF_WRITE_SOLUTIONS*
- *MSK_IPAR_PARAM_READ_CASE_NAME*
- *MSK_IPAR_PARAM_READ_IGN_ERROR*
- *MSK_IPAR_PTF_WRITE_TRANSFORM*
- *MSK_IPAR_READ_DEBUG*
- *MSK_IPAR_READ_KEEP_FREE_CON*
- *MSK_IPAR_READ_LP_DROP_NEW_VARS_IN_BOU*
- *MSK_IPAR_READ_LP_QUOTED_NAMES*
- *MSK_IPAR_READ_MPS_FORMAT*
- *MSK_IPAR_READ_MPS_WIDTH*
- *MSK_IPAR_READ_TASK_IGNORE_PARAM*
- *MSK_IPAR_SOL_READ_NAME_WIDTH*
- *MSK_IPAR_SOL_READ_WIDTH*
- *MSK_IPAR_WRITE_BAS_CONSTRAINTS*
- *MSK_IPAR_WRITE_BAS_HEAD*
- *MSK_IPAR_WRITE_BAS_VARIABLES*
- *MSK_IPAR_WRITE_COMPRESSION*
- *MSK_IPAR_WRITE_DATA_PARAM*
- *MSK_IPAR_WRITE_FREE_CON*
- *MSK_IPAR_WRITE_GENERIC_NAMES*
- *MSK_IPAR_WRITE_GENERIC_NAMES_IO*
- *MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_ITEMS*
- *MSK_IPAR_WRITE_INT_CONSTRAINTS*
- *MSK_IPAR_WRITE_INT_HEAD*
- *MSK_IPAR_WRITE_INT_VARIABLES*

- *MSK_IPAR_WRITE_LP_FULL_OBJ*
- *MSK_IPAR_WRITE_LP_LINE_WIDTH*
- *MSK_IPAR_WRITE_LP_QUOTED_NAMES*
- *MSK_IPAR_WRITE_LP_STRICT_FORMAT*
- *MSK_IPAR_WRITE_LP_TERMS_PER_LINE*
- *MSK_IPAR_WRITE_MPS_FORMAT*
- *MSK_IPAR_WRITE_MPS_INT*
- *MSK_IPAR_WRITE_PRECISION*
- *MSK_IPAR_WRITE_SOL_BARVARIABLES*
- *MSK_IPAR_WRITE_SOL_CONSTRAINTS*
- *MSK_IPAR_WRITE_SOL_HEAD*
- *MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES*
- *MSK_IPAR_WRITE_SOL_VARIABLES*
- *MSK_IPAR_WRITE_TASK_INC_SOL*
- *MSK_IPAR_WRITE_XML_MODE*
- *MSK_SPAR_BAS_SOL_FILE_NAME*
- *MSK_SPAR_DATA_FILE_NAME*
- *MSK_SPAR_DEBUG_FILE_NAME*
- *MSK_SPAR_INT_SOL_FILE_NAME*
- *MSK_SPAR_ITR_SOL_FILE_NAME*
- *MSK_SPAR_MIO_DEBUG_STRING*
- *MSK_SPAR_PARAM_COMMENT_SIGN*
- *MSK_SPAR_PARAM_READ_FILE_NAME*
- *MSK_SPAR_PARAM_WRITE_FILE_NAME*
- *MSK_SPAR_READ_MPS_BOU_NAME*
- *MSK_SPAR_READ_MPS_OBJ_NAME*
- *MSK_SPAR_READ_MPS_RAN_NAME*
- *MSK_SPAR_READ_MPS_RHS_NAME*
- *MSK_SPAR_SENSITIVITY_FILE_NAME*
- *MSK_SPAR_SENSITIVITY_RES_FILE_NAME*
- *MSK_SPAR_SOL_FILTER_XC_LOW*
- *MSK_SPAR_SOL_FILTER_XC_UPR*
- *MSK_SPAR_SOL_FILTER_XX_LOW*
- *MSK_SPAR_SOL_FILTER_XX_UPR*
- *MSK_SPAR_STAT_FILE_NAME*
- *MSK_SPAR_STAT_KEY*
- *MSK_SPAR_STAT_NAME*
- *MSK_SPAR_WRITE_LP_GEN_VAR_NAME*

Debugging

- *MSK_IPAR_AUTO_SORT_A_BEFORE_OPT*

Dual simplex

- *MSK_IPAR_SIM_DUAL_CRASH*
- *MSK_IPAR_SIM_DUAL_RESTRICT_SELECTION*
- *MSK_IPAR_SIM_DUAL_SELECTION*

Infeasibility report

- *MSK_IPAR_INFEAS_GENERIC_NAMES*
- *MSK_IPAR_INFEAS_REPORT_LEVEL*
- *MSK_IPAR_LOG_INFEAS_ANA*

Interior-point method

- *MSK_DPAR_CHECK_CONVEXITY_REL_TOL*
- *MSK_DPAR_INTPNT_CO_TOL_DFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_INFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_MU_RED*
- *MSK_DPAR_INTPNT_CO_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_CO_TOL_PFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_QO_TOL_DFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_INFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_MU_RED*
- *MSK_DPAR_INTPNT_QO_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_QO_TOL_PFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_TOL_DFEAS*
- *MSK_DPAR_INTPNT_TOL_DSAFE*
- *MSK_DPAR_INTPNT_TOL_INFEAS*
- *MSK_DPAR_INTPNT_TOL_MU_RED*
- *MSK_DPAR_INTPNT_TOL_PATH*
- *MSK_DPAR_INTPNT_TOL_PFEAS*
- *MSK_DPAR_INTPNT_TOL_PSAFE*
- *MSK_DPAR_INTPNT_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_TOL_REL_STEP*

- *MSK_DPAR_INTPNT_TOL_STEP_SIZE*
- *MSK_DPAR_QCQO_REFORMULATE_REL_DROP_TOL*
- *MSK_IPAR_BI_IGNORE_MAX_ITER*
- *MSK_IPAR_BI_IGNORE_NUM_ERROR*
- *MSK_IPAR_INTPNT_BASIS*
- *MSK_IPAR_INTPNT_DIFF_STEP*
- *MSK_IPAR_INTPNT_HOTSTART*
- *MSK_IPAR_INTPNT_MAX_ITERATIONS*
- *MSK_IPAR_INTPNT_MAX_NUM_COR*
- *MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS*
- *MSK_IPAR_INTPNT_OFF_COL_TRH*
- *MSK_IPAR_INTPNT_ORDER_GP_NUM_SEEDS*
- *MSK_IPAR_INTPNT_ORDER_METHOD*
- *MSK_IPAR_INTPNT_PURIFY*
- *MSK_IPAR_INTPNT_REGULARIZATION_USE*
- *MSK_IPAR_INTPNT_SCALING*
- *MSK_IPAR_INTPNT_SOLVE_FORM*
- *MSK_IPAR_INTPNT_STARTING_POINT*
- *MSK_IPAR_LOG_INTPNT*

License manager

- *MSK_IPAR_CACHE_LICENSE*
- *MSK_IPAR_LICENSE_DEBUG*
- *MSK_IPAR_LICENSE_PAUSE_TIME*
- *MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS*
- *MSK_IPAR_LICENSE_TRH_EXPIRY_WRN*
- *MSK_IPAR_LICENSE_WAIT*

Logging

- *MSK_IPAR_LOG*
- *MSK_IPAR_LOG_ANA_PRO*
- *MSK_IPAR_LOG_BI*
- *MSK_IPAR_LOG_BI_FREQ*
- *MSK_IPAR_LOG_CUT_SECOND_OPT*
- *MSK_IPAR_LOG_EXPAND*
- *MSK_IPAR_LOG_FEAS_REPAIR*

- *MSK_IPAR_LOG_FILE*
- *MSK_IPAR_LOG_INCLUDE_SUMMARY*
- *MSK_IPAR_LOG_INFEAS_ANA*
- *MSK_IPAR_LOG_INTPNT*
- *MSK_IPAR_LOG_LOCAL_INFO*
- *MSK_IPAR_LOG_MIO*
- *MSK_IPAR_LOG_MIO_FREQ*
- *MSK_IPAR_LOG_ORDER*
- *MSK_IPAR_LOG_PRESOLVE*
- *MSK_IPAR_LOG_RESPONSE*
- *MSK_IPAR_LOG_SENSITIVITY*
- *MSK_IPAR_LOG_SENSITIVITY_OPT*
- *MSK_IPAR_LOG_SIM*
- *MSK_IPAR_LOG_SIM_FREQ*
- *MSK_IPAR_LOG_STORAGE*

Mixed-integer optimization

- *MSK_DPAR_MIO_MAX_TIME*
- *MSK_DPAR_MIO_REL_GAP_CONST*
- *MSK_DPAR_MIO_TOL_ABS_GAP*
- *MSK_DPAR_MIO_TOL_ABS_RELAX_INT*
- *MSK_DPAR_MIO_TOL_FEAS*
- *MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT*
- *MSK_DPAR_MIO_TOL_REL_GAP*
- *MSK_IPAR_LOG_MIO*
- *MSK_IPAR_LOG_MIO_FREQ*
- *MSK_IPAR_MIO_BRANCH_DIR*
- *MSK_IPAR_MIO_CONIC_OUTER_APPROXIMATION*
- *MSK_IPAR_MIO_CUT_CLIQUE*
- *MSK_IPAR_MIO_CUT_CMIR*
- *MSK_IPAR_MIO_CUT_GMI*
- *MSK_IPAR_MIO_CUT_IMPLIED_BOUND*
- *MSK_IPAR_MIO_CUT_KNAPSACK_COVER*
- *MSK_IPAR_MIO_CUT_SELECTION_LEVEL*
- *MSK_IPAR_MIO_FEASPUMP_LEVEL*
- *MSK_IPAR_MIO_HEURISTIC_LEVEL*

- *MSK_IPAR_MIO_MAX_NUM_BRANCHES*
- *MSK_IPAR_MIO_MAX_NUM_RELAXS*
- *MSK_IPAR_MIO_MAX_NUM_ROOT_CUT_ROUNDS*
- *MSK_IPAR_MIO_MAX_NUM_SOLUTIONS*
- *MSK_IPAR_MIO_NODE_OPTIMIZER*
- *MSK_IPAR_MIO_NODE_SELECTION*
- *MSK_IPAR_MIO_PERSPECTIVE_REFORMULATE*
- *MSK_IPAR_MIO_PROBING_LEVEL*
- *MSK_IPAR_MIO_PROPAGATE_OBJECTIVE_CONSTRAINT*
- *MSK_IPAR_MIO_RINS_MAX_NODES*
- *MSK_IPAR_MIO_ROOT_OPTIMIZER*
- *MSK_IPAR_MIO_ROOT_REPEAT_PRESOLVE_LEVEL*
- *MSK_IPAR_MIO_SEED*
- *MSK_IPAR_MIO_VB_DETECTION_LEVEL*

Output information

- *MSK_IPAR_INFEAS_REPORT_LEVEL*
- *MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS*
- *MSK_IPAR_LICENSE_TRH_EXPIRY_WRN*
- *MSK_IPAR_LOG*
- *MSK_IPAR_LOG_BI*
- *MSK_IPAR_LOG_BI_FREQ*
- *MSK_IPAR_LOG_CUT_SECOND_OPT*
- *MSK_IPAR_LOG_EXPAND*
- *MSK_IPAR_LOG_FEAS_REPAIR*
- *MSK_IPAR_LOG_FILE*
- *MSK_IPAR_LOG_INCLUDE_SUMMARY*
- *MSK_IPAR_LOG_INFEAS_ANA*
- *MSK_IPAR_LOG_INTPNT*
- *MSK_IPAR_LOG_LOCAL_INFO*
- *MSK_IPAR_LOG_MIO*
- *MSK_IPAR_LOG_MIO_FREQ*
- *MSK_IPAR_LOG_ORDER*
- *MSK_IPAR_LOG_RESPONSE*
- *MSK_IPAR_LOG_SENSITIVITY*
- *MSK_IPAR_LOG_SENSITIVITY_OPT*

- *MSK_IPAR_LOG_SIM*
- *MSK_IPAR_LOG_SIM_FREQ*
- *MSK_IPAR_LOG_SIM_MINOR*
- *MSK_IPAR_LOG_STORAGE*
- *MSK_IPAR_MAX_NUM_WARNINGS*

Overall solver

- *MSK_IPAR_BI_CLEAN_OPTIMIZER*
- *MSK_IPAR_INFEAS_PREFER_PRIMAL*
- *MSK_IPAR_LICENSE_WAIT*
- *MSK_IPAR_MIO_MODE*
- *MSK_IPAR_OPTIMIZER*
- *MSK_IPAR_PRESOLVE_LEVEL*
- *MSK_IPAR_PRESOLVE_MAX_NUM_REDUCTIONS*
- *MSK_IPAR_PRESOLVE_USE*
- *MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER*
- *MSK_IPAR_SENSITIVITY_ALL*
- *MSK_IPAR_SENSITIVITY_OPTIMIZER*
- *MSK_IPAR_SENSITIVITY_TYPE*
- *MSK_IPAR_SOLUTION_CALLBACK*

Overall system

- *MSK_IPAR_AUTO_UPDATE_SOL_INFO*
- *MSK_IPAR_INTPNT_MULTI_THREAD*
- *MSK_IPAR_LICENSE_WAIT*
- *MSK_IPAR_LOG_STORAGE*
- *MSK_IPAR_MT_SPINCOUNT*
- *MSK_IPAR_NUM_THREADS*
- *MSK_IPAR_REMOVE_UNUSED_SOLUTIONS*
- *MSK_IPAR_TIMING_LEVEL*
- *MSK_SPAR_REMOTE_ACCESS_TOKEN*

Presolve

- *MSK_DPAR_PRESOLVE_TOL_ABS_LINDEP*
- *MSK_DPAR_PRESOLVE_TOL_AIJ*
- *MSK_DPAR_PRESOLVE_TOL_REL_LINDEP*
- *MSK_DPAR_PRESOLVE_TOL_S*
- *MSK_DPAR_PRESOLVE_TOL_X*
- *MSK_IPAR_PRESOLVE_ELIMINATOR_MAX_FILL*
- *MSK_IPAR_PRESOLVE_ELIMINATOR_MAX_NUM_TRIES*
- *MSK_IPAR_PRESOLVE_LEVEL*
- *MSK_IPAR_PRESOLVE_LINDEP_ABS_WORK_TRH*
- *MSK_IPAR_PRESOLVE_LINDEP_REL_WORK_TRH*
- *MSK_IPAR_PRESOLVE_LINDEP_USE*
- *MSK_IPAR_PRESOLVE_MAX_NUM_PASS*
- *MSK_IPAR_PRESOLVE_MAX_NUM_REDUCTIONS*
- *MSK_IPAR_PRESOLVE_USE*

Primal simplex

- *MSK_IPAR_SIM_PRIMAL_CRASH*
- *MSK_IPAR_SIM_PRIMAL_RESTRICT_SELECTION*
- *MSK_IPAR_SIM_PRIMAL_SELECTION*

Progress callback

- *MSK_IPAR_SOLUTION_CALLBACK*

Simplex optimizer

- *MSK_DPAR_BASIS_REL_TOL_S*
- *MSK_DPAR_BASIS_TOL_S*
- *MSK_DPAR_BASIS_TOL_X*
- *MSK_DPAR_SIM_LU_TOL_REL_PIV*
- *MSK_DPAR_SIMPLEX_ABS_TOL_PIV*
- *MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE*
- *MSK_IPAR_LOG_SIM*
- *MSK_IPAR_LOG_SIM_FREQ*
- *MSK_IPAR_LOG_SIM_MINOR*
- *MSK_IPAR_SENSITIVITY_OPTIMIZER*
- *MSK_IPAR_SIM_BASIS_FACTOR_USE*

- *MSK_IPAR_SIM_DEGEN*
- *MSK_IPAR_SIM_DUAL_PHASEONE_METHOD*
- *MSK_IPAR_SIM_EXPLOIT_DUPVEC*
- *MSK_IPAR_SIM_HOTSTART*
- *MSK_IPAR_SIM_HOTSTART_LU*
- *MSK_IPAR_SIM_MAX_ITERATIONS*
- *MSK_IPAR_SIM_MAX_NUM_SETBACKS*
- *MSK_IPAR_SIM_NON_SINGULAR*
- *MSK_IPAR_SIM_PRIMAL_PHASEONE_METHOD*
- *MSK_IPAR_SIM_REFACTOR_FREQ*
- *MSK_IPAR_SIM_REFORMULATION*
- *MSK_IPAR_SIM_SAVE_LU*
- *MSK_IPAR_SIM_SCALING*
- *MSK_IPAR_SIM_SCALING_METHOD*
- *MSK_IPAR_SIM_SEED*
- *MSK_IPAR_SIM_SOLVE_FORM*
- *MSK_IPAR_SIM_STABILITY_PRIORITY*
- *MSK_IPAR_SIM_SWITCH_OPTIMIZER*

Solution input/output

- *MSK_IPAR_INFEAS_REPORT_AUTO*
- *MSK_IPAR_SOL_FILTER_KEEP_BASIC*
- *MSK_IPAR_SOL_FILTER_KEEP_RANGED*
- *MSK_IPAR_SOL_READ_NAME_WIDTH*
- *MSK_IPAR_SOL_READ_WIDTH*
- *MSK_IPAR_WRITE_BAS_CONSTRAINTS*
- *MSK_IPAR_WRITE_BAS_HEAD*
- *MSK_IPAR_WRITE_BAS_VARIABLES*
- *MSK_IPAR_WRITE_INT_CONSTRAINTS*
- *MSK_IPAR_WRITE_INT_HEAD*
- *MSK_IPAR_WRITE_INT_VARIABLES*
- *MSK_IPAR_WRITE_SOL_BARVARIABLES*
- *MSK_IPAR_WRITE_SOL_CONSTRAINTS*
- *MSK_IPAR_WRITE_SOL_HEAD*
- *MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES*
- *MSK_IPAR_WRITE_SOL_VARIABLES*

- *MSK_SPAR_BAS_SOL_FILE_NAME*
- *MSK_SPAR_INT_SOL_FILE_NAME*
- *MSK_SPAR_ITR_SOL_FILE_NAME*
- *MSK_SPAR_SOL_FILTER_XC_LOW*
- *MSK_SPAR_SOL_FILTER_XC_UPR*
- *MSK_SPAR_SOL_FILTER_XX_LOW*
- *MSK_SPAR_SOL_FILTER_XX_UPR*

Termination criteria

- *MSK_DPAR_BASIS_REL_TOL_S*
- *MSK_DPAR_BASIS_TOL_S*
- *MSK_DPAR_BASIS_TOL_X*
- *MSK_DPAR_INTPNT_CO_TOL_DFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_INFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_MU_RED*
- *MSK_DPAR_INTPNT_CO_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_CO_TOL_PFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_QO_TOL_DFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_INFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_MU_RED*
- *MSK_DPAR_INTPNT_QO_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_QO_TOL_PFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_TOL_DFEAS*
- *MSK_DPAR_INTPNT_TOL_INFEAS*
- *MSK_DPAR_INTPNT_TOL_MU_RED*
- *MSK_DPAR_INTPNT_TOL_PFEAS*
- *MSK_DPAR_INTPNT_TOL_REL_GAP*
- *MSK_DPAR_LOWER_OBJ_CUT*
- *MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH*
- *MSK_DPAR_MIO_MAX_TIME*
- *MSK_DPAR_MIO_REL_GAP_CONST*
- *MSK_DPAR_MIO_TOL_REL_GAP*
- *MSK_DPAR_OPTIMIZER_MAX_TIME*
- *MSK_DPAR_UPPER_OBJ_CUT*

- *MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH*
- *MSK_IPAR_BI_MAX_ITERATIONS*
- *MSK_IPAR_INTPNT_MAX_ITERATIONS*
- *MSK_IPAR_MIO_MAX_NUM_BRANCHES*
- *MSK_IPAR_MIO_MAX_NUM_ROOT_CUT_ROUNDS*
- *MSK_IPAR_MIO_MAX_NUM_SOLUTIONS*
- *MSK_IPAR_SIM_MAX_ITERATIONS*

Other

- *MSK_IPAR_COMPRESS_STATFILE*

15.5 Parameters (alphabetical list sorted by type)

- *Double parameters*
- *Integer parameters*
- *String parameters*

15.5.1 Double parameters

MSKdparame

The enumeration type containing all double parameters.

MSK_DPAR_ANA_SOL_INFEAS_TOL

If a constraint violates its bound with an amount larger than this value, the constraint name, index and violation will be printed by the solution analyzer.

Default 1e-6

Accepted [0.0; +inf]

Example `MSK_putdoupam(task, MSK_DPAR_ANA_SOL_INFEAS_TOL, 1e-6)`

Groups *Analysis*

MSK_DPAR_BASIS_REL_TOL_S

Maximum relative dual bound violation allowed in an optimal basic solution.

Default 1.0e-12

Accepted [0.0; +inf]

Example `MSK_putdoupam(task, MSK_DPAR_BASIS_REL_TOL_S, 1.0e-12)`

Groups *Simplex optimizer, Termination criteria*

MSK_DPAR_BASIS_TOL_S

Maximum absolute dual bound violation in an optimal basic solution.

Default 1.0e-6

Accepted [1.0e-9; +inf]

Example `MSK_putdoupam(task, MSK_DPAR_BASIS_TOL_S, 1.0e-6)`

Groups *Simplex optimizer, Termination criteria*

MSK_DPAR_BASIS_TOL_X

Maximum absolute primal bound violation allowed in an optimal basic solution.

Default 1.0e-6

Accepted [1.0e-9; +inf]

Example `MSK_putdoupam(task, MSK_DPAR_BASIS_TOL_X, 1.0e-6)`

Groups *Simplex optimizer, Termination criteria*

MSK_DPAR_CHECK_CONVEXITY_REL_TOL

This parameter controls when the full convexity check declares a problem to be non-convex. Increasing this tolerance relaxes the criteria for declaring the problem non-convex.

A problem is declared non-convex if negative (positive) pivot elements are detected in the Cholesky factor of a matrix which is required to be PSD (NSD). This parameter controls how much this non-negativity requirement may be violated.

If d_i is the pivot element for column i , then the matrix Q is considered to not be PSD if:

$$d_i \leq -|Q_{ii}|\text{check_convexity_rel_tol}$$

Default 1e-10

Accepted [0; +inf]

Example MSK_putdoupam(task, MSK_DPAR_CHECK_CONVEXITY_REL_TOL, 1e-10)

Groups *Interior-point method*

MSK_DPAR_DATA_SYM_MAT_TOL

Absolute zero tolerance for elements in symmetric matrices. If any value in a symmetric matrix is smaller than this parameter in absolute terms **MOSEK** will treat the values as zero and generate a warning.

Default 1.0e-12

Accepted [1.0e-16; 1.0e-6]

Example MSK_putdoupam(task, MSK_DPAR_DATA_SYM_MAT_TOL, 1.0e-12)

Groups *Data check*

MSK_DPAR_DATA_SYM_MAT_TOL_HUGE

An element in a symmetric matrix which is larger than this value in absolute size causes an error.

Default 1.0e20

Accepted [0.0; +inf]

Example MSK_putdoupam(task, MSK_DPAR_DATA_SYM_MAT_TOL_HUGE, 1.0e20)

Groups *Data check*

MSK_DPAR_DATA_SYM_MAT_TOL_LARGE

An element in a symmetric matrix which is larger than this value in absolute size causes a warning message to be printed.

Default 1.0e10

Accepted [0.0; +inf]

Example MSK_putdoupam(task, MSK_DPAR_DATA_SYM_MAT_TOL_LARGE, 1.0e10)

Groups *Data check*

MSK_DPAR_DATA_TOL_AIJ_HUGE

An element in A which is larger than this value in absolute size causes an error.

Default 1.0e20

Accepted [0.0; +inf]

Example MSK_putdoupam(task, MSK_DPAR_DATA_TOL_AIJ_HUGE, 1.0e20)

Groups *Data check*

MSK_DPAR_DATA_TOL_AIJ_LARGE

An element in A which is larger than this value in absolute size causes a warning message to be printed.

Default 1.0e10

Accepted [0.0; +inf]

Example MSK_putdoupam(task, MSK_DPAR_DATA_TOL_AIJ_LARGE, 1.0e10)

Groups *Data check*

MSK_DPAR_DATA_TOL_BOUND_INF

An bound which in absolute value is greater than this parameter is considered infinite.

Default 1.0e16

Accepted [0.0; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_DATA_TOL_BOUND_INF, 1.0e16)

Groups *Data check*

MSK_DPAR_DATA_TOL_BOUND_WRN

If a bound value is larger than this value in absolute size, then a warning message is issued.

Default 1.0e8

Accepted [0.0; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_DATA_TOL_BOUND_WRN, 1.0e8)

Groups *Data check*

MSK_DPAR_DATA_TOL_C_HUGE

An element in c which is larger than the value of this parameter in absolute terms is considered to be huge and generates an error.

Default 1.0e16

Accepted [0.0; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_DATA_TOL_C_HUGE, 1.0e16)

Groups *Data check*

MSK_DPAR_DATA_TOL_CJ_LARGE

An element in c which is larger than this value in absolute terms causes a warning message to be printed.

Default 1.0e8

Accepted [0.0; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_DATA_TOL_CJ_LARGE, 1.0e8)

Groups *Data check*

MSK_DPAR_DATA_TOL_QIJ

Absolute zero tolerance for elements in Q matrices.

Default 1.0e-16

Accepted [0.0; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_DATA_TOL_QIJ, 1.0e-16)

Groups *Data check*

MSK_DPAR_DATA_TOL_X

Zero tolerance for constraints and variables i.e. if the distance between the lower and upper bound is less than this value, then the lower and upper bound is considered identical.

Default 1.0e-8

Accepted [0.0; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_DATA_TOL_X, 1.0e-8)

Groups *Data check*

MSK_DPAR_INTPNT_CO_TOL_DFEAS

Dual feasibility tolerance used by the interior-point optimizer for conic problems.

Default 1.0e-8

Accepted [0.0; 1.0]

Example MSK_putdoupparam(task, MSK_DPAR_INTPNT_CO_TOL_DFEAS, 1.0e-8)

See also *MSK_DPAR_INTPNT_CO_TOL_NEAR_REL*

Groups *Interior-point method, Termination criteria, Conic interior-point method*

MSK_DPAR_INTPNT_CO_TOL_INFEAS

Infeasibility tolerance used by the interior-point optimizer for conic problems. Controls when the interior-point optimizer declares the model primal or dual infeasible. A small number means the optimizer gets more conservative about declaring the model infeasible.

Default 1.0e-12

Accepted [0.0; 1.0]

Example `MSK_putdoupparam(task, MSK_DPAR_INTPNT_CO_TOL_INFEAS, 1.0e-12)`

Groups *Interior-point method, Termination criteria, Conic interior-point method*

MSK_DPAR_INTPNT_CO_TOL_MU_RED

Relative complementarity gap tolerance used by the interior-point optimizer for conic problems.

Default 1.0e-8

Accepted [0.0; 1.0]

Example `MSK_putdoupparam(task, MSK_DPAR_INTPNT_CO_TOL_MU_RED, 1.0e-8)`

Groups *Interior-point method, Termination criteria, Conic interior-point method*

MSK_DPAR_INTPNT_CO_TOL_NEAR_REL

Optimality tolerance used by the interior-point optimizer for conic problems. If **MOSEK** cannot compute a solution that has the prescribed accuracy then it will check if the solution found satisfies the termination criteria with all tolerances multiplied by the value of this parameter. If yes, then the solution is also declared optimal.

Default 1000

Accepted [1.0; +inf]

Example `MSK_putdoupparam(task, MSK_DPAR_INTPNT_CO_TOL_NEAR_REL, 1000)`

Groups *Interior-point method, Termination criteria, Conic interior-point method*

MSK_DPAR_INTPNT_CO_TOL_PFEAS

Primal feasibility tolerance used by the interior-point optimizer for conic problems.

Default 1.0e-8

Accepted [0.0; 1.0]

Example `MSK_putdoupparam(task, MSK_DPAR_INTPNT_CO_TOL_PFEAS, 1.0e-8)`

See also [*MSK_DPAR_INTPNT_CO_TOL_NEAR_REL*](#)

Groups *Interior-point method, Termination criteria, Conic interior-point method*

MSK_DPAR_INTPNT_CO_TOL_REL_GAP

Relative gap termination tolerance used by the interior-point optimizer for conic problems.

Default 1.0e-8

Accepted [0.0; 1.0]

Example `MSK_putdoupparam(task, MSK_DPAR_INTPNT_CO_TOL_REL_GAP, 1.0e-8)`

See also [*MSK_DPAR_INTPNT_CO_TOL_NEAR_REL*](#)

Groups *Interior-point method, Termination criteria, Conic interior-point method*

MSK_DPAR_INTPNT_QO_TOL_DFEAS

Dual feasibility tolerance used by the interior-point optimizer for quadratic problems.

Default 1.0e-8

Accepted [0.0; 1.0]

Example `MSK_putdoupparam(task, MSK_DPAR_INTPNT_QO_TOL_DFEAS, 1.0e-8)`

See also [*MSK_DPAR_INTPNT_QO_TOL_NEAR_REL*](#)

Groups *Interior-point method, Termination criteria*

MSK_DPAR_INTPNT_QO_TOL_INFEAS

Infeasibility tolerance used by the interior-point optimizer for quadratic problems. Controls when the interior-point optimizer declares the model primal or dual infeasible. A small number means the optimizer gets more conservative about declaring the model infeasible.

Default 1.0e-12

Accepted [0.0; 1.0]

Example `MSK_putdouparam(task, MSK_DPAR_INTPNT_QO_TOL_INFEAS, 1.0e-12)`

Groups *Interior-point method, Termination criteria*

MSK_DPAR_INTPNT_QO_TOL_MU_RED

Relative complementarity gap tolerance used by the interior-point optimizer for quadratic problems.

Default 1.0e-8

Accepted [0.0; 1.0]

Example `MSK_putdouparam(task, MSK_DPAR_INTPNT_QO_TOL_MU_RED, 1.0e-8)`

Groups *Interior-point method, Termination criteria*

MSK_DPAR_INTPNT_QO_TOL_NEAR_REL

Optimality tolerance used by the interior-point optimizer for quadratic problems. If **MOSEK** cannot compute a solution that has the prescribed accuracy then it will check if the solution found satisfies the termination criteria with all tolerances multiplied by the value of this parameter. If yes, then the solution is also declared optimal.

Default 1000

Accepted [1.0; +inf]

Example `MSK_putdouparam(task, MSK_DPAR_INTPNT_QO_TOL_NEAR_REL, 1000)`

Groups *Interior-point method, Termination criteria*

MSK_DPAR_INTPNT_QO_TOL_PFEAS

Primal feasibility tolerance used by the interior-point optimizer for quadratic problems.

Default 1.0e-8

Accepted [0.0; 1.0]

Example `MSK_putdouparam(task, MSK_DPAR_INTPNT_QO_TOL_PFEAS, 1.0e-8)`

See also [*MSK_DPAR_INTPNT_QO_TOL_NEAR_REL*](#)

Groups *Interior-point method, Termination criteria*

MSK_DPAR_INTPNT_QO_TOL_REL_GAP

Relative gap termination tolerance used by the interior-point optimizer for quadratic problems.

Default 1.0e-8

Accepted [0.0; 1.0]

Example `MSK_putdouparam(task, MSK_DPAR_INTPNT_QO_TOL_REL_GAP, 1.0e-8)`

See also [*MSK_DPAR_INTPNT_QO_TOL_NEAR_REL*](#)

Groups *Interior-point method, Termination criteria*

MSK_DPAR_INTPNT_TOL_DFEAS

Dual feasibility tolerance used by the interior-point optimizer for linear problems.

Default 1.0e-8

Accepted [0.0; 1.0]

Example `MSK_putdouparam(task, MSK_DPAR_INTPNT_TOL_DFEAS, 1.0e-8)`

Groups *Interior-point method, Termination criteria*

MSK_DPAR_INTPNT_TOL_DSAFE

Controls the initial dual starting point used by the interior-point optimizer. If the interior-point optimizer converges slowly and/or the constraint or variable bounds are very large, then it might be worthwhile to increase this value.

Default 1.0
Accepted [1.0e-4; +inf]
Example MSK_putdoupparam(task, MSK_DPAR_INTPNT_TOL_DSAFE, 1.0)
Groups *Interior-point method*

MSK_DPAR_INTPNT_TOL_INFEAS

Infeasibility tolerance used by the interior-point optimizer for linear problems. Controls when the interior-point optimizer declares the model primal or dual infeasible. A small number means the optimizer gets more conservative about declaring the model infeasible.

Default 1.0e-10
Accepted [0.0; 1.0]
Example MSK_putdoupparam(task, MSK_DPAR_INTPNT_TOL_INFEAS, 1.0e-10)
Groups *Interior-point method, Termination criteria*

MSK_DPAR_INTPNT_TOL_MU_RED

Relative complementarity gap tolerance used by the interior-point optimizer for linear problems.

Default 1.0e-16
Accepted [0.0; 1.0]
Example MSK_putdoupparam(task, MSK_DPAR_INTPNT_TOL_MU_RED, 1.0e-16)
Groups *Interior-point method, Termination criteria*

MSK_DPAR_INTPNT_TOL_PATH

Controls how close the interior-point optimizer follows the central path. A large value of this parameter means the central path is followed very closely. On numerically unstable problems it may be worthwhile to increase this parameter.

Default 1.0e-8
Accepted [0.0; 0.9999]
Example MSK_putdoupparam(task, MSK_DPAR_INTPNT_TOL_PATH, 1.0e-8)
Groups *Interior-point method*

MSK_DPAR_INTPNT_TOL_PFEAS

Primal feasibility tolerance used by the interior-point optimizer for linear problems.

Default 1.0e-8
Accepted [0.0; 1.0]
Example MSK_putdoupparam(task, MSK_DPAR_INTPNT_TOL_PFEAS, 1.0e-8)
Groups *Interior-point method, Termination criteria*

MSK_DPAR_INTPNT_TOL_PSAFE

Controls the initial primal starting point used by the interior-point optimizer. If the interior-point optimizer converges slowly and/or the constraint or variable bounds are very large, then it may be worthwhile to increase this value.

Default 1.0
Accepted [1.0e-4; +inf]
Example MSK_putdoupparam(task, MSK_DPAR_INTPNT_TOL_PSAFE, 1.0)
Groups *Interior-point method*

MSK_DPAR_INTPNT_TOL_REL_GAP

Relative gap termination tolerance used by the interior-point optimizer for linear problems.

Default 1.0e-8
Accepted [1.0e-14; +inf]
Example MSK_putdoupparam(task, MSK_DPAR_INTPNT_TOL_REL_GAP, 1.0e-8)
Groups *Termination criteria, Interior-point method*

MSK_DPAR_INTPNT_TOL_REL_STEP

Relative step size to the boundary for linear and quadratic optimization problems.

Default 0.9999

Accepted [1.0e-4; 0.999999]

Example MSK_putdoupparam(task, MSK_DPAR_INTPNT_TOL_REL_STEP, 0.9999)

Groups *Interior-point method*

MSK_DPAR_INTPNT_TOL_STEP_SIZE

Minimal step size tolerance. If the step size falls below the value of this parameter, then the interior-point optimizer assumes that it is stalled. In other words the interior-point optimizer does not make any progress and therefore it is better to stop.

Default 1.0e-6

Accepted [0.0; 1.0]

Example MSK_putdoupparam(task, MSK_DPAR_INTPNT_TOL_STEP_SIZE, 1.0e-6)

Groups *Interior-point method*

MSK_DPAR_LOWER_OBJ_CUT

If either a primal or dual feasible solution is found proving that the optimal objective value is outside the interval [*MSK_DPAR_LOWER_OBJ_CUT*, *MSK_DPAR_UPPER_OBJ_CUT*], then **MOSEK** is terminated.

Default -1.0e30

Accepted [-inf; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_LOWER_OBJ_CUT, -1.0e30)

See also *MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH*

Groups *Termination criteria*

MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH

If the lower objective cut is less than the value of this parameter value, then the lower objective cut i.e. *MSK_DPAR_LOWER_OBJ_CUT* is treated as $-\infty$.

Default -0.5e30

Accepted [-inf; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH, -0.5e30)

Groups *Termination criteria*

MSK_DPAR_MIO_MAX_TIME

This parameter limits the maximum time spent by the mixed-integer optimizer. A negative number means infinity.

Default -1.0

Accepted [-inf; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_MIO_MAX_TIME, -1.0)

Groups *Mixed-integer optimization, Termination criteria*

MSK_DPAR_MIO_REL_GAP_CONST

This value is used to compute the relative gap for the solution to an integer optimization problem.

Default 1.0e-10

Accepted [1.0e-15; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_MIO_REL_GAP_CONST, 1.0e-10)

Groups *Mixed-integer optimization, Termination criteria*

MSK_DPAR_MIO_TOL_ABS_GAP

Absolute optimality tolerance employed by the mixed-integer optimizer.

Default 0.0

Accepted [0.0; +inf]

Example MSK_putdouparam(task, MSK_DPAR_MIO_TOL_ABS_GAP, 0.0)

Groups *Mixed-integer optimization*

MSK_DPAR_MIO_TOL_ABS_RELAX_INT

Absolute integer feasibility tolerance. If the distance to the nearest integer is less than this tolerance then an integer constraint is assumed to be satisfied.

Default 1.0e-5

Accepted [1e-9; +inf]

Example MSK_putdouparam(task, MSK_DPAR_MIO_TOL_ABS_RELAX_INT, 1.0e-5)

Groups *Mixed-integer optimization*

MSK_DPAR_MIO_TOL_FEAS

Feasibility tolerance for mixed integer solver.

Default 1.0e-6

Accepted [1e-9; 1e-3]

Example MSK_putdouparam(task, MSK_DPAR_MIO_TOL_FEAS, 1.0e-6)

Groups *Mixed-integer optimization*

MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT

If the relative improvement of the dual bound is smaller than this value, the solver will terminate the root cut generation. A value of 0.0 means that the value is selected automatically.

Default 0.0

Accepted [0.0; 1.0]

Example MSK_putdouparam(task, MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT, 0.0)

Groups *Mixed-integer optimization*

MSK_DPAR_MIO_TOL_REL_GAP

Relative optimality tolerance employed by the mixed-integer optimizer.

Default 1.0e-4

Accepted [0.0; +inf]

Example MSK_putdouparam(task, MSK_DPAR_MIO_TOL_REL_GAP, 1.0e-4)

Groups *Mixed-integer optimization, Termination criteria*

MSK_DPAR_OPTIMIZER_MAX_TIME

Maximum amount of time the optimizer is allowed to spent on the optimization. A negative number means infinity.

Default -1.0

Accepted [-inf; +inf]

Example MSK_putdouparam(task, MSK_DPAR_OPTIMIZER_MAX_TIME, -1.0)

Groups *Termination criteria*

MSK_DPAR_PREOLVE_TOL_ABS_LINDEP

Absolute tolerance employed by the linear dependency checker.

Default 1.0e-6

Accepted [0.0; +inf]

Example MSK_putdouparam(task, MSK_DPAR_PREOLVE_TOL_ABS_LINDEP, 1.0e-6)

Groups *Presolve*

MSK_DPAR_PREOLVE_TOL_AIJ

Absolute zero tolerance employed for a_{ij} in the presolve.

Default 1.0e-12

Accepted [1.0e-15; +inf]

Example `MSK_putdoupparam(task, MSK_DPAR_PREOLVE_TOL_AIJ, 1.0e-12)`

Groups *Presolve*

MSK_DPAR_PREOLVE_TOL_REL_LINDEP

Relative tolerance employed by the linear dependency checker.

Default 1.0e-10

Accepted [0.0; +inf]

Example `MSK_putdoupparam(task, MSK_DPAR_PREOLVE_TOL_REL_LINDEP, 1.0e-10)`

Groups *Presolve*

MSK_DPAR_PREOLVE_TOL_S

Absolute zero tolerance employed for s_i in the presolve.

Default 1.0e-8

Accepted [0.0; +inf]

Example `MSK_putdoupparam(task, MSK_DPAR_PREOLVE_TOL_S, 1.0e-8)`

Groups *Presolve*

MSK_DPAR_PREOLVE_TOL_X

Absolute zero tolerance employed for x_j in the presolve.

Default 1.0e-8

Accepted [0.0; +inf]

Example `MSK_putdoupparam(task, MSK_DPAR_PREOLVE_TOL_X, 1.0e-8)`

Groups *Presolve*

MSK_DPAR_QCQO_REFORMULATE_REL_DROP_TOL

This parameter determines when columns are dropped in incomplete Cholesky factorization during reformulation of quadratic problems.

Default 1e-15

Accepted [0; +inf]

Example `MSK_putdoupparam(task, MSK_DPAR_QCQO_REFORMULATE_REL_DROP_TOL, 1e-15)`

Groups *Interior-point method*

MSK_DPAR_SEMIDEFINITE_TOL_APPROX

Tolerance to define a matrix to be positive semidefinite.

Default 1.0e-10

Accepted [1.0e-15; +inf]

Example `MSK_putdoupparam(task, MSK_DPAR_SEMIDEFINITE_TOL_APPROX, 1.0e-10)`

Groups *Data check*

MSK_DPAR_SIM_LU_TOL_REL_PIV

Relative pivot tolerance employed when computing the LU factorization of the basis in the simplex optimizers and in the basis identification procedure. A value closer to 1.0 generally improves numerical stability but typically also implies an increase in the computational work.

Default 0.01

Accepted [1.0e-6; 0.999999]

Example `MSK_putdoupparam(task, MSK_DPAR_SIM_LU_TOL_REL_PIV, 0.01)`

Groups *Basis identification, Simplex optimizer*

MSK_DPAR_SIMPLEX_ABS_TOL_PIV

Absolute pivot tolerance employed by the simplex optimizers.

Default 1.0e-7

Accepted [1.0e-12; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_SIMPLEX_ABS_TOL_PIV, 1.0e-7)

Groups *Simplex optimizer*

MSK_DPAR_UPPER_OBJ_CUT

If either a primal or dual feasible solution is found proving that the optimal objective value is outside the interval [*MSK_DPAR_LOWER_OBJ_CUT*, *MSK_DPAR_UPPER_OBJ_CUT*], then **MOSEK** is terminated.

Default 1.0e30

Accepted [-inf; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_UPPER_OBJ_CUT, 1.0e30)

See also *MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH*

Groups *Termination criteria*

MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH

If the upper objective cut is greater than the value of this parameter, then the upper objective cut *MSK_DPAR_UPPER_OBJ_CUT* is treated as ∞ .

Default 0.5e30

Accepted [-inf; +inf]

Example MSK_putdoupparam(task, MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH, 0.5e30)

Groups *Termination criteria*

15.5.2 Integer parameters

MSKiparame

The enumeration type containing all integer parameters.

MSK_IPAR_ANA_SOL_BASIS

Controls whether the basis matrix is analyzed in solution analyzer.

Default *ON*

Accepted *ON*, *OFF* (see *MSKonoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_ANA_SOL_BASIS, MSK_ON)

Groups *Analysis*

MSK_IPAR_ANA_SOL_PRINT_VIOLATED

A parameter of the problem analyzer. Controls whether a list of violated constraints is printed. All constraints violated by more than the value set by the parameter *MSK_DPAR_ANA_SOL_INFEAS_TOL* will be printed.

Default *OFF*

Accepted *ON*, *OFF* (see *MSKonoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_ANA_SOL_PRINT_VIOLATED, MSK_OFF)

Groups *Analysis*

MSK_IPAR_AUTO_SORT_A_BEFORE_OPT

Controls whether the elements in each column of *A* are sorted before an optimization is performed. This is not required but makes the optimization more deterministic.

Default *OFF*

Accepted *ON*, *OFF* (see *MSKonoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_AUTO_SORT_A_BEFORE_OPT, MSK_OFF)

Groups *Debugging*

MSK_IPAR_AUTO_UPDATE_SOL_INFO

Controls whether the solution information items are automatically updated after an optimization is performed.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_AUTO_UPDATE_SOL_INFO, MSK_OFF)`

Groups *Overall system*

MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE

If a slack variable is in the basis, then the corresponding column in the basis is a unit vector with -1 in the right position. However, if this parameter is set to *MSK_ON*, -1 is replaced by 1.

This has significance for the results returned by the *MSK_solvewithbasis* function.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE, MSK_OFF)`

Groups *Simplex optimizer*

MSK_IPAR_BI_CLEAN_OPTIMIZER

Controls which simplex optimizer is used in the clean-up phase. Anything else than *MSK_OPTIMIZER_PRIMAL_SIMPLEX* or *MSK_OPTIMIZER_DUAL_SIMPLEX* is equivalent to *MSK_OPTIMIZER_FREE_SIMPLEX*.

Default *FREE*

Accepted *FREE, INTPNT, CONIC, PRIMAL_SIMPLEX, DUAL_SIMPLEX, FREE_SIMPLEX, MIXED_INT* (see *MSKoptimizertypee*)

Example `MSK_putintparam(task, MSK_IPAR_BI_CLEAN_OPTIMIZER, MSK_OPTIMIZER_FREE)`

Groups *Basis identification, Overall solver*

MSK_IPAR_BI_IGNORE_MAX_ITER

If the parameter *MSK_IPAR_INTPNT_BASIS* has the value *MSK_BI_NO_ERROR* and the interior-point optimizer has terminated due to maximum number of iterations, then basis identification is performed if this parameter has the value *MSK_ON*.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_BI_IGNORE_MAX_ITER, MSK_OFF)`

Groups *Interior-point method, Basis identification*

MSK_IPAR_BI_IGNORE_NUM_ERROR

If the parameter *MSK_IPAR_INTPNT_BASIS* has the value *MSK_BI_NO_ERROR* and the interior-point optimizer has terminated due to a numerical problem, then basis identification is performed if this parameter has the value *MSK_ON*.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_BI_IGNORE_NUM_ERROR, MSK_OFF)`

Groups *Interior-point method, Basis identification*

MSK_IPAR_BI_MAX_ITERATIONS

Controls the maximum number of simplex iterations allowed to optimize a basis after the basis identification.

Default 1000000

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_BI_MAX_ITERATIONS, 1000000)`

Groups *Basis identification, Termination criteria*

MSK_IPAR_CACHE_LICENSE

Specifies if the license is kept checked out for the lifetime of the **MOSEK** environment/model/process (*MSK_ON*) or returned to the server immediately after the optimization (*MSK_OFF*).

By default the license is checked out for the lifetime of the **MOSEK** environment by the first call to *MSK_optimize*.

Check-in and check-out of licenses have an overhead. Frequent communication with the license server should be avoided.

Default *ON*

Accepted *ON, OFF* (see *MSK_onoffkeye*)

Example *MSK_putintparam(task, MSK_IPAR_CACHE_LICENSE, MSK_ON)*

Groups *License manager*

MSK_IPAR_CHECK_CONVEXITY

Specify the level of convexity check on quadratic problems.

Default *FULL*

Accepted *NONE, SIMPLE, FULL* (see *MSK_checkconvexitytypee*)

Example *MSK_putintparam(task, MSK_IPAR_CHECK_CONVEXITY, MSK_CHECK_CONVEXITY_FULL)*

Groups *Data check*

MSK_IPAR_COMPRESS_STATFILE

Control compression of stat files.

Default *ON*

Accepted *ON, OFF* (see *MSK_onoffkeye*)

Example *MSK_putintparam(task, MSK_IPAR_COMPRESS_STATFILE, MSK_ON)*

MSK_IPAR_INFEAS_GENERIC_NAMES

Controls whether generic names are used when an infeasible subproblem is created.

Default *OFF*

Accepted *ON, OFF* (see *MSK_onoffkeye*)

Example *MSK_putintparam(task, MSK_IPAR_INFEAS_GENERIC_NAMES, MSK_OFF)*

Groups *Infeasibility report*

MSK_IPAR_INFEAS_PREFER_PRIMAL

If both certificates of primal and dual infeasibility are supplied then only the primal is used when this option is turned on.

Default *ON*

Accepted *ON, OFF* (see *MSK_onoffkeye*)

Example *MSK_putintparam(task, MSK_IPAR_INFEAS_PREFER_PRIMAL, MSK_ON)*

Groups *Overall solver*

MSK_IPAR_INFEAS_REPORT_AUTO

Controls whether an infeasibility report is automatically produced after the optimization if the problem is primal or dual infeasible.

Default *OFF*

Accepted *ON, OFF* (see *MSK_onoffkeye*)

Example *MSK_putintparam(task, MSK_IPAR_INFEAS_REPORT_AUTO, MSK_OFF)*

Groups *Data input/output, Solution input/output*

MSK_IPAR_INFEAS_REPORT_LEVEL

Controls the amount of information presented in an infeasibility report. Higher values imply more information.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_INFEAS_REPORT_LEVEL, 1)`

Groups *Infeasibility report, Output information*

MSK_IPAR_INTPNT_BASIS

Controls whether the interior-point optimizer also computes an optimal basis.

Default *ALWAYS*

Accepted *NEVER, ALWAYS, NO_ERROR, IF_FEASIBLE, RESERVED* (see *MSKbasindtypee*)

Example `MSK_putintparam(task, MSK_IPAR_INTPNT_BASIS, MSK_BI_ALWAYS)`

See also *MSK_IPAR_BI_IGNORE_MAX_ITER, MSK_IPAR_BI_IGNORE_NUM_ERROR, MSK_IPAR_BI_MAX_ITERATIONS, MSK_IPAR_BI_CLEAN_OPTIMIZER*

Groups *Interior-point method, Basis identification*

MSK_IPAR_INTPNT_DIFF_STEP

Controls whether different step sizes are allowed in the primal and dual space.

Default *ON*

Accepted

- *ON*: Different step sizes are allowed.
- *OFF*: Different step sizes are not allowed.

Example `MSK_putintparam(task, MSK_IPAR_INTPNT_DIFF_STEP, MSK_ON)`

Groups *Interior-point method*

MSK_IPAR_INTPNT_HOTSTART

Currently not in use.

Default *NONE*

Accepted *NONE, PRIMAL, DUAL, PRIMAL_DUAL* (see *MSKintpnthotstarte*)

Example `MSK_putintparam(task, MSK_IPAR_INTPNT_HOTSTART, MSK_INTPNT_HOTSTART_NONE)`

Groups *Interior-point method*

MSK_IPAR_INTPNT_MAX_ITERATIONS

Controls the maximum number of iterations allowed in the interior-point optimizer.

Default 400

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_INTPNT_MAX_ITERATIONS, 400)`

Groups *Interior-point method, Termination criteria*

MSK_IPAR_INTPNT_MAX_NUM_COR

Controls the maximum number of correctors allowed by the multiple corrector procedure. A negative value means that **MOSEK** is making the choice.

Default -1

Accepted [-1; +inf]

Example `MSK_putintparam(task, MSK_IPAR_INTPNT_MAX_NUM_COR, -1)`

Groups *Interior-point method*

MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS

Maximum number of steps to be used by the iterative refinement of the search direction. A negative value implies that the optimizer chooses the maximum number of iterative refinement steps.

Default -1

Accepted [-inf; +inf]

Example MSK_putintparam(task, MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS, -1)

Groups *Interior-point method*

MSK_IPAR_INTPNT_MULTI_THREAD

Controls whether the interior-point optimizers are allowed to employ multiple threads if more threads is available.

Default *ON*

Accepted *ON, OFF* (see *MSK_onoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_INTPNT_MULTI_THREAD, MSK_ON)

Groups *Overall system*

MSK_IPAR_INTPNT_OFF_COL_TRH

Controls how many offending columns are detected in the Jacobian of the constraint matrix.

0	no detection
1	aggressive detection
> 1	higher values mean less aggressive detection

Default 40

Accepted [0; +inf]

Example MSK_putintparam(task, MSK_IPAR_INTPNT_OFF_COL_TRH, 40)

Groups *Interior-point method*

MSK_IPAR_INTPNT_ORDER_GP_NUM_SEEDS

The GP ordering is dependent on a random seed. Therefore, trying several random seeds may lead to a better ordering. This parameter controls the number of random seeds tried.

A value of 0 means that MOSEK makes the choice.

Default 0

Accepted [0; +inf]

Example MSK_putintparam(task, MSK_IPAR_INTPNT_ORDER_GP_NUM_SEEDS, 0)

Groups *Interior-point method*

MSK_IPAR_INTPNT_ORDER_METHOD

Controls the ordering strategy used by the interior-point optimizer when factorizing the Newton equation system.

Default *FREE*

Accepted *FREE, APPMINLOC, EXPERIMENTAL, TRY_GRAPHPAR, FORCE_GRAPHPAR, NONE*
(see *MSK_orderingtypee*)

Example MSK_putintparam(task, MSK_IPAR_INTPNT_ORDER_METHOD, MSK_ORDER_METHOD_FREE)

Groups *Interior-point method*

MSK_IPAR_INTPNT_PURIFY

Currently not in use.

Default *NONE*

Accepted *NONE, PRIMAL, DUAL, PRIMAL_DUAL, AUTO* (see *MSK_purifye*)

Example MSK_putintparam(task, MSK_IPAR_INTPNT_PURIFY, MSK_PURIFY_NONE)

Groups *Interior-point method*

MSK_IPAR_INTPNT_REGULARIZATION_USE

Controls whether regularization is allowed.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_INTPNT_REGULARIZATION_USE, MSK_ON)`

Groups *Interior-point method*

MSK_IPAR_INTPNT_SCALING

Controls how the problem is scaled before the interior-point optimizer is used.

Default *FREE*

Accepted *FREE, NONE, MODERATE, AGGRESSIVE* (see *MSKscalingtypee*)

Example `MSK_putintparam(task, MSK_IPAR_INTPNT_SCALING, MSK_SCALING_FREE)`

Groups *Interior-point method*

MSK_IPAR_INTPNT_SOLVE_FORM

Controls whether the primal or the dual problem is solved.

Default *FREE*

Accepted *FREE, PRIMAL, DUAL* (see *MSKsolveforme*)

Example `MSK_putintparam(task, MSK_IPAR_INTPNT_SOLVE_FORM, MSK_SOLVE_FREE)`

Groups *Interior-point method*

MSK_IPAR_INTPNT_STARTING_POINT

Starting point used by the interior-point optimizer.

Default *FREE*

Accepted *FREE, GUESS, CONSTANT, SATISFY_BOUNDS* (see *MSKstartpointtypee*)

Example `MSK_putintparam(task, MSK_IPAR_INTPNT_STARTING_POINT, MSK_STARTING_POINT_FREE)`

Groups *Interior-point method*

MSK_IPAR_LICENSE_DEBUG

This option is used to turn on debugging of the license manager.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_LICENSE_DEBUG, MSK_OFF)`

Groups *License manager*

MSK_IPAR_LICENSE_PAUSE_TIME

If *MSK_IPAR_LICENSE_WAIT* is *MSK_ON* and no license is available, then **MOSEK** sleeps a number of milliseconds between each check of whether a license has become free.

Default 100

Accepted [0; 1000000]

Example `MSK_putintparam(task, MSK_IPAR_LICENSE_PAUSE_TIME, 100)`

Groups *License manager*

MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS

Controls whether license features expire warnings are suppressed.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS, MSK_OFF)`

Groups *License manager, Output information*

MSK_IPAR_LICENSE_TRH_EXPIRY_WRN

If a license feature expires in a numbers of days less than the value of this parameter then a warning will be issued.

Default 7

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LICENSE_TRH_EXPIRY_WRN, 7)`

Groups *License manager, Output information*

MSK_IPAR_LICENSE_WAIT

If all licenses are in use **MOSEK** returns with an error code. However, by turning on this parameter **MOSEK** will wait for an available license.

Default *OFF*

Accepted *ON, OFF* (see *MSK_onoffkey*)

Example `MSK_putintparam(task, MSK_IPAR_LICENSE_WAIT, MSK_OFF)`

Groups *Overall solver, Overall system, License manager*

MSK_IPAR_LOG

Controls the amount of log information. The value 0 implies that all log information is suppressed. A higher level implies that more information is logged.

Please note that if a task is employed to solve a sequence of optimization problems the value of this parameter is reduced by the value of *MSK_IPAR_LOG_CUT_SECOND_OPT* for the second and any subsequent optimizations.

Default 10

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG, 10)`

See also *MSK_IPAR_LOG_CUT_SECOND_OPT*

Groups *Output information, Logging*

MSK_IPAR_LOG_ANA_PRO

Controls amount of output from the problem analyzer.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_ANA_PRO, 1)`

Groups *Analysis, Logging*

MSK_IPAR_LOG_BI

Controls the amount of output printed by the basis identification procedure. A higher level implies that more information is logged.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_BI, 1)`

Groups *Basis identification, Output information, Logging*

MSK_IPAR_LOG_BI_FREQ

Controls how frequently the optimizer outputs information about the basis identification and how frequent the user-defined callback function is called.

Default 2500

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_BI_FREQ, 2500)`

Groups *Basis identification, Output information, Logging*

MSK_IPAR_LOG_CHECK_CONVEXITY

Controls logging in convexity check on quadratic problems. Set to a positive value to turn logging on. If a quadratic coefficient matrix is found to violate the requirement of PSD (NSD) then a list of negative (positive) pivot elements is printed. The absolute value of the pivot elements is also shown.

Default 0

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_CHECK_CONVEXITY, 0)`

Groups *Data check*

MSK_IPAR_LOG_CUT_SECOND_OPT

If a task is employed to solve a sequence of optimization problems, then the value of the log levels is reduced by the value of this parameter. E.g *MSK_IPAR_LOG* and *MSK_IPAR_LOG_SIM* are reduced by the value of this parameter for the second and any subsequent optimizations.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_CUT_SECOND_OPT, 1)`

See also *MSK_IPAR_LOG*, *MSK_IPAR_LOG_INTPNT*, *MSK_IPAR_LOG_MIO*,
MSK_IPAR_LOG_SIM

Groups *Output information, Logging*

MSK_IPAR_LOG_EXPAND

Controls the amount of logging when a data item such as the maximum number constraints is expanded.

Default 0

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_EXPAND, 0)`

Groups *Output information, Logging*

MSK_IPAR_LOG_FEAS_REPAIR

Controls the amount of output printed when performing feasibility repair. A value higher than one means extensive logging.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_FEAS_REPAIR, 1)`

Groups *Output information, Logging*

MSK_IPAR_LOG_FILE

If turned on, then some log info is printed when a file is written or read.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_FILE, 1)`

Groups *Data input/output, Output information, Logging*

MSK_IPAR_LOG_INCLUDE_SUMMARY

If on, then the solution summary will be printed by *MSK_optimize*, so a separate call to *MSK_solutionsummary* is not necessary.

Default *OFF*

Accepted *ON*, *OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_LOG_INCLUDE_SUMMARY, MSK_OFF)`

Groups *Output information, Logging*

MSK_IPAR_LOG_INFEAS_ANA

Controls amount of output printed by the infeasibility analyzer procedures. A higher level implies that more information is logged.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_INFEAS_ANA, 1)`

Groups *Infeasibility report, Output information, Logging*

MSK_IPAR_LOG_INTPNT

Controls amount of output printed by the interior-point optimizer. A higher level implies that more information is logged.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_INTPNT, 1)`

Groups *Interior-point method, Output information, Logging*

MSK_IPAR_LOG_LOCAL_INFO

Controls whether local identifying information like environment variables, filenames, IP addresses etc. are printed to the log.

Note that this will only affect some functions. Some functions that specifically emit system information will not be affected.

Default *ON*

Accepted *ON, OFF* (see *MSK_onoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_LOG_LOCAL_INFO, MSK_ON)`

Groups *Output information, Logging*

MSK_IPAR_LOG_MIO

Controls the log level for the mixed-integer optimizer. A higher level implies that more information is logged.

Default 4

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_MIO, 4)`

Groups *Mixed-integer optimization, Output information, Logging*

MSK_IPAR_LOG_MIO_FREQ

Controls how frequent the mixed-integer optimizer prints the log line. It will print line every time *MSK_IPAR_LOG_MIO_FREQ* relaxations have been solved.

Default 10

Accepted [-inf; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_MIO_FREQ, 10)`

Groups *Mixed-integer optimization, Output information, Logging*

MSK_IPAR_LOG_ORDER

If turned on, then factor lines are added to the log.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_ORDER, 1)`

Groups *Output information, Logging*

MSK_IPAR_LOG_PRESOLVE

Controls amount of output printed by the presolve procedure. A higher level implies that more information is logged.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_PRESOLVE, 1)`

Groups *Logging*

MSK_IPAR_LOG_RESPONSE

Controls amount of output printed when response codes are reported. A higher level implies that more information is logged.

Default 0

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_RESPONSE, 0)`

Groups *Output information, Logging*

MSK_IPAR_LOG_SENSITIVITY

Controls the amount of logging during the sensitivity analysis.

- 0. Means no logging information is produced.
- 1. Timing information is printed.
- 2. Sensitivity results are printed.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_SENSITIVITY, 1)`

Groups *Output information, Logging*

MSK_IPAR_LOG_SENSITIVITY_OPT

Controls the amount of logging from the optimizers employed during the sensitivity analysis. 0 means no logging information is produced.

Default 0

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_SENSITIVITY_OPT, 0)`

Groups *Output information, Logging*

MSK_IPAR_LOG_SIM

Controls amount of output printed by the simplex optimizer. A higher level implies that more information is logged.

Default 4

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_SIM, 4)`

Groups *Simplex optimizer, Output information, Logging*

MSK_IPAR_LOG_SIM_FREQ

Controls how frequent the simplex optimizer outputs information about the optimization and how frequent the user-defined callback function is called.

Default 1000

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_SIM_FREQ, 1000)`

Groups *Simplex optimizer, Output information, Logging*

MSK_IPAR_LOG_SIM_MINOR

Currently not in use.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_LOG_SIM_MINOR, 1)`

Groups *Simplex optimizer, Output information*

MSK_IPAR_LOG_STORAGE

When turned on, **MOSEK** prints messages regarding the storage usage and allocation.

Default 0

Accepted [0; +inf]

Example MSK_putintparam(task, MSK_IPAR_LOG_STORAGE, 0)

Groups *Output information, Overall system, Logging*

MSK_IPAR_MAX_NUM_WARNINGS

Each warning is shown a limited number of times controlled by this parameter. A negative value is identical to infinite number of times.

Default 10

Accepted [-inf; +inf]

Example MSK_putintparam(task, MSK_IPAR_MAX_NUM_WARNINGS, 10)

Groups *Output information*

MSK_IPAR_MIO_BRANCH_DIR

Controls whether the mixed-integer optimizer is branching up or down by default.

Default *FREE*

Accepted *FREE, UP, DOWN, NEAR, FAR, ROOT_LP, GUIDED, PSEUDOCOST* (see *MSKbranchdire*)

Example MSK_putintparam(task, MSK_IPAR_MIO_BRANCH_DIR, MSK_BRANCH_DIR_FREE)

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_CONIC_OUTER_APPROXIMATION

If this option is turned on outer approximation is used when solving relaxations of conic problems; otherwise interior point is used.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_MIO_CONIC_OUTER_APPROXIMATION, MSK_OFF)

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_CLIQUE

Controls whether clique cuts should be generated.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_MIO_CUT_CLIQUE, MSK_ON)

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_CMIR

Controls whether mixed integer rounding cuts should be generated.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_MIO_CUT_CMIR, MSK_ON)

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_GMI

Controls whether GMI cuts should be generated.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_MIO_CUT_GMI, MSK_ON)

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_IMPLIED_BOUND

Controls whether implied bound cuts should be generated.

Default *OFF*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_MIO_CUT_IMPLIED_BOUND, MSK_OFF)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_KNAPSACK_COVER

Controls whether knapsack cover cuts should be generated.

Default *OFF*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_MIO_CUT_KNAPSACK_COVER, MSK_OFF)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_SELECTION_LEVEL

Controls how aggressively generated cuts are selected to be included in the relaxation.

- -1. The optimizer chooses the level of cut selection
- 0. Generated cuts less likely to be added to the relaxation
- 1. Cuts are more aggressively selected to be included in the relaxation

Default -1

Accepted [-1; +1]

Example `MSK_putintparam(task, MSK_IPAR_MIO_CUT_SELECTION_LEVEL, -1)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_FEASPUMP_LEVEL

Controls the way the Feasibility Pump heuristic is employed by the mixed-integer optimizer.

- -1. The optimizer chooses how the Feasibility Pump is used
- 0. The Feasibility Pump is disabled
- 1. The Feasibility Pump is enabled with an effort to improve solution quality
- 2. The Feasibility Pump is enabled with an effort to reach feasibility early

Default -1

Accepted [-1; 2]

Example `MSK_putintparam(task, MSK_IPAR_MIO_FEASPUMP_LEVEL, -1)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_HEURISTIC_LEVEL

Controls the heuristic employed by the mixed-integer optimizer to locate an initial good integer feasible solution. A value of zero means the heuristic is not used at all. A larger value than 0 means that a gradually more sophisticated heuristic is used which is computationally more expensive. A negative value implies that the optimizer chooses the heuristic. Normally a value around 3 to 5 should be optimal.

Default -1

Accepted [-inf; +inf]

Example `MSK_putintparam(task, MSK_IPAR_MIO_HEURISTIC_LEVEL, -1)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_MAX_NUM_BRANCHES

Maximum number of branches allowed during the branch and bound search. A negative value means infinite.

Default -1

Accepted [-inf; +inf]

Example `MSK_putintparam(task, MSK_IPAR_MIO_MAX_NUM_BRANCHES, -1)`

Groups *Mixed-integer optimization, Termination criteria*

MSK_IPAR_MIO_MAX_NUM_RELAXS

Maximum number of relaxations allowed during the branch and bound search. A negative value means infinite.

Default -1

Accepted [-inf; +inf]

Example `MSK_putintparam(task, MSK_IPAR_MIO_MAX_NUM_RELAXS, -1)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_MAX_NUM_ROOT_CUT_ROUNDS

Maximum number of cut separation rounds at the root node.

Default 100

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_MIO_MAX_NUM_ROOT_CUT_ROUNDS, 100)`

Groups *Mixed-integer optimization, Termination criteria*

MSK_IPAR_MIO_MAX_NUM_SOLUTIONS

The mixed-integer optimizer can be terminated after a certain number of different feasible solutions has been located. If this parameter has the value $n > 0$, then the mixed-integer optimizer will be terminated when n feasible solutions have been located.

Default -1

Accepted [-inf; +inf]

Example `MSK_putintparam(task, MSK_IPAR_MIO_MAX_NUM_SOLUTIONS, -1)`

Groups *Mixed-integer optimization, Termination criteria*

MSK_IPAR_MIO_MODE

Controls whether the optimizer includes the integer restrictions when solving a (mixed) integer optimization problem.

Default *SATISFIED*

Accepted *IGNORED, SATISFIED* (see *MSKmiomodee*)

Example `MSK_putintparam(task, MSK_IPAR_MIO_MODE, MSK_MIO_MODE_SATISFIED)`

Groups *Overall solver*

MSK_IPAR_MIO_NODE_OPTIMIZER

Controls which optimizer is employed at the non-root nodes in the mixed-integer optimizer.

Default *FREE*

Accepted *FREE, INTPNT, CONIC, PRIMAL_SIMPLEX, DUAL_SIMPLEX, FREE_SIMPLEX, MIXED_INT* (see *MSKoptimizertypee*)

Example `MSK_putintparam(task, MSK_IPAR_MIO_NODE_OPTIMIZER, MSK_OPTIMIZER_FREE)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_NODE_SELECTION

Controls the node selection strategy employed by the mixed-integer optimizer.

Default *FREE*

Accepted *FREE, FIRST, BEST, PSEUDO* (see *MSKmionodeseltypee*)

Example `MSK_putintparam(task, MSK_IPAR_MIO_NODE_SELECTION, MSK_MIO_NODE_SELECTION_FREE)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_PERSPECTIVE_REFORMULATE

Enables or disables perspective reformulation in presolve.

Default *ON*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_MIO_PERSPECTIVE_REFORMULATE, MSK_ON)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_PROBING_LEVEL

Controls the amount of probing employed by the mixed-integer optimizer in presolve.

- -1. The optimizer chooses the level of probing employed
- 0. Probing is disabled
- 1. A low amount of probing is employed
- 2. A medium amount of probing is employed
- 3. A high amount of probing is employed

Default -1

Accepted [-1; 3]

Example `MSK_putintparam(task, MSK_IPAR_MIO_PROBING_LEVEL, -1)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_PROPAGATE_OBJECTIVE_CONSTRAINT

Use objective domain propagation.

Default *OFF*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_MIO_PROPAGATE_OBJECTIVE_CONSTRAINT, MSK_OFF)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_RINS_MAX_NODES

Controls the maximum number of nodes allowed in each call to the RINS heuristic. The default value of -1 means that the value is determined automatically. A value of zero turns off the heuristic.

Default -1

Accepted [-1; +inf]

Example `MSK_putintparam(task, MSK_IPAR_MIO_RINS_MAX_NODES, -1)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_ROOT_OPTIMIZER

Controls which optimizer is employed at the root node in the mixed-integer optimizer.

Default *FREE*

Accepted *FREE, INTPNT, CONIC, PRIMAL_SIMPLEX, DUAL_SIMPLEX, FREE_SIMPLEX, MIXED_INT* (see *MSKOptimizertypee*)

Example `MSK_putintparam(task, MSK_IPAR_MIO_ROOT_OPTIMIZER, MSK_OPTIMIZER_FREE)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_ROOT_REPEAT_PRESOLVE_LEVEL

Controls whether presolve can be repeated at root node.

- -1. The optimizer chooses whether presolve is repeated
- 0. Never repeat presolve
- 1. Always repeat presolve

Default -1

Accepted [-1; 1]

Example `MSK_putintparam(task, MSK_IPAR_MIO_ROOT_REPEAT_PREOLVE_LEVEL, -1)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_SEED

Sets the random seed used for randomization in the mixed integer optimizer. Selecting a different seed can change the path the optimizer takes to the optimal solution.

Default 42

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_MIO_SEED, 42)`

Groups *Mixed-integer optimization*

MSK_IPAR_MIO_VB_DETECTION_LEVEL

Controls how much effort is put into detecting variable bounds.

- -1. The optimizer chooses
- 0. No variable bounds are detected
- 1. Only detect variable bounds that are directly represented in the problem
- 2. Detect variable bounds in probing

Default -1

Accepted [-1; +2]

Example `MSK_putintparam(task, MSK_IPAR_MIO_VB_DETECTION_LEVEL, -1)`

Groups *Mixed-integer optimization*

MSK_IPAR_MT_SPINCOUNT

Set the number of iterations to spin before sleeping.

Default 0

Accepted [0; 1000000000]

Example `MSK_putintparam(task, MSK_IPAR_MT_SPINCOUNT, 0)`

Groups *Overall system*

MSK_IPAR_NUM_THREADS

Controls the number of threads employed by the optimizer. If set to 0 the number of threads used will be equal to the number of cores detected on the machine.

If using the conic optimizer, the value of this parameter set at first optimization remains constant through the lifetime of the process. **MOSEK** will allocate a thread pool of given size, and changing the parameter value later will have no effect. It will, however, remain possible to demand single-threaded execution by setting *MSK_IPAR_INTPNT_MULTI_THREAD*.

For the mixed-integer optimizer and interior-point linear optimizer there is no such restriction.

Default 0

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_NUM_THREADS, 0)`

Groups *Overall system*

MSK_IPAR_OPF_WRITE_HEADER

Write a text header with date and **MOSEK** version in an OPF file.

Default *ON*

Accepted *ON*, *OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_OPF_WRITE_HEADER, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_OPF_WRITE_HINTS

Write a hint section with problem dimensions in the beginning of an OPF file.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_OPF_WRITE_HINTS, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_OPF_WRITE_LINE_LENGTH

Aim to keep lines in OPF files not much longer than this.

Default 80

Accepted `[0; +inf]`

Example `MSK_putintparam(task, MSK_IPAR_OPF_WRITE_LINE_LENGTH, 80)`

Groups *Data input/output*

MSK_IPAR_OPF_WRITE_PARAMETERS

Write a parameter section in an OPF file.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_OPF_WRITE_PARAMETERS, MSK_OFF)`

Groups *Data input/output*

MSK_IPAR_OPF_WRITE_PROBLEM

Write objective, constraints, bounds etc. to an OPF file.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_OPF_WRITE_PROBLEM, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_OPF_WRITE_SOL_BAS

If *MSK_IPAR_OPF_WRITE_SOLUTIONS* is *MSK_ON* and a basic solution is defined, include the basic solution in OPF files.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_OPF_WRITE_SOL_BAS, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_OPF_WRITE_SOL_ITG

If *MSK_IPAR_OPF_WRITE_SOLUTIONS* is *MSK_ON* and an integer solution is defined, write the integer solution in OPF files.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_OPF_WRITE_SOL_ITG, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_OPF_WRITE_SOL_ITR

If *MSK_IPAR_OPF_WRITE_SOLUTIONS* is *MSK_ON* and an interior solution is defined, write the interior solution in OPF files.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_OPF_WRITE_SOL_ITR, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_OPF_WRITE_SOLUTIONS

Enable inclusion of solutions in the OPF files.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_OPF_WRITE_SOLUTIONS, MSK_OFF)`

Groups *Data input/output*

MSK_IPAR_OPTIMIZER

The parameter controls which optimizer is used to optimize the task.

Default *FREE*

Accepted *FREE, INTPNT, CONIC, PRIMAL_SIMPLEX, DUAL_SIMPLEX, FREE_SIMPLEX, MIXED_INT* (see *MSKoptimizertypee*)

Example `MSK_putintparam(task, MSK_IPAR_OPTIMIZER, MSK_OPTIMIZER_FREE)`

Groups *Overall solver*

MSK_IPAR_PARAM_READ_CASE_NAME

If turned on, then names in the parameter file are case sensitive.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_PARAM_READ_CASE_NAME, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_PARAM_READ_IGN_ERROR

If turned on, then errors in parameter settings is ignored.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_PARAM_READ_IGN_ERROR, MSK_OFF)`

Groups *Data input/output*

MSK_IPAR_PREOLVE_ELIMINATOR_MAX_FILL

Controls the maximum amount of fill-in that can be created by one pivot in the elimination phase of the presolve. A negative value means the parameter value is selected automatically.

Default *-1*

Accepted *[-inf; +inf]*

Example `MSK_putintparam(task, MSK_IPAR_PREOLVE_ELIMINATOR_MAX_FILL, -1)`

Groups *Presolve*

MSK_IPAR_PREOLVE_ELIMINATOR_MAX_NUM_TRIES

Control the maximum number of times the eliminator is tried. A negative value implies **MOSEK** decides.

Default *-1*

Accepted *[-inf; +inf]*

Example `MSK_putintparam(task, MSK_IPAR_PREOLVE_ELIMINATOR_MAX_NUM_TRIES, -1)`

Groups *Presolve*

MSK_IPAR_PREOLVE_LEVEL

Currently not used.

Default *-1*

Accepted *[-inf; +inf]*

Example `MSK_putintparam(task, MSK_IPAR_PREOLVE_LEVEL, -1)`

Groups *Overall solver, Presolve*

MSK_IPAR_PREOLVE_LINDEP_ABS_WORK_TRH

Controls linear dependency check in presolve. The linear dependency check is potentially computationally expensive.

Default 100

Accepted [-inf; +inf]

Example MSK_putintparam(task, MSK_IPAR_PREOLVE_LINDEP_ABS_WORK_TRH, 100)

Groups *Presolve*

MSK_IPAR_PREOLVE_LINDEP_REL_WORK_TRH

Controls linear dependency check in presolve. The linear dependency check is potentially computationally expensive.

Default 100

Accepted [-inf; +inf]

Example MSK_putintparam(task, MSK_IPAR_PREOLVE_LINDEP_REL_WORK_TRH, 100)

Groups *Presolve*

MSK_IPAR_PREOLVE_LINDEP_USE

Controls whether the linear constraints are checked for linear dependencies.

Default *ON*

Accepted *ON*, *OFF* (see *MSK_onoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_PREOLVE_LINDEP_USE, MSK_ON)

Groups *Presolve*

MSK_IPAR_PREOLVE_MAX_NUM_PASS

Control the maximum number of times presolve passes over the problem. A negative value implies MOSEK decides.

Default -1

Accepted [-inf; +inf]

Example MSK_putintparam(task, MSK_IPAR_PREOLVE_MAX_NUM_PASS, -1)

Groups *Presolve*

MSK_IPAR_PREOLVE_MAX_NUM_REDUCTIONS

Controls the maximum number of reductions performed by the presolve. The value of the parameter is normally only changed in connection with debugging. A negative value implies that an infinite number of reductions are allowed.

Default -1

Accepted [-inf; +inf]

Example MSK_putintparam(task, MSK_IPAR_PREOLVE_MAX_NUM_REDUCTIONS, -1)

Groups *Overall solver*, *Presolve*

MSK_IPAR_PREOLVE_USE

Controls whether the presolve is applied to a problem before it is optimized.

Default *FREE*

Accepted *OFF*, *ON*, *FREE* (see *MSK_presolvemodee*)

Example MSK_putintparam(task, MSK_IPAR_PREOLVE_USE, MSK_PREOLVE_MODE_FREE)

Groups *Overall solver*, *Presolve*

MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER

Controls which optimizer that is used to find the optimal repair.

Default *FREE*

Accepted *FREE, INTPNT, CONIC, PRIMAL_SIMPLEX, DUAL_SIMPLEX, FREE_SIMPLEX, MIXED_INT* (see *MSKoptimizertypee*)

Example `MSK_putintparam(task, MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER, MSK_OPTIMIZER_FREE)`

Groups *Overall solver*

MSK_IPAR_PTF_WRITE_TRANSFORM

If *MSK_IPAR_PTF_WRITE_TRANSFORM* is *MSK_ON*, constraint blocks with identifiable conic slacks are transformed into conic constraints and the slacks are eliminated.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_PTF_WRITE_TRANSFORM, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_READ_DEBUG

Turns on additional debugging information when reading files.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_READ_DEBUG, MSK_OFF)`

Groups *Data input/output*

MSK_IPAR_READ_KEEP_FREE_CON

Controls whether the free constraints are included in the problem.

Default *OFF*

Accepted

- *ON*: The free constraints are kept.
- *OFF*: The free constraints are discarded.

Example `MSK_putintparam(task, MSK_IPAR_READ_KEEP_FREE_CON, MSK_OFF)`

Groups *Data input/output*

MSK_IPAR_READ_LP_DROP_NEW_VARS_IN_BOU

If this option is turned on, **MOSEK** will drop variables that are defined for the first time in the bounds section.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_READ_LP_DROP_NEW_VARS_IN_BOU, MSK_OFF)`

Groups *Data input/output*

MSK_IPAR_READ_LP_QUOTED_NAMES

If a name is in quotes when reading an LP file, the quotes will be removed.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_READ_LP_QUOTED_NAMES, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_READ_MPS_FORMAT

Controls how strictly the MPS file reader interprets the MPS format.

Default *FREE*

Accepted *STRICT, RELAXED, FREE, CPLEX* (see *MSKmpsformat*)

Example `MSK_putintparam(task, MSK_IPAR_READ_MPS_FORMAT, MSK_MPS_FORMAT_FREE)`

Groups *Data input/output*

MSK_IPAR_READ_MPS_WIDTH

Controls the maximal number of characters allowed in one line of the MPS file.

Default 1024

Accepted [80; +inf]

Example MSK_putintparam(task, MSK_IPAR_READ_MPS_WIDTH, 1024)

Groups *Data input/output*

MSK_IPAR_READ_TASK_IGNORE_PARAM

Controls whether **MOSEK** should ignore the parameter setting defined in the task file and use the default parameter setting instead.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_READ_TASK_IGNORE_PARAM, MSK_OFF)

Groups *Data input/output*

MSK_IPAR_REMOVE_UNUSED_SOLUTIONS

Removes unused solutions before the optimization is performed.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_REMOVE_UNUSED_SOLUTIONS, MSK_OFF)

Groups *Overall system*

MSK_IPAR_SENSITIVITY_ALL

If set to *MSK_ON*, then *MSK_sensitivityreport* analyzes all bounds and variables instead of reading a specification from the file.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example MSK_putintparam(task, MSK_IPAR_SENSITIVITY_ALL, MSK_OFF)

Groups *Overall solver*

MSK_IPAR_SENSITIVITY_OPTIMIZER

Controls which optimizer is used for optimal partition sensitivity analysis.

Default *FREE_SIMPLEX*

Accepted *FREE, INTPNT, CONIC, PRIMAL_SIMPLEX, DUAL_SIMPLEX, FREE_SIMPLEX, MIXED_INT* (see *MSKoptimizertypee*)

Example MSK_putintparam(task, MSK_IPAR_SENSITIVITY_OPTIMIZER, MSK_OPTIMIZER_FREE_SIMPLEX)

Groups *Overall solver, Simplex optimizer*

MSK_IPAR_SENSITIVITY_TYPE

Controls which type of sensitivity analysis is to be performed.

Default *BASIS*

Accepted *BASIS* (see *MSKsensitivitytypee*)

Example MSK_putintparam(task, MSK_IPAR_SENSITIVITY_TYPE, MSK_SENSITIVITY_TYPE_BASIS)

Groups *Overall solver*

MSK_IPAR_SIM_BASIS_FACTOR_USE

Controls whether an LU factorization of the basis is used in a hot-start. Forcing a refactorization sometimes improves the stability of the simplex optimizers, but in most cases there is a performance penalty.

Default *ON*

Accepted *ON, OFF* (see *MSK_{onoffkeye}*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_BASIS_FACTOR_USE, MSK_ON)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_DEGEN

Controls how aggressively degeneration is handled.

Default *FREE*

Accepted *NONE, FREE, AGGRESSIVE, MODERATE, MINIMUM* (see *MSK_{simdegene}*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_DEGEN, MSK_SIM_DEGEN_FREE)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_DUAL_CRASH

Controls whether crashing is performed in the dual simplex optimizer. If this parameter is set to x , then a crash will be performed if a basis consists of more than $(100 - x) \bmod f_v$ entries, where f_v is the number of fixed variables.

Default 90

Accepted $[0; +\infty]$

Example `MSK_putintparam(task, MSK_IPAR_SIM_DUAL_CRASH, 90)`

Groups *Dual simplex*

MSK_IPAR_SIM_DUAL_PHASEONE_METHOD

An experimental feature.

Default 0

Accepted $[0; 10]$

Example `MSK_putintparam(task, MSK_IPAR_SIM_DUAL_PHASEONE_METHOD, 0)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_DUAL_RESTRICT_SELECTION

The dual simplex optimizer can use a so-called restricted selection/pricing strategy to choose the outgoing variable. Hence, if restricted selection is applied, then the dual simplex optimizer first choose a subset of all the potential outgoing variables. Next, for some time it will choose the outgoing variable only among the subset. From time to time the subset is redefined. A larger value of this parameter implies that the optimizer will be more aggressive in its restriction strategy, i.e. a value of 0 implies that the restriction strategy is not applied at all.

Default 50

Accepted $[0; 100]$

Example `MSK_putintparam(task, MSK_IPAR_SIM_DUAL_RESTRICT_SELECTION, 50)`

Groups *Dual simplex*

MSK_IPAR_SIM_DUAL_SELECTION

Controls the choice of the incoming variable, known as the selection strategy, in the dual simplex optimizer.

Default *FREE*

Accepted *FREE, FULL, ASE, DEVEX, SE, PARTIAL* (see *MSK_{simseltypee}*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_DUAL_SELECTION, MSK_SIM_SELECTION_FREE)`

Groups *Dual simplex*

MSK_IPAR_SIM_EXPLOIT_DUPVEC

Controls if the simplex optimizers are allowed to exploit duplicated columns.

Default *OFF*

Accepted *ON, OFF, FREE* (see *MSK_{simdupvece}*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_EXPLOIT_DUPVEC, MSK_SIM_EXPLOIT_DUPVEC_OFF)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_HOTSTART

Controls the type of hot-start that the simplex optimizer perform.

Default *FREE*

Accepted *NONE, FREE, STATUS_KEYS* (see *MSKsimhotstarte*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_HOTSTART, MSK_SIM_HOTSTART_FREE)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_HOTSTART_LU

Determines if the simplex optimizer should exploit the initial factorization.

Default *ON*

Accepted

- *ON*: Factorization is reused if possible.
- *OFF*: Factorization is recomputed.

Example `MSK_putintparam(task, MSK_IPAR_SIM_HOTSTART_LU, MSK_ON)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_MAX_ITERATIONS

Maximum number of iterations that can be used by a simplex optimizer.

Default 10000000

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_SIM_MAX_ITERATIONS, 10000000)`

Groups *Simplex optimizer, Termination criteria*

MSK_IPAR_SIM_MAX_NUM_SETBACKS

Controls how many set-backs are allowed within a simplex optimizer. A set-back is an event where the optimizer moves in the wrong direction. This is impossible in theory but may happen due to numerical problems.

Default 250

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_SIM_MAX_NUM_SETBACKS, 250)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_NON_SINGULAR

Controls if the simplex optimizer ensures a non-singular basis, if possible.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_NON_SINGULAR, MSK_ON)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_PRIMAL_CRASH

Controls whether crashing is performed in the primal simplex optimizer. In general, if a basis consists of more than (100-this parameter value)% fixed variables, then a crash will be performed.

Default 90

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_SIM_PRIMAL_CRASH, 90)`

Groups *Primal simplex*

MSK_IPAR_SIM_PRIMAL_PHASEONE_METHOD

An experimental feature.

Default 0

Accepted [0; 10]

Example `MSK_putintparam(task, MSK_IPAR_SIM_PRIMAL_PHASEONE_METHOD, 0)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_PRIMAL_RESTRICT_SELECTION

The primal simplex optimizer can use a so-called restricted selection/pricing strategy to choose the outgoing variable. Hence, if restricted selection is applied, then the primal simplex optimizer first choose a subset of all the potential incoming variables. Next, for some time it will choose the incoming variable only among the subset. From time to time the subset is redefined. A larger value of this parameter implies that the optimizer will be more aggressive in its restriction strategy, i.e. a value of 0 implies that the restriction strategy is not applied at all.

Default 50

Accepted [0; 100]

Example `MSK_putintparam(task, MSK_IPAR_SIM_PRIMAL_RESTRICT_SELECTION, 50)`

Groups *Primal simplex*

MSK_IPAR_SIM_PRIMAL_SELECTION

Controls the choice of the incoming variable, known as the selection strategy, in the primal simplex optimizer.

Default *FREE*

Accepted *FREE, FULL, ASE, DEVEX, SE, PARTIAL* (see *MSKsimseltypee*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_PRIMAL_SELECTION, MSK_SIM_SELECTION_FREE)`

Groups *Primal simplex*

MSK_IPAR_SIM_REFACTOR_FREQ

Controls how frequent the basis is refactorized. The value 0 means that the optimizer determines the best point of refactorization. It is strongly recommended NOT to change this parameter.

Default 0

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_SIM_REFACTOR_FREQ, 0)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_REFORMULATION

Controls if the simplex optimizers are allowed to reformulate the problem.

Default *OFF*

Accepted *ON, OFF, FREE, AGGRESSIVE* (see *MSKsimreforme*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_REFORMULATION, MSK_SIM_REFORMULATION_OFF)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_SAVE_LU

Controls if the LU factorization stored should be replaced with the LU factorization corresponding to the initial basis.

Default *OFF*

Accepted *ON, OFF* (see *MSKnonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_SAVE_LU, MSK_OFF)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_SCALING

Controls how much effort is used in scaling the problem before a simplex optimizer is used.

Default *FREE*

Accepted *FREE, NONE, MODERATE, AGGRESSIVE* (see *MSKscalingtypee*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_SCALING, MSK_SCALING_FREE)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_SCALING_METHOD

Controls how the problem is scaled before a simplex optimizer is used.

Default *POW2*

Accepted *POW2, FREE* (see *MSKscalingmethode*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_SCALING_METHOD, MSK_SCALING_METHOD_POW2)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_SEED

Sets the random seed used for randomization in the simplex optimizers.

Default 23456

Accepted [0; 32749]

Example `MSK_putintparam(task, MSK_IPAR_SIM_SEED, 23456)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_SOLVE_FORM

Controls whether the primal or the dual problem is solved by the primal-/dual-simplex optimizer.

Default *FREE*

Accepted *FREE, PRIMAL, DUAL* (see *MSKsolveforme*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_SOLVE_FORM, MSK_SOLVE_FREE)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_STABILITY_PRIORITY

Controls how high priority the numerical stability should be given.

Default 50

Accepted [0; 100]

Example `MSK_putintparam(task, MSK_IPAR_SIM_STABILITY_PRIORITY, 50)`

Groups *Simplex optimizer*

MSK_IPAR_SIM_SWITCH_OPTIMIZER

The simplex optimizer sometimes chooses to solve the dual problem instead of the primal problem. This implies that if you have chosen to use the dual simplex optimizer and the problem is dualized, then it actually makes sense to use the primal simplex optimizer instead. If this parameter is on and the problem is dualized and furthermore the simplex optimizer is chosen to be the primal (dual) one, then it is switched to the dual (primal).

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_SIM_SWITCH_OPTIMIZER, MSK_OFF)`

Groups *Simplex optimizer*

MSK_IPAR_SOL_FILTER_KEEP_BASIC

If turned on, then basic and super basic constraints and variables are written to the solution file independent of the filter setting.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_SOL_FILTER_KEEP_BASIC, MSK_OFF)`

Groups *Solution input/output*

MSK_IPAR_SOL_FILTER_KEEP_RANGED

If turned on, then ranged constraints and variables are written to the solution file independent of the filter setting.

Default *OFF*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_SOL_FILTER_KEEP_RANGED, MSK_OFF)`

Groups *Solution input/output*

MSK_IPAR_SOL_READ_NAME_WIDTH

When a solution is read by **MOSEK** and some constraint, variable or cone names contain blanks, then a maximum name width must be specified. A negative value implies that no name contains blanks.

Default *-1*

Accepted *[-inf; +inf]*

Example `MSK_putintparam(task, MSK_IPAR_SOL_READ_NAME_WIDTH, -1)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_SOL_READ_WIDTH

Controls the maximal acceptable width of line in the solutions when read by **MOSEK**.

Default *1024*

Accepted *[80; +inf]*

Example `MSK_putintparam(task, MSK_IPAR_SOL_READ_WIDTH, 1024)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_SOLUTION_CALLBACK

Indicates whether solution callbacks will be performed during the optimization.

Default *OFF*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_SOLUTION_CALLBACK, MSK_OFF)`

Groups *Progress callback, Overall solver*

MSK_IPAR_TIMING_LEVEL

Controls the amount of timing performed inside **MOSEK**.

Default *1*

Accepted *[0; +inf]*

Example `MSK_putintparam(task, MSK_IPAR_TIMING_LEVEL, 1)`

Groups *Overall system*

MSK_IPAR_WRITE_BAS_CONSTRAINTS

Controls whether the constraint section is written to the basic solution file.

Default *ON*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_BAS_CONSTRAINTS, MSK_ON)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_BAS_HEAD

Controls whether the header section is written to the basic solution file.

Default *ON*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_BAS_HEAD, MSK_ON)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_BAS_VARIABLES

Controls whether the variables section is written to the basic solution file.

Default *ON*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_BAS_VARIABLES, MSK_ON)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_COMPRESSION

Controls whether the data file is compressed while it is written. 0 means no compression while higher values mean more compression.

Default 9

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_WRITE_COMPRESSION, 9)`

Groups *Data input/output*

MSK_IPAR_WRITE_DATA_PARAM

If this option is turned on the parameter settings are written to the data file as parameters.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_DATA_PARAM, MSK_OFF)`

Groups *Data input/output*

MSK_IPAR_WRITE_FREE_CON

Controls whether the free constraints are written to the data file.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_FREE_CON, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_WRITE_GENERIC_NAMES

Controls whether generic names should be used instead of user-defined names when writing to the data file.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_GENERIC_NAMES, MSK_OFF)`

Groups *Data input/output*

MSK_IPAR_WRITE_GENERIC_NAMES_IO

Index origin used in generic names.

Default 1

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_WRITE_GENERIC_NAMES_IO, 1)`

Groups *Data input/output*

MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_ITEMS

Controls if the writer ignores incompatible problem items when writing files.

Default *OFF*

Accepted

- *ON*: Ignore items that cannot be written to the current output file format.
- *OFF*: Produce an error if the problem contains items that cannot be written to the current output file format.

Example `MSK_putintparam(task, MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_ITEMS, MSK_OFF)`

Groups *Data input/output*

MSK_IPAR_WRITE_INT_CONSTRAINTS

Controls whether the constraint section is written to the integer solution file.

Default *ON*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_INT_CONSTRAINTS, MSK_ON)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_INT_HEAD

Controls whether the header section is written to the integer solution file.

Default *ON*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_INT_HEAD, MSK_ON)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_INT_VARIABLES

Controls whether the variables section is written to the integer solution file.

Default *ON*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_INT_VARIABLES, MSK_ON)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_LP_FULL_OBJ

Write all variables, including the ones with 0-coefficients, in the objective.

Default *ON*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_LP_FULL_OBJ, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_WRITE_LP_LINE_WIDTH

Maximum width of line in an LP file written by **MOSEK**.

Default 80

Accepted [40; +inf]

Example `MSK_putintparam(task, MSK_IPAR_WRITE_LP_LINE_WIDTH, 80)`

Groups *Data input/output*

MSK_IPAR_WRITE_LP_QUOTED_NAMES

If this option is turned on, then **MOSEK** will quote invalid LP names when writing an LP file.

Default *ON*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_LP_QUOTED_NAMES, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_WRITE_LP_STRICT_FORMAT

Controls whether LP output files satisfy the LP format strictly.

Default *OFF*

Accepted *ON, OFF* (see *MSKOnoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_LP_STRICT_FORMAT, MSK_OFF)`

Groups *Data input/output*

MSK_IPAR_WRITE_LP_TERMS_PER_LINE

Maximum number of terms on a single line in an LP file written by **MOSEK**. 0 means unlimited.

Default 10

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_WRITE_LP_TERMS_PER_LINE, 10)`

Groups *Data input/output*

MSK_IPAR_WRITE_MPS_FORMAT

Controls in which format the MPS is written.

Default *FREE*

Accepted *STRICT, RELAXED, FREE, CPLEX* (see *MSKmpsformat*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_MPS_FORMAT,
MSK_MPS_FORMAT_FREE)`

Groups *Data input/output*

MSK_IPAR_WRITE_MPS_INT

Controls if marker records are written to the MPS file to indicate whether variables are integer restricted.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_MPS_INT, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_WRITE_PRECISION

Controls the precision with which double numbers are printed in the MPS data file. In general it is not worthwhile to use a value higher than 15.

Default 15

Accepted [0; +inf]

Example `MSK_putintparam(task, MSK_IPAR_WRITE_PRECISION, 15)`

Groups *Data input/output*

MSK_IPAR_WRITE_SOL_BARVARIABLES

Controls whether the symmetric matrix variables section is written to the solution file.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_SOL_BARVARIABLES, MSK_ON)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_SOL_CONSTRAINTS

Controls whether the constraint section is written to the solution file.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_SOL_CONSTRAINTS, MSK_ON)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_SOL_HEAD

Controls whether the header section is written to the solution file.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_SOL_HEAD, MSK_ON)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES

Even if the names are invalid MPS names, then they are employed when writing the solution file.

Default *OFF*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES,
MSK_OFF)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_SOL_VARIABLES

Controls whether the variables section is written to the solution file.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_SOL_VARIABLES, MSK_ON)`

Groups *Data input/output, Solution input/output*

MSK_IPAR_WRITE_TASK_INC_SOL

Controls whether the solutions are stored in the task file too.

Default *ON*

Accepted *ON, OFF* (see *MSKonoffkeye*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_TASK_INC_SOL, MSK_ON)`

Groups *Data input/output*

MSK_IPAR_WRITE_XML_MODE

Controls if linear coefficients should be written by row or column when writing in the XML file format.

Default *ROW*

Accepted *ROW, COL* (see *MSKxmlwriteroutputtypee*)

Example `MSK_putintparam(task, MSK_IPAR_WRITE_XML_MODE, MSK_WRITE_XML_MODE_ROW)`

Groups *Data input/output*

15.5.3 String parameters

MSKsparame

The enumeration type containing all string parameters.

MSK_SPAR_BAS_SOL_FILE_NAME

Name of the bas solution file.

Accepted Any valid file name.

Example `MSK_putstrparam(task, MSK_SPAR_BAS_SOL_FILE_NAME, "somevalue")`

Groups *Data input/output, Solution input/output*

MSK_SPAR_DATA_FILE_NAME

Data are read and written to this file.

Accepted Any valid file name.

Example `MSK_putstrparam(task, MSK_SPAR_DATA_FILE_NAME, "somevalue")`

Groups *Data input/output*

MSK_SPAR_DEBUG_FILE_NAME

MOSEK debug file.

Accepted Any valid file name.

Example `MSK_putstrparam(task, MSK_SPAR_DEBUG_FILE_NAME, "somevalue")`

Groups *Data input/output*

MSK_SPAR_INT_SOL_FILE_NAME

Name of the int solution file.

Accepted Any valid file name.

Example `MSK_putstrparam(task, MSK_SPAR_INT_SOL_FILE_NAME, "somevalue")`

Groups *Data input/output, Solution input/output*

MSK_SPAR_ITR_SOL_FILE_NAME

Name of the itr solution file.

Accepted Any valid file name.

Example MSK_putstrparam(task, MSK_SPAR_ITR_SOL_FILE_NAME, "somevalue")

Groups *Data input/output, Solution input/output*

MSK_SPAR_MIO_DEBUG_STRING

For internal debugging purposes.

Accepted Any valid string.

Example MSK_putstrparam(task, MSK_SPAR_MIO_DEBUG_STRING, "somevalue")

Groups *Data input/output*

MSK_SPAR_PARAM_COMMENT_SIGN

Only the first character in this string is used. It is considered as a start of comment sign in the MOSEK parameter file. Spaces are ignored in the string.

Default

%%

Accepted Any valid string.

Example MSK_putstrparam(task, MSK_SPAR_PARAM_COMMENT_SIGN, "%%")

Groups *Data input/output*

MSK_SPAR_PARAM_READ_FILE_NAME

Modifications to the parameter database is read from this file.

Accepted Any valid file name.

Example MSK_putstrparam(task, MSK_SPAR_PARAM_READ_FILE_NAME, "somevalue")

Groups *Data input/output*

MSK_SPAR_PARAM_WRITE_FILE_NAME

The parameter database is written to this file.

Accepted Any valid file name.

Example MSK_putstrparam(task, MSK_SPAR_PARAM_WRITE_FILE_NAME, "somevalue")

Groups *Data input/output*

MSK_SPAR_READ_MPS_BOU_NAME

Name of the BOUNDS vector used. An empty name means that the first BOUNDS vector is used.

Accepted Any valid MPS name.

Example MSK_putstrparam(task, MSK_SPAR_READ_MPS_BOU_NAME, "somevalue")

Groups *Data input/output*

MSK_SPAR_READ_MPS_OBJ_NAME

Name of the free constraint used as objective function. An empty name means that the first constraint is used as objective function.

Accepted Any valid MPS name.

Example MSK_putstrparam(task, MSK_SPAR_READ_MPS_OBJ_NAME, "somevalue")

Groups *Data input/output*

MSK_SPAR_READ_MPS_RAN_NAME

Name of the RANGE vector used. An empty name means that the first RANGE vector is used.

Accepted Any valid MPS name.

Example MSK_putstrparam(task, MSK_SPAR_READ_MPS_RAN_NAME, "somevalue")

Groups *Data input/output*

MSK_SPAR_READ_MPS_RHS_NAME

Name of the RHS used. An empty name means that the first RHS vector is used.

Accepted Any valid MPS name.

Example `MSK_putstrparam(task, MSK_SPAR_READ_MPS_RHS_NAME, "somevalue")`

Groups *Data input/output*

MSK_SPAR_REMOTE_ACCESS_TOKEN

An access token used to submit tasks to a remote **MOSEK** server. An access token is a random 32-byte string encoded in base64, i.e. it is a 44 character ASCII string.

Accepted Any valid string.

Example `MSK_putstrparam(task, MSK_SPAR_REMOTE_ACCESS_TOKEN, "somevalue")`

Groups *Overall system*

MSK_SPAR_SENSITIVITY_FILE_NAME

If defined *MSK_sensitivityreport* reads this file as a sensitivity analysis data file specifying the type of analysis to be done.

Accepted Any valid string.

Example `MSK_putstrparam(task, MSK_SPAR_SENSITIVITY_FILE_NAME, "somevalue")`

Groups *Data input/output*

MSK_SPAR_SENSITIVITY_RES_FILE_NAME

If this is a nonempty string, then *MSK_sensitivityreport* writes results to this file.

Accepted Any valid string.

Example `MSK_putstrparam(task, MSK_SPAR_SENSITIVITY_RES_FILE_NAME, "somevalue")`

Groups *Data input/output*

MSK_SPAR_SOL_FILTER_XC_LOW

A filter used to determine which constraints should be listed in the solution file. A value of 0.5 means that all constraints having $xc[i] > 0.5$ should be listed, whereas +0.5 means that all constraints having $xc[i] \geq blc[i] + 0.5$ should be listed. An empty filter means that no filter is applied.

Accepted Any valid filter.

Example `MSK_putstrparam(task, MSK_SPAR_SOL_FILTER_XC_LOW, "somevalue")`

Groups *Data input/output, Solution input/output*

MSK_SPAR_SOL_FILTER_XC_UPR

A filter used to determine which constraints should be listed in the solution file. A value of 0.5 means that all constraints having $xc[i] < 0.5$ should be listed, whereas -0.5 means all constraints having $xc[i] \leq buc[i] - 0.5$ should be listed. An empty filter means that no filter is applied.

Accepted Any valid filter.

Example `MSK_putstrparam(task, MSK_SPAR_SOL_FILTER_XC_UPR, "somevalue")`

Groups *Data input/output, Solution input/output*

MSK_SPAR_SOL_FILTER_XX_LOW

A filter used to determine which variables should be listed in the solution file. A value of "0.5" means that all constraints having $xx[j] \geq 0.5$ should be listed, whereas "+0.5" means that all constraints having $xx[j] \geq blx[j] + 0.5$ should be listed. An empty filter means no filter is applied.

Accepted Any valid filter.

Example `MSK_putstrparam(task, MSK_SPAR_SOL_FILTER_XX_LOW, "somevalue")`

Groups *Data input/output, Solution input/output*

MSK_SPAR_SOL_FILTER_XX_UPR

A filter used to determine which variables should be listed in the solution file. A value of “0.5” means that all constraints having $xx[j] < 0.5$ should be printed, whereas “-0.5” means all constraints having $xx[j] \leq bux[j] - 0.5$ should be listed. An empty filter means no filter is applied.

Accepted Any valid file name.

Example `MSK_putstrparam(task, MSK_SPAR_SOL_FILTER_XX_UPR, "somevalue")`

Groups *Data input/output, Solution input/output*

MSK_SPAR_STAT_FILE_NAME

Statistics file name.

Accepted Any valid file name.

Example `MSK_putstrparam(task, MSK_SPAR_STAT_FILE_NAME, "somevalue")`

Groups *Data input/output*

MSK_SPAR_STAT_KEY

Key used when writing the summary file.

Accepted Any valid string.

Example `MSK_putstrparam(task, MSK_SPAR_STAT_KEY, "somevalue")`

Groups *Data input/output*

MSK_SPAR_STAT_NAME

Name used when writing the statistics file.

Accepted Any valid XML string.

Example `MSK_putstrparam(task, MSK_SPAR_STAT_NAME, "somevalue")`

Groups *Data input/output*

MSK_SPAR_WRITE_LP_GEN_VAR_NAME

Sometimes when an LP file is written additional variables must be inserted. They will have the prefix denoted by this parameter.

Default `xmskgen`

Accepted Any valid string.

Example `MSK_putstrparam(task, MSK_SPAR_WRITE_LP_GEN_VAR_NAME, "xmskgen")`

Groups *Data input/output*

15.6 Response codes

Response codes include:

- *Termination codes*
- *Warnings*
- *Errors*

The numerical code (in brackets) identifies the response in error messages and in the log output.

MSKrescodee

The enumeration type containing all response codes.

15.6.1 Termination

MSK_RES_OK (0)

No error occurred.

MSK_RES_TRM_MAX_ITERATIONS (10000)

The optimizer terminated at the maximum number of iterations.

MSK_RES_TRM_MAX_TIME (10001)

The optimizer terminated at the maximum amount of time.

MSK_RES_TRM_OBJECTIVE_RANGE (10002)

The optimizer terminated with an objective value outside the objective range.

MSK_RES_TRM_MIO_NUM_RELAXS (10008)

The mixed-integer optimizer terminated as the maximum number of relaxations was reached.

MSK_RES_TRM_MIO_NUM_BRANCHES (10009)

The mixed-integer optimizer terminated as the maximum number of branches was reached.

MSK_RES_TRM_NUM_MAX_NUM_INT_SOLUTIONS (10015)

The mixed-integer optimizer terminated as the maximum number of feasible solutions was reached.

MSK_RES_TRM_STALL (10006)

The optimizer is terminated due to slow progress.

Stalling means that numerical problems prevent the optimizer from making reasonable progress and that it makes no sense to continue. In many cases this happens if the problem is badly scaled or otherwise ill-conditioned. There is no guarantee that the solution will be feasible or optimal. However, often stalling happens near the optimum, and the returned solution may be of good quality. Therefore, it is recommended to check the status of the solution. If the solution status is optimal the solution is most likely good enough for most practical purposes.

Please note that if a linear optimization problem is solved using the interior-point optimizer with basis identification turned on, the returned basic solution likely to have high accuracy, even though the optimizer stalled.

Some common causes of stalling are a) badly scaled models, b) near feasible or near infeasible problems.

MSK_RES_TRM_USER_CALLBACK (10007)

The optimizer terminated due to the return of the user-defined callback function.

MSK_RES_TRM_MAX_NUM_SETBACKS (10020)

The optimizer terminated as the maximum number of set-backs was reached. This indicates serious numerical problems and a possibly badly formulated problem.

MSK_RES_TRM_NUMERICAL_PROBLEM (10025)

The optimizer terminated due to numerical problems.

MSK_RES_TRM_INTERNAL (10030)

The optimizer terminated due to some internal reason. Please contact **MOSEK** support.

MSK_RES_TRM_INTERNAL_STOP (10031)

The optimizer terminated for internal reasons. Please contact **MOSEK** support.

15.6.2 Warnings

MSK_RES_WRN_OPEN_PARAM_FILE (50)

The parameter file could not be opened.

MSK_RES_WRN_LARGE_BOUND (51)

A numerically large bound value is specified.

MSK_RES_WRN_LARGE_LO_BOUND (52)

A numerically large lower bound value is specified.

MSK_RES_WRN_LARGE_UP_BOUND (53)

A numerically large upper bound value is specified.

MSK_RES_WRN_LARGE_CON_FX (54)

An equality constraint is fixed to a numerically large value. This can cause numerical problems.

MSK_RES_WRN_LARGE_CJ (57)

A numerically large value is specified for one c_j .

MSK_RES_WRN_LARGE_AIJ (62)

A numerically large value is specified for an $a_{i,j}$ element in A . The parameter *MSK_DPAR_DATA_TOL_AIJ_LARGE* controls when an $a_{i,j}$ is considered large.

MSK_RES_WRN_ZERO_AIJ (63)
 One or more zero elements are specified in A.

MSK_RES_WRN_NAME_MAX_LEN (65)
 A name is longer than the buffer that is supposed to hold it.

MSK_RES_WRN_SPAR_MAX_LEN (66)
 A value for a string parameter is longer than the buffer that is supposed to hold it.

MSK_RES_WRN_MPS_SPLIT_RHS_VECTOR (70)
 An RHS vector is split into several nonadjacent parts in an MPS file.

MSK_RES_WRN_MPS_SPLIT_RAN_VECTOR (71)
 A RANGE vector is split into several nonadjacent parts in an MPS file.

MSK_RES_WRN_MPS_SPLIT_BOU_VECTOR (72)
 A BOUNDS vector is split into several nonadjacent parts in an MPS file.

MSK_RES_WRN_LP_OLD_QUAD_FORMAT (80)
 Missing $\sqrt{2}$ after quadratic expressions in bound or objective.

MSK_RES_WRN_LP_DROP_VARIABLE (85)
 Ignored a variable because the variable was not previously defined. Usually this implies that a variable appears in the bound section but not in the objective or the constraints.

MSK_RES_WRN_NZ_IN_UPR_TRI (200)
 Non-zero elements specified in the upper triangle of a matrix were ignored.

MSK_RES_WRN_DROPPED_NZ_QOBJ (201)
 One or more non-zero elements were dropped in the Q matrix in the objective.

MSK_RES_WRN_IGNORE_INTEGER (250)
 Ignored integer constraints.

MSK_RES_WRN_NO_GLOBAL_OPTIMIZER (251)
 No global optimizer is available.

MSK_RES_WRN_MIO_INFEASIBLE_FINAL (270)
 The final mixed-integer problem with all the integer variables fixed at their optimal values is infeasible.

MSK_RES_WRN_SOL_FILTER (300)
 Invalid solution filter is specified.

MSK_RES_WRN_UNDEF_SOL_FILE_NAME (350)
 Undefined name occurred in a solution.

MSK_RES_WRN_SOL_FILE_IGNORED_CON (351)
 One or more lines in the constraint section were ignored when reading a solution file.

MSK_RES_WRN_SOL_FILE_IGNORED_VAR (352)
 One or more lines in the variable section were ignored when reading a solution file.

MSK_RES_WRN_TOO_FEW_BASIS_VARS (400)
 An incomplete basis has been specified. Too few basis variables are specified.

MSK_RES_WRN_TOO_MANY_BASIS_VARS (405)
 A basis with too many variables has been specified.

MSK_RES_WRN_LICENSE_EXPIRE (500)
 The license expires.

MSK_RES_WRN_LICENSE_SERVER (501)
 The license server is not responding.

MSK_RES_WRN_EMPTY_NAME (502)
 A variable or constraint name is empty. The output file may be invalid.

MSK_RES_WRN_USING_GENERIC_NAMES (503)
 Generic names are used because a name is not valid. For instance when writing an LP file the names must not contain blanks or start with a digit.

MSK_RES_WRN_LICENSE_FEATURE_EXPIRE (505)
 The license expires.

MSK_RES_WRN_PARAM_NAME_DOUB (510)
 The parameter name is not recognized as a double parameter.

MSK_RES_WRN_PARAM_NAME_INT (511)
 The parameter name is not recognized as an integer parameter.

MSK_RES_WRN_PARAM_NAME_STR (512)
 The parameter name is not recognized as a string parameter.

MSK_RES_WRN_PARAM_STR_VALUE (515)
The string is not recognized as a symbolic value for the parameter.

MSK_RES_WRN_PARAM_IGNORED_CMIO (516)
A parameter was ignored by the conic mixed integer optimizer.

MSK_RES_WRN_ZEROS_IN_SPARSE_ROW (705)
One or more (near) zero elements are specified in a sparse row of a matrix. Since, it is redundant to specify zero elements then it may indicate an error.

MSK_RES_WRN_ZEROS_IN_SPARSE_COL (710)
One or more (near) zero elements are specified in a sparse column of a matrix. It is redundant to specify zero elements. Hence, it may indicate an error.

MSK_RES_WRN_INCOMPLETE_LINEAR_DEPENDENCY_CHECK (800)
The linear dependency check(s) is incomplete. Normally this is not an important warning unless the optimization problem has been formulated with linear dependencies. Linear dependencies may prevent **MOSEK** from solving the problem.

MSK_RES_WRN_ELIMINATOR_SPACE (801)
The eliminator is skipped at least once due to lack of space.

MSK_RES_WRN_PRESOLVE_OUTOFSPACE (802)
The presolve is incomplete due to lack of space.

MSK_RES_WRN_WRITE_CHANGED_NAMES (803)
Some names were changed because they were invalid for the output file format.

MSK_RES_WRN_WRITE_DISCARDED_CFIX (804)
The fixed objective term could not be converted to a variable and was discarded in the output file.

MSK_RES_WRN_DUPLICATE_CONSTRAINT_NAMES (850)
Two constraint names are identical.

MSK_RES_WRN_DUPLICATE_VARIABLE_NAMES (851)
Two variable names are identical.

MSK_RES_WRN_DUPLICATE_BARVARIABLE_NAMES (852)
Two barvariable names are identical.

MSK_RES_WRN_DUPLICATE_CONE_NAMES (853)
Two cone names are identical.

MSK_RES_WRN_ANA_LARGE_BOUNDS (900)
This warning is issued by the problem analyzer, if one or more constraint or variable bounds are very large. One should consider omitting these bounds entirely by setting them to $+\infty$ or $-\infty$.

MSK_RES_WRN_ANA_C_ZERO (901)
This warning is issued by the problem analyzer, if the coefficients in the linear part of the objective are all zero.

MSK_RES_WRN_ANA_EMPTY_COLS (902)
This warning is issued by the problem analyzer, if columns, in which all coefficients are zero, are found.

MSK_RES_WRN_ANA_CLOSE_BOUNDS (903)
This warning is issued by problem analyzer, if ranged constraints or variables with very close upper and lower bounds are detected. One should consider treating such constraints as equalities and such variables as constants.

MSK_RES_WRN_ANA_ALMOST_INT_BOUNDS (904)
This warning is issued by the problem analyzer if a constraint is bound nearly integral.

MSK_RES_WRN_QUAD_CONES_WITH_ROOT_FIXED_AT_ZERO (930)
For at least one quadratic cone the root is fixed at (nearly) zero. This may cause problems such as a very large dual solution. Therefore, it is recommended to remove such cones before optimizing the problem, or to fix all the variables in the cone to 0.

MSK_RES_WRN_RQUAD_CONES_WITH_ROOT_FIXED_AT_ZERO (931)
For at least one rotated quadratic cone at least one of the root variables are fixed at (nearly) zero. This may cause problems such as a very large dual solution. Therefore, it is recommended to remove such cones before optimizing the problem, or to fix all the variables in the cone to 0.

MSK_RES_WRN_EXP_CONES_WITH_VARIABLES_FIXED_AT_ZERO (932)
For at least one exponential cone $x \geq y \exp(z/y)$ either the variable x or y is fixed at (nearly) zero. This may cause problems such as a very large dual solution. Therefore, it is recommended to remove such cones before optimizing the problem, or to fix all the variables in the cone to 0.

MSK_RES_WRN_POW_CONES_WITH_ROOT_FIXED_AT_ZERO (933)

For at least one power cone at least one of the root variables are fixed at (nearly) zero. This may cause problems such as a very large dual solution. Therefore, it is recommended to remove such cones before optimizing the problem, or to fix all the variables in the cone to 0.

MSK_RES_WRN_NO_DUALIZER (950)

No automatic dualizer is available for the specified problem. The primal problem is solved.

MSK_RES_WRN_SYM_MAT_LARGE (960)

A numerically large value is specified for an $e_{i,j}$ element in E . The parameter *MSK_DPAR_DATA_SYM_MAT_TOL_LARGE* controls when an $e_{i,j}$ is considered large.

15.6.3 Errors

MSK_RES_ERR_LICENSE (1000)

Invalid license.

MSK_RES_ERR_LICENSE_EXPIRED (1001)

The license has expired.

MSK_RES_ERR_LICENSE_VERSION (1002)

The license is valid for another version of **MOSEK**.

MSK_RES_ERR_SIZE_LICENSE (1005)

The problem is bigger than the license.

MSK_RES_ERR_PROB_LICENSE (1006)

The software is not licensed to solve the problem.

MSK_RES_ERR_FILE_LICENSE (1007)

Invalid license file.

MSK_RES_ERR_MISSING_LICENSE_FILE (1008)

MOSEK cannot find license file or a token server. See the **MOSEK** licensing manual for details.

MSK_RES_ERR_SIZE_LICENSE_CON (1010)

The problem has too many constraints to be solved with the available license.

MSK_RES_ERR_SIZE_LICENSE_VAR (1011)

The problem has too many variables to be solved with the available license.

MSK_RES_ERR_SIZE_LICENSE_INTVAR (1012)

The problem contains too many integer variables to be solved with the available license.

MSK_RES_ERR_OPTIMIZER_LICENSE (1013)

The optimizer required is not licensed.

MSK_RES_ERR_FLEXLM (1014)

The FLEXlm license manager reported an error.

MSK_RES_ERR_LICENSE_SERVER (1015)

The license server is not responding.

MSK_RES_ERR_LICENSE_MAX (1016)

Maximum number of licenses is reached.

MSK_RES_ERR_LICENSE_MOSEKLM_DAEMON (1017)

The MOSEKLM license manager daemon is not up and running.

MSK_RES_ERR_LICENSE_FEATURE (1018)

A requested feature is not available in the license file(s). Most likely due to an incorrect license system setup.

MSK_RES_ERR_PLATFORM_NOT_LICENSED (1019)

A requested license feature is not available for the required platform.

MSK_RES_ERR_LICENSE_CANNOT_ALLOCATE (1020)

The license system cannot allocate the memory required.

MSK_RES_ERR_LICENSE_CANNOT_CONNECT (1021)

MOSEK cannot connect to the license server. Most likely the license server is not up and running.

MSK_RES_ERR_LICENSE_INVALID_HOSTID (1025)

The host ID specified in the license file does not match the host ID of the computer.

MSK_RES_ERR_LICENSE_SERVER_VERSION (1026)

The version specified in the checkout request is greater than the highest version number the daemon supports.

MSK_RES_ERR_LICENSE_NO_SERVER_SUPPORT (1027)

The license server does not support the requested feature. Possible reasons for this error include:

- The feature has expired.
- The feature's start date is later than today's date.
- The version requested is higher than feature's the highest supported version.
- A corrupted license file.

Try restarting the license and inspect the license server debug file, usually called `lmgrd.log`.

MSK_RES_ERR_LICENSE_NO_SERVER_LINE (1028)

There is no **SERVER** line in the license file. All non-zero license count features need at least one **SERVER** line.

MSK_RES_ERR_OLDER_DLL (1035)

The dynamic link library is older than the specified version.

MSK_RES_ERR_NEWER_DLL (1036)

The dynamic link library is newer than the specified version.

MSK_RES_ERR_LINK_FILE_DLL (1040)

A file cannot be linked to a stream in the DLL version.

MSK_RES_ERR_THREAD_MUTEX_INIT (1045)

Could not initialize a mutex.

MSK_RES_ERR_THREAD_MUTEX_LOCK (1046)

Could not lock a mutex.

MSK_RES_ERR_THREAD_MUTEX_UNLOCK (1047)

Could not unlock a mutex.

MSK_RES_ERR_THREAD_CREATE (1048)

Could not create a thread. This error may occur if a large number of environments are created and not deleted again. In any case it is a good practice to minimize the number of environments created.

MSK_RES_ERR_THREAD_COND_INIT (1049)

Could not initialize a condition.

MSK_RES_ERR_UNKNOWN (1050)

Unknown error.

MSK_RES_ERR_SPACE (1051)

Out of space.

MSK_RES_ERR_FILE_OPEN (1052)

Error while opening a file.

MSK_RES_ERR_FILE_READ (1053)

File read error.

MSK_RES_ERR_FILE_WRITE (1054)

File write error.

MSK_RES_ERR_DATA_FILE_EXT (1055)

The data file format cannot be determined from the file name.

MSK_RES_ERR_INVALID_FILE_NAME (1056)

An invalid file name has been specified.

MSK_RES_ERR_INVALID_SOL_FILE_NAME (1057)

An invalid file name has been specified.

MSK_RES_ERR_END_OF_FILE (1059)

End of file reached.

MSK_RES_ERR_NULL_ENV (1060)

`env` is a `NULL` pointer.

MSK_RES_ERR_NULL_TASK (1061)

`task` is a `NULL` pointer.

MSK_RES_ERR_INVALID_STREAM (1062)

An invalid stream is referenced.

MSK_RES_ERR_NO_INIT_ENV (1063)

`env` is not initialized.

MSK_RES_ERR_INVALID_TASK (1064)

The `task` is invalid.

MSK_RES_ERR_NULL_POINTER (1065)

An argument to a function is unexpectedly a `NULL` pointer.

MSK_RES_ERR_LIVING_TASKS (1066)
 All tasks associated with an environment must be deleted before the environment is deleted. There are still some undeleted tasks.

MSK_RES_ERR_BLANK_NAME (1070)
 An all blank name has been specified.

MSK_RES_ERR_DUP_NAME (1071)
 The same name was used multiple times for the same problem item type.

MSK_RES_ERR_FORMAT_STRING (1072)
 The name format string is invalid.

MSK_RES_ERR_INVALID_OBJ_NAME (1075)
 An invalid objective name is specified.

MSK_RES_ERR_INVALID_CON_NAME (1076)
 An invalid constraint name is used.

MSK_RES_ERR_INVALID_VAR_NAME (1077)
 An invalid variable name is used.

MSK_RES_ERR_INVALID_CONE_NAME (1078)
 An invalid cone name is used.

MSK_RES_ERR_INVALID_BARVAR_NAME (1079)
 An invalid symmetric matrix variable name is used.

MSK_RES_ERR_SPACE_LEAKING (1080)
MOSEK is leaking memory. This can be due to either an incorrect use of **MOSEK** or a bug.

MSK_RES_ERR_SPACE_NO_INFO (1081)
 No available information about the space usage.

MSK_RES_ERR_READ_FORMAT (1090)
 The specified format cannot be read.

MSK_RES_ERR_MPS_FILE (1100)
 An error occurred while reading an MPS file.

MSK_RES_ERR_MPS_INV_FIELD (1101)
 A field in the MPS file is invalid. Probably it is too wide.

MSK_RES_ERR_MPS_INV_MARKER (1102)
 An invalid marker has been specified in the MPS file.

MSK_RES_ERR_MPS_NULL_CON_NAME (1103)
 An empty constraint name is used in an MPS file.

MSK_RES_ERR_MPS_NULL_VAR_NAME (1104)
 An empty variable name is used in an MPS file.

MSK_RES_ERR_MPS_UNDEF_CON_NAME (1105)
 An undefined constraint name occurred in an MPS file.

MSK_RES_ERR_MPS_UNDEF_VAR_NAME (1106)
 An undefined variable name occurred in an MPS file.

MSK_RES_ERR_MPS_INV_CON_KEY (1107)
 An invalid constraint key occurred in an MPS file.

MSK_RES_ERR_MPS_INV_BOUND_KEY (1108)
 An invalid bound key occurred in an MPS file.

MSK_RES_ERR_MPS_INV_SEC_NAME (1109)
 An invalid section name occurred in an MPS file.

MSK_RES_ERR_MPS_NO_OBJECTIVE (1110)
 No objective is defined in an MPS file.

MSK_RES_ERR_MPS_SPLITTED_VAR (1111)
 All elements in a column of the A matrix must be specified consecutively. Hence, it is illegal to specify non-zero elements in A for variable 1, then for variable 2 and then variable 1 again.

MSK_RES_ERR_MPS_MUL_CON_NAME (1112)
 A constraint name was specified multiple times in the ROWS section.

MSK_RES_ERR_MPS_MUL_QSEC (1113)
 Multiple QSECTIONS are specified for a constraint in the MPS data file.

MSK_RES_ERR_MPS_MUL_QOBJ (1114)
 The Q term in the objective is specified multiple times in the MPS data file.

MSK_RES_ERR_MPS_INV_SEC_ORDER (1115)
 The sections in the MPS data file are not in the correct order.

MSK_RES_ERR_MPS_MUL_CSEC (1116)
Multiple CSECTIONs are given the same name.

MSK_RES_ERR_MPS_CONE_TYPE (1117)
Invalid cone type specified in a CSECTION.

MSK_RES_ERR_MPS_CONE_OVERLAP (1118)
A variable is specified to be a member of several cones.

MSK_RES_ERR_MPS_CONE_REPEAT (1119)
A variable is repeated within the CSECTION.

MSK_RES_ERR_MPS_NON_SYMMETRIC_Q (1120)
A non symmetric matrix has been specified.

MSK_RES_ERR_MPS_DUPLICATE_Q_ELEMENT (1121)
Duplicate elements is specified in a Q matrix.

MSK_RES_ERR_MPS_INVALID_OBJSENSE (1122)
An invalid objective sense is specified.

MSK_RES_ERR_MPS_TAB_IN_FIELD2 (1125)
A tab char occurred in field 2.

MSK_RES_ERR_MPS_TAB_IN_FIELD3 (1126)
A tab char occurred in field 3.

MSK_RES_ERR_MPS_TAB_IN_FIELD5 (1127)
A tab char occurred in field 5.

MSK_RES_ERR_MPS_INVALID_OBJ_NAME (1128)
An invalid objective name is specified.

MSK_RES_ERR_LP_INCOMPATIBLE (1150)
The problem cannot be written to an LP formatted file.

MSK_RES_ERR_LP_EMPTY (1151)
The problem cannot be written to an LP formatted file.

MSK_RES_ERR_LP_DUP_SLACK_NAME (1152)
The name of the slack variable added to a ranged constraint already exists.

MSK_RES_ERR_WRITE_MPS_INVALID_NAME (1153)
An invalid name is created while writing an MPS file. Usually this will make the MPS file unreadable.

MSK_RES_ERR_LP_INVALID_VAR_NAME (1154)
A variable name is invalid when used in an LP formatted file.

MSK_RES_ERR_LP_FREE_CONSTRAINT (1155)
Free constraints cannot be written in LP file format.

MSK_RES_ERR_WRITE_OPF_INVALID_VAR_NAME (1156)
Empty variable names cannot be written to OPF files.

MSK_RES_ERR_LP_FILE_FORMAT (1157)
Syntax error in an LP file.

MSK_RES_ERR_WRITE_LP_FORMAT (1158)
Problem cannot be written as an LP file.

MSK_RES_ERR_READ_LP_MISSING_END_TAG (1159)
Syntax error in LP file. Possibly missing End tag.

MSK_RES_ERR_LP_FORMAT (1160)
Syntax error in an LP file.

MSK_RES_ERR_WRITE_LP_NON_UNIQUE_NAME (1161)
An auto-generated name is not unique.

MSK_RES_ERR_READ_LP_NONEXISTING_NAME (1162)
A variable never occurred in objective or constraints.

MSK_RES_ERR_LP_WRITE_CONIC_PROBLEM (1163)
The problem contains cones that cannot be written to an LP formatted file.

MSK_RES_ERR_LP_WRITE_GECO_PROBLEM (1164)
The problem contains general convex terms that cannot be written to an LP formatted file.

MSK_RES_ERR_WRITING_FILE (1166)
An error occurred while writing file

MSK_RES_ERR_PTF_FORMAT (1167)
Syntax error in an PTF file

MSK_RES_ERR_OPF_FORMAT (1168)
 Syntax error in an OPF file

MSK_RES_ERR_OPF_NEW_VARIABLE (1169)
 Introducing new variables is now allowed. When a [variables] section is present, it is not allowed to introduce new variables later in the problem.

MSK_RES_ERR_INVALID_NAME_IN_SOL_FILE (1170)
 An invalid name occurred in a solution file.

MSK_RES_ERR_LP_INVALID_CON_NAME (1171)
 A constraint name is invalid when used in an LP formatted file.

MSK_RES_ERR_OPF_PREMATURE_EOF (1172)
 Premature end of file in an OPF file.

MSK_RES_ERR_JSON_SYNTAX (1175)
 Syntax error in an JSON data

MSK_RES_ERR_JSON_STRING (1176)
 Error in JSON string.

MSK_RES_ERR_JSON_NUMBER_OVERFLOW (1177)
 Invalid number entry - wrong type or value overflow.

MSK_RES_ERR_JSON_FORMAT (1178)
 Error in an JSON Task file

MSK_RES_ERR_JSON_DATA (1179)
 Inconsistent data in JSON Task file

MSK_RES_ERR_JSON_MISSING_DATA (1180)
 Missing data section in JSON task file.

MSK_RES_ERR_ARGUMENT_LENNEQ (1197)
 Incorrect length of arguments.

MSK_RES_ERR_ARGUMENT_TYPE (1198)
 Incorrect argument type.

MSK_RES_ERR_NUM_ARGUMENTS (1199)
 Incorrect number of function arguments.

MSK_RES_ERR_IN_ARGUMENT (1200)
 A function argument is incorrect.

MSK_RES_ERR_ARGUMENT_DIMENSION (1201)
 A function argument is of incorrect dimension.

MSK_RES_ERR_SHAPE_IS_TOO_LARGE (1202)
 The size of the n-dimensional shape is too large.

MSK_RES_ERR_INDEX_IS_TOO_SMALL (1203)
 An index in an argument is too small.

MSK_RES_ERR_INDEX_IS_TOO_LARGE (1204)
 An index in an argument is too large.

MSK_RES_ERR_PARAM_NAME (1205)
 The parameter name is not correct.

MSK_RES_ERR_PARAM_NAME_DOUB (1206)
 The parameter name is not correct for a double parameter.

MSK_RES_ERR_PARAM_NAME_INT (1207)
 The parameter name is not correct for an integer parameter.

MSK_RES_ERR_PARAM_NAME_STR (1208)
 The parameter name is not correct for a string parameter.

MSK_RES_ERR_PARAM_INDEX (1210)
 Parameter index is out of range.

MSK_RES_ERR_PARAM_IS_TOO_LARGE (1215)
 The parameter value is too large.

MSK_RES_ERR_PARAM_IS_TOO_SMALL (1216)
 The parameter value is too small.

MSK_RES_ERR_PARAM_VALUE_STR (1217)
 The parameter value string is incorrect.

MSK_RES_ERR_PARAM_TYPE (1218)
 The parameter type is invalid.

MSK_RES_ERR_INF_DOU_INDEX (1219)
 A double information index is out of range for the specified type.

MSK_RES_ERR_INF_INT_INDEX (1220)
 An integer information index is out of range for the specified type.

MSK_RES_ERR_INDEX_ARR_IS_TOO_SMALL (1221)
 An index in an array argument is too small.

MSK_RES_ERR_INDEX_ARR_IS_TOO_LARGE (1222)
 An index in an array argument is too large.

MSK_RES_ERR_INF_LINT_INDEX (1225)
 A long integer information index is out of range for the specified type.

MSK_RES_ERR_ARG_IS_TOO_SMALL (1226)
 The value of a argument is too small.

MSK_RES_ERR_ARG_IS_TOO_LARGE (1227)
 The value of a argument is too large.

MSK_RES_ERR_INVALID_WHICHSOL (1228)
whichsol is invalid.

MSK_RES_ERR_INF_DOU_NAME (1230)
 A double information name is invalid.

MSK_RES_ERR_INF_INT_NAME (1231)
 An integer information name is invalid.

MSK_RES_ERR_INF_TYPE (1232)
 The information type is invalid.

MSK_RES_ERR_INF_LINT_NAME (1234)
 A long integer information name is invalid.

MSK_RES_ERR_INDEX (1235)
 An index is out of range.

MSK_RES_ERR_WHICHSOL (1236)
 The solution defined by *whichsol* does not exists.

MSK_RES_ERR_SOLITEM (1237)
 The solution item number *solitem* is invalid. Please note that *MSK_SOL_ITEM_SNX* is invalid for the basic solution.

MSK_RES_ERR_WHICHITEM_NOT_ALLOWED (1238)
whichitem is unacceptable.

MSK_RES_ERR_MAXNUMCON (1240)
 The maximum number of constraints specified is smaller than the number of constraints in the task.

MSK_RES_ERR_MAXNUMVAR (1241)
 The maximum number of variables specified is smaller than the number of variables in the task.

MSK_RES_ERR_MAXNUMBARVAR (1242)
 The maximum number of semidefinite variables specified is smaller than the number of semidefinite variables in the task.

MSK_RES_ERR_MAXNUMQNZ (1243)
 The maximum number of non-zeros specified for the Q matrices is smaller than the number of non-zeros in the current Q matrices.

MSK_RES_ERR_TOO_SMALL_MAX_NUM_NZ (1245)
 The maximum number of non-zeros specified is too small.

MSK_RES_ERR_INVALID_IDX (1246)
 A specified index is invalid.

MSK_RES_ERR_INVALID_MAX_NUM (1247)
 A specified index is invalid.

MSK_RES_ERR_NUMCONLIM (1250)
 Maximum number of constraints limit is exceeded.

MSK_RES_ERR_NUMVARLIM (1251)
 Maximum number of variables limit is exceeded.

MSK_RES_ERR_TOO_SMALL_MAXNUMANZ (1252)
 The maximum number of non-zeros specified for A is smaller than the number of non-zeros in the current A .

MSK_RES_ERR_INV_APTRE (1253)
 `aptre[j]` is strictly smaller than `aptrb[j]` for some `j`.

MSK_RES_ERR_MUL_A_ELEMENT (1254)
 An element in A is defined multiple times.

MSK_RES_ERR_INV_BK (1255)
 Invalid bound key.

MSK_RES_ERR_INV_BKC (1256)
 Invalid bound key is specified for a constraint.

MSK_RES_ERR_INV_BKX (1257)
 An invalid bound key is specified for a variable.

MSK_RES_ERR_INV_VAR_TYPE (1258)
 An invalid variable type is specified for a variable.

MSK_RES_ERR_SOLVER_PROBTYPE (1259)
 Problem type does not match the chosen optimizer.

MSK_RES_ERR_OBJECTIVE_RANGE (1260)
 Empty objective range.

MSK_RES_ERR_UNDEF_SOLUTION (1265)
 MOSEK has the following solution types:

- an interior-point solution,
- a basic solution,
- and an integer solution.

Each optimizer may set one or more of these solutions; e.g by default a successful optimization with the interior-point optimizer defines the interior-point solution and, for linear problems, also the basic solution. This error occurs when asking for a solution or for information about a solution that is not defined.

MSK_RES_ERR_BASIS (1266)
 An invalid basis is specified. Either too many or too few basis variables are specified.

MSK_RES_ERR_INV_SKC (1267)
 Invalid value in `skc`.

MSK_RES_ERR_INV_SKX (1268)
 Invalid value in `skx`.

MSK_RES_ERR_INV_SKN (1274)
 Invalid value in `skn`.

MSK_RES_ERR_INV_SK_STR (1269)
 Invalid status key string encountered.

MSK_RES_ERR_INV_SK (1270)
 Invalid status key code.

MSK_RES_ERR_INV_CONE_TYPE_STR (1271)
 Invalid cone type string encountered.

MSK_RES_ERR_INV_CONE_TYPE (1272)
 Invalid cone type code is encountered.

MSK_RES_ERR_INVALID_SURPLUS (1275)
 Invalid surplus.

MSK_RES_ERR_INV_NAME_ITEM (1280)
 An invalid name item code is used.

MSK_RES_ERR_PRO_ITEM (1281)
 An invalid problem is used.

MSK_RES_ERR_INVALID_FORMAT_TYPE (1283)
 Invalid format type.

MSK_RES_ERR_FIRSTI (1285)
 Invalid `firsti`.

MSK_RES_ERR_LASTI (1286)
 Invalid `lasti`.

MSK_RES_ERR_FIRSTJ (1287)
 Invalid `firstj`.

MSK_RES_ERR_LASTJ (1288)
Invalid lastj.

MSK_RES_ERR_MAX_LEN_IS_TOO_SMALL (1289)
A maximum length that is too small has been specified.

MSK_RES_ERR_NONLINEAR_EQUALITY (1290)
The model contains a nonlinear equality which defines a nonconvex set.

MSK_RES_ERR_NONCONVEX (1291)
The optimization problem is nonconvex.

MSK_RES_ERR_NONLINEAR_RANGED (1292)
Nonlinear constraints with finite lower and upper bound always define a nonconvex feasible set.

MSK_RES_ERR_CON_Q_NOT_PSD (1293)
The quadratic constraint matrix is not positive semidefinite as expected for a constraint with finite upper bound. This results in a nonconvex problem. The parameter `MSK_DPAR_CHECK_CONVEXITY_REL_TOL` can be used to relax the convexity check.

MSK_RES_ERR_CON_Q_NOT_NSD (1294)
The quadratic constraint matrix is not negative semidefinite as expected for a constraint with finite lower bound. This results in a nonconvex problem. The parameter `MSK_DPAR_CHECK_CONVEXITY_REL_TOL` can be used to relax the convexity check.

MSK_RES_ERR_OBJ_Q_NOT_PSD (1295)
The quadratic coefficient matrix in the objective is not positive semidefinite as expected for a minimization problem. The parameter `MSK_DPAR_CHECK_CONVEXITY_REL_TOL` can be used to relax the convexity check.

MSK_RES_ERR_OBJ_Q_NOT_NSD (1296)
The quadratic coefficient matrix in the objective is not negative semidefinite as expected for a maximization problem. The parameter `MSK_DPAR_CHECK_CONVEXITY_REL_TOL` can be used to relax the convexity check.

MSK_RES_ERR_ARGUMENT_PERM_ARRAY (1299)
An invalid permutation array is specified.

MSK_RES_ERR_CONE_INDEX (1300)
An index of a non-existing cone has been specified.

MSK_RES_ERR_CONE_SIZE (1301)
A cone with incorrect number of members is specified.

MSK_RES_ERR_CONE_OVERLAP (1302)
One or more of the variables in the cone to be added is already member of another cone. Now assume the variable is x_j then add a new variable say x_k and the constraint

$$x_j = x_k$$

and then let x_k be member of the cone to be appended.

MSK_RES_ERR_CONE_REP_VAR (1303)
A variable is included multiple times in the cone.

MSK_RES_ERR_MAXNUMCONE (1304)
The value specified for `maxnumcone` is too small.

MSK_RES_ERR_CONE_TYPE (1305)
Invalid cone type specified.

MSK_RES_ERR_CONE_TYPE_STR (1306)
Invalid cone type specified.

MSK_RES_ERR_CONE_OVERLAP_APPEND (1307)
The cone to be appended has one variable which is already member of another cone.

MSK_RES_ERR_REMOVE_CONE_VARIABLE (1310)
A variable cannot be removed because it will make a cone invalid.

MSK_RES_ERR_APPENDING_TOO_BIG_CONE (1311)
Trying to append a too big cone.

MSK_RES_ERR_CONE_PARAMETER (1320)
An invalid cone parameter.

MSK_RES_ERR_SOL_FILE_INVALID_NUMBER (1350)
An invalid number is specified in a solution file.

MSK_RES_ERR_HUGE_C (1375)
A huge value in absolute size is specified for one c_j .

MSK_RES_ERR_HUGE_AIJ (1380)
 A numerically huge value is specified for an $a_{i,j}$ element in A . The parameter `MSK_DPAR_DATA_TOL_AIJ_HUGE` controls when an $a_{i,j}$ is considered huge.

MSK_RES_ERR_DUPLICATE_AIJ (1385)
 An element in the A matrix is specified twice.

MSK_RES_ERR_LOWER_BOUND_IS_A_NAN (1390)
 The lower bound specified is not a number (nan).

MSK_RES_ERR_UPPER_BOUND_IS_A_NAN (1391)
 The upper bound specified is not a number (nan).

MSK_RES_ERR_INFINITE_BOUND (1400)
 A numerically huge bound value is specified.

MSK_RES_ERR_INV_QOBJ_SUBI (1401)
 Invalid value in `qosubi`.

MSK_RES_ERR_INV_QOBJ_SUBJ (1402)
 Invalid value in `qosubj`.

MSK_RES_ERR_INV_QOBJ_VAL (1403)
 Invalid value in `qoval`.

MSK_RES_ERR_INV_QCON_SUBK (1404)
 Invalid value in `qcsubk`.

MSK_RES_ERR_INV_QCON_SUBI (1405)
 Invalid value in `qcsubi`.

MSK_RES_ERR_INV_QCON_SUBJ (1406)
 Invalid value in `qcsbj`.

MSK_RES_ERR_INV_QCON_VAL (1407)
 Invalid value in `qcval`.

MSK_RES_ERR_QCON_SUBI_TOO_SMALL (1408)
 Invalid value in `qcsubi`.

MSK_RES_ERR_QCON_SUBI_TOO_LARGE (1409)
 Invalid value in `qcsubi`.

MSK_RES_ERR_QOBJ_UPPER_TRIANGLE (1415)
 An element in the upper triangle of Q^o is specified. Only elements in the lower triangle should be specified.

MSK_RES_ERR_QCON_UPPER_TRIANGLE (1417)
 An element in the upper triangle of a Q^k is specified. Only elements in the lower triangle should be specified.

MSK_RES_ERR_FIXED_BOUND_VALUES (1420)
 A fixed constraint/variable has been specified using the bound keys but the numerical value of the lower and upper bound is different.

MSK_RES_ERR_TOO_SMALL_A_TRUNCATION_VALUE (1421)
 A too small value for the A truncation value is specified.

MSK_RES_ERR_INVALID_OBJECTIVE_SENSE (1445)
 An invalid objective sense is specified.

MSK_RES_ERR_UNDEFINED_OBJECTIVE_SENSE (1446)
 The objective sense has not been specified before the optimization.

MSK_RES_ERR_Y_IS_UNDEFINED (1449)
 The solution item y is undefined.

MSK_RES_ERR_NAN_IN_DOUBLE_DATA (1450)
 An invalid floating point value was used in some double data.

MSK_RES_ERR_NAN_IN_BLC (1461)
 l^c contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_BUC (1462)
 u^c contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_C (1470)
 c contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_BLX (1471)
 l^x contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_BUX (1472)
 u^x contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_INVALID_AIJ (1473)
 $a_{i,j}$ contains an invalid floating point value, i.e. a NaN or an infinite value.

MSK_RES_ERR_SYM_MAT_INVALID (1480)
A symmetric matrix contains an invalid floating point value, i.e. a NaN or an infinite value.

MSK_RES_ERR_SYM_MAT_HUGE (1482)
A symmetric matrix contains a huge value in absolute size. The parameter `MSK_DPAR_DATA_SYM_MAT_TOL_HUGE` controls when an $e_{i,j}$ is considered huge.

MSK_RES_ERR_INV_PROBLEM (1500)
Invalid problem type. Probably a nonconvex problem has been specified.

MSK_RES_ERR_MIXED_CONIC_AND_NL (1501)
The problem contains nonlinear terms conic constraints. The requested operation cannot be applied to this type of problem.

MSK_RES_ERR_GLOBAL_INV_CONIC_PROBLEM (1503)
The global optimizer can only be applied to problems without semidefinite variables.

MSK_RES_ERR_INV_OPTIMIZER (1550)
An invalid optimizer has been chosen for the problem.

MSK_RES_ERR_MIO_NO_OPTIMIZER (1551)
No optimizer is available for the current class of integer optimization problems.

MSK_RES_ERR_NO_OPTIMIZER_VAR_TYPE (1552)
No optimizer is available for this class of optimization problems.

MSK_RES_ERR_FINAL_SOLUTION (1560)
An error occurred during the solution finalization.

MSK_RES_ERR_FIRST (1570)
Invalid `first`.

MSK_RES_ERR_LAST (1571)
Invalid index `last`. A given index was out of expected range.

MSK_RES_ERR_SLICE_SIZE (1572)
Invalid slice size specified.

MSK_RES_ERR_NEGATIVE_SURPLUS (1573)
Negative surplus.

MSK_RES_ERR_NEGATIVE_APPEND (1578)
Cannot append a negative number.

MSK_RES_ERR_POSTSOLVE (1580)
An error occurred during the postsolve. Please contact **MOSEK** support.

MSK_RES_ERR_OVERFLOW (1590)
A computation produced an overflow i.e. a very large number.

MSK_RES_ERR_NO_BASIS_SOL (1600)
No basic solution is defined.

MSK_RES_ERR_BASIS_FACTOR (1610)
The factorization of the basis is invalid.

MSK_RES_ERR_BASIS_SINGULAR (1615)
The basis is singular and hence cannot be factored.

MSK_RES_ERR_FACTOR (1650)
An error occurred while factorizing a matrix.

MSK_RES_ERR_FEASREPAIR_CANNOT_RELAX (1700)
An optimization problem cannot be relaxed.

MSK_RES_ERR_FEASREPAIR_SOLVING_RELAXED (1701)
The relaxed problem could not be solved to optimality. Please consult the log file for further details.

MSK_RES_ERR_FEASREPAIR_INCONSISTENT_BOUND (1702)
The upper bound is less than the lower bound for a variable or a constraint. Please correct this before running the feasibility repair.

MSK_RES_ERR_REPAIR_INVALID_PROBLEM (1710)
The feasibility repair does not support the specified problem type.

MSK_RES_ERR_REPAIR_OPTIMIZATION_FAILED (1711)
Computation the optimal relaxation failed. The cause may have been numerical problems.

MSK_RES_ERR_NAME_MAX_LEN (1750)
A name is longer than the buffer that is supposed to hold it.

MSK_RES_ERR_NAME_IS_NULL (1760)
The name buffer is a NULL pointer.

MSK_RES_ERR_INVALID_COMPRESSION (1800)
Invalid compression type.

MSK_RES_ERR_INVALID_IOMODE (1801)
Invalid io mode.

MSK_RES_ERR_NO_PRIMAL_INFEAS_CER (2000)
A certificate of primal infeasibility is not available.

MSK_RES_ERR_NO_DUAL_INFEAS_CER (2001)
A certificate of infeasibility is not available.

MSK_RES_ERR_NO_SOLUTION_IN_CALLBACK (2500)
The required solution is not available.

MSK_RES_ERR_INV_MARKI (2501)
Invalid value in marki.

MSK_RES_ERR_INV_MARKJ (2502)
Invalid value in markj.

MSK_RES_ERR_INV_NUMI (2503)
Invalid numi.

MSK_RES_ERR_INV_NUMJ (2504)
Invalid numj.

MSK_RES_ERR_TASK_INCOMPATIBLE (2560)
The Task file is incompatible with this platform. This results from reading a file on a 32 bit platform generated on a 64 bit platform.

MSK_RES_ERR_TASK_INVALID (2561)
The Task file is invalid.

MSK_RES_ERR_TASK_WRITE (2562)
Failed to write the task file.

MSK_RES_ERR_LU_MAX_NUM_TRIES (2800)
Could not compute the LU factors of the matrix within the maximum number of allowed tries.

MSK_RES_ERR_INVALID_UTF8 (2900)
An invalid UTF8 string is encountered.

MSK_RES_ERR_INVALID_WCHAR (2901)
An invalid `wchar` string is encountered.

MSK_RES_ERR_NO_DUAL_FOR_ITG_SOL (2950)
No dual information is available for the integer solution.

MSK_RES_ERR_NO_SNX_FOR_BAS_SOL (2953)
 s_n^x is not available for the basis solution.

MSK_RES_ERR_INTERNAL (3000)
An internal error occurred. Please report this problem.

MSK_RES_ERR_API_ARRAY_TOO_SMALL (3001)
An input array was too short.

MSK_RES_ERR_API_CB_CONNECT (3002)
Failed to connect a callback object.

MSK_RES_ERR_API_FATAL_ERROR (3005)
An internal error occurred in the API. Please report this problem.

MSK_RES_ERR_API_INTERNAL (3999)
An internal fatal error occurred in an interface function.

MSK_RES_ERR_SEN_FORMAT (3050)
Syntax error in sensitivity analysis file.

MSK_RES_ERR_SEN_UNDEF_NAME (3051)
An undefined name was encountered in the sensitivity analysis file.

MSK_RES_ERR_SEN_INDEX_RANGE (3052)
Index out of range in the sensitivity analysis file.

MSK_RES_ERR_SEN_BOUND_INVALID_UP (3053)
Analysis of upper bound requested for an index, where no upper bound exists.

MSK_RES_ERR_SEN_BOUND_INVALID_LO (3054)
Analysis of lower bound requested for an index, where no lower bound exists.

MSK_RES_ERR_SEN_INDEX_INVALID (3055)
Invalid range given in the sensitivity file.

MSK_RES_ERR_SEN_INVALID_REGEX (3056)
Syntax error in regexp or regexp longer than 1024.

MSK_RES_ERR_SEN_SOLUTION_STATUS (3057)
No optimal solution found to the original problem given for sensitivity analysis.

MSK_RES_ERR_SEN_NUMERICAL (3058)
Numerical difficulties encountered performing the sensitivity analysis.

MSK_RES_ERR_SEN_UNHANDLED_PROBLEM_TYPE (3080)
Sensitivity analysis cannot be performed for the specified problem. Sensitivity analysis is only possible for linear problems.

MSK_RES_ERR_UNB_STEP_SIZE (3100)
A step size in an optimizer was unexpectedly unbounded. For instance, if the step-size becomes unbounded in phase 1 of the simplex algorithm then an error occurs. Normally this will happen only if the problem is badly formulated. Please contact **MOSEK** support if this error occurs.

MSK_RES_ERR_IDENTICAL_TASKS (3101)
Some tasks related to this function call were identical. Unique tasks were expected.

MSK_RES_ERR_AD_INVALID_CODELIST (3102)
The code list data was invalid.

MSK_RES_ERR_INTERNAL_TEST_FAILED (3500)
An internal unit test function failed.

MSK_RES_ERR_XML_INVALID_PROBLEM_TYPE (3600)
The problem type is not supported by the XML format.

MSK_RES_ERR_INVALIDAMPL_STUB (3700)
Invalid AMPL stub.

MSK_RES_ERR_INT64_TO_INT32_CAST (3800)
A 64 bit integer could not be cast to a 32 bit integer.

MSK_RES_ERR_SIZE_LICENSE_NUMCORES (3900)
The computer contains more cpu cores than the license allows for.

MSK_RES_ERR_INFEAS_UNDEFINED (3910)
The requested value is not defined for this solution type.

MSK_RES_ERR_NO_BARX_FOR_SOLUTION (3915)
There is no \bar{X} available for the solution specified. In particular note there are no \bar{X} defined for the basic and integer solutions.

MSK_RES_ERR_NO_BARS_FOR_SOLUTION (3916)
There is no \bar{s} available for the solution specified. In particular note there are no \bar{s} defined for the basic and integer solutions.

MSK_RES_ERR_BAR_VAR_DIM (3920)
The dimension of a symmetric matrix variable has to be greater than 0.

MSK_RES_ERR_SYM_MAT_INVALID_ROW_INDEX (3940)
A row index specified for sparse symmetric matrix is invalid.

MSK_RES_ERR_SYM_MAT_INVALID_COL_INDEX (3941)
A column index specified for sparse symmetric matrix is invalid.

MSK_RES_ERR_SYM_MAT_NOT_LOWER_TRINGULAR (3942)
Only the lower triangular part of sparse symmetric matrix should be specified.

MSK_RES_ERR_SYM_MAT_INVALID_VALUE (3943)
The numerical value specified in a sparse symmetric matrix is not a floating point value.

MSK_RES_ERR_SYM_MAT_DUPLICATE (3944)
A value in a symmetric matrix as been specified more than once.

MSK_RES_ERR_INVALID_SYM_MAT_DIM (3950)
A sparse symmetric matrix of invalid dimension is specified.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_SYM_MAT (4000)
The file format does not support a problem with symmetric matrix variables.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_CFIX (4001)
The file format does not support a problem with nonzero fixed term in c.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_RANGED_CONSTRAINTS (4002)
The file format does not support a problem with ranged constraints.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_FREE_CONSTRAINTS (4003)
The file format does not support a problem with free constraints.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_CONES (4005)
The file format does not support a problem with conic constraints.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_NONLINEAR (4010)
The file format does not support a problem with nonlinear terms.

MSK_RES_ERR_DUPLICATE_CONSTRAINT_NAMES (4500)
Two constraint names are identical.

MSK_RES_ERR_DUPLICATE_VARIABLE_NAMES (4501)
Two variable names are identical.

MSK_RES_ERR_DUPLICATE_BARVARIABLE_NAMES (4502)
Two barvariable names are identical.

MSK_RES_ERR_DUPLICATE_CONE_NAMES (4503)
Two cone names are identical.

MSK_RES_ERR_NON_UNIQUE_ARRAY (5000)
An array does not contain unique elements.

MSK_RES_ERR_ARGUMENT_IS_TOO_LARGE (5005)
The value of a function argument is too large.

MSK_RES_ERR_MIO_INTERNAL (5010)
A fatal error occurred in the mixed integer optimizer. Please contact **MOSEK** support.

MSK_RES_ERR_INVALID_PROBLEM_TYPE (6000)
An invalid problem type.

MSK_RES_ERR_UNHANDLED_SOLUTION_STATUS (6010)
Unhandled solution status.

MSK_RES_ERR_UPPER_TRIANGLE (6020)
An element in the upper triangle of a lower triangular matrix is specified.

MSK_RES_ERR_LAU_SINGULAR_MATRIX (7000)
A matrix is singular.

MSK_RES_ERR_LAU_NOT_POSITIVE_DEFINITE (7001)
A matrix is not positive definite.

MSK_RES_ERR_LAU_INVALID_LOWER_TRIANGULAR_MATRIX (7002)
An invalid lower triangular matrix.

MSK_RES_ERR_LAU_UNKNOWN (7005)
An unknown error.

MSK_RES_ERR_LAU_ARG_M (7010)
Invalid argument m.

MSK_RES_ERR_LAU_ARG_N (7011)
Invalid argument n.

MSK_RES_ERR_LAU_ARG_K (7012)
Invalid argument k.

MSK_RES_ERR_LAU_ARG_TRANSA (7015)
Invalid argument transa.

MSK_RES_ERR_LAU_ARG_TRANSB (7016)
Invalid argument transb.

MSK_RES_ERR_LAU_ARG_UPLO (7017)
Invalid argument uplo.

MSK_RES_ERR_LAU_ARG_TRANS (7018)
Invalid argument trans.

MSK_RES_ERR_LAU_INVALID_SPARSE_SYMMETRIC_MATRIX (7019)
An invalid sparse symmetric matrix is specified. Note only the lower triangular part with no duplicates is specified.

MSK_RES_ERR_CBF_PARSE (7100)
An error occurred while parsing an CBF file.

MSK_RES_ERR_CBF_OBJ_SENSE (7101)
An invalid objective sense is specified.

MSK_RES_ERR_CBF_NO_VARIABLES (7102)
No variables are specified.

MSK_RES_ERR_CBF_TOO_MANY_CONSTRAINTS (7103)
Too many constraints specified.

MSK_RES_ERR_CBF_TOO_MANY_VARIABLES (7104)
Too many variables specified.

MSK_RES_ERR_CBF_NO_VERSION_SPECIFIED (7105)
No version specified.

MSK_RES_ERR_CBF_SYNTAX (7106)
Invalid syntax.

MSK_RES_ERR_CBF_DUPLICATE_OBJ (7107)
Duplicate OBJ keyword.

MSK_RES_ERR_CBF_DUPLICATE_CON (7108)
Duplicate CON keyword.

MSK_RES_ERR_CBF_DUPLICATE_VAR (7109)
Duplicate VAR keyword.

MSK_RES_ERR_CBF_DUPLICATE_INT (7110)
Duplicate INT keyword.

MSK_RES_ERR_CBF_INVALID_VAR_TYPE (7111)
Invalid variable type.

MSK_RES_ERR_CBF_INVALID_CON_TYPE (7112)
Invalid constraint type.

MSK_RES_ERR_CBF_INVALID_DOMAIN_DIMENSION (7113)
Invalid domain dimension.

MSK_RES_ERR_CBF_DUPLICATE_OBJCOORD (7114)
Duplicate index in OBJCOORD.

MSK_RES_ERR_CBF_DUPLICATE_BCOORD (7115)
Duplicate index in BCOORD.

MSK_RES_ERR_CBF_DUPLICATE_ACOORD (7116)
Duplicate index in ACOORD.

MSK_RES_ERR_CBF_TOO_FEW_VARIABLES (7117)
Too few variables defined.

MSK_RES_ERR_CBF_TOO_FEW_CONSTRAINTS (7118)
Too few constraints defined.

MSK_RES_ERR_CBF_TOO_FEW_INTS (7119)
Too few ints are specified.

MSK_RES_ERR_CBF_TOO_MANY_INTS (7120)
Too many ints are specified.

MSK_RES_ERR_CBF_INVALID_INT_INDEX (7121)
Invalid INT index.

MSK_RES_ERR_CBF_UNSUPPORTED (7122)
Unsupported feature is present.

MSK_RES_ERR_CBF_DUPLICATE_PSDVAR (7123)
Duplicate PSDVAR keyword.

MSK_RES_ERR_CBF_INVALID_PSDVAR_DIMENSION (7124)
Invalid PSDVAR dimension.

MSK_RES_ERR_CBF_TOO_FEW_PSDVAR (7125)
Too few variables defined.

MSK_RES_ERR_CBF_INVALID_EXP_DIMENSION (7126)
Invalid dimension of a exponential cone.

MSK_RES_ERR_CBF_DUPLICATE_POW_CONES (7130)
Multiple POWCONES specified.

MSK_RES_ERR_CBF_DUPLICATE_POW_STAR_CONES (7131)
Multiple POW*CONES specified.

MSK_RES_ERR_CBF_INVALID_POWER (7132)
Invalid power specified.

MSK_RES_ERR_CBF_POWER_CONE_IS_TOO_LONG (7133)
Power cone is too long.

MSK_RES_ERR_CBF_INVALID_POWER_CONE_INDEX (7134)
Invalid power cone index.

MSK_RES_ERR_CBF_INVALID_POWER_STAR_CONE_INDEX (7135)
 Invalid power star cone index.

MSK_RES_ERR_CBF_UNHANDLED_POWER_CONE_TYPE (7136)
 An unhandled power cone type.

MSK_RES_ERR_CBF_UNHANDLED_POWER_STAR_CONE_TYPE (7137)
 An unhandled power star cone type.

MSK_RES_ERR_CBF_POWER_CONE_MISMATCH (7138)
 The power cone does not match with its definition.

MSK_RES_ERR_CBF_POWER_STAR_CONE_MISMATCH (7139)
 The power star cone does not match with its definition.

MSK_RES_ERR_CBF_INVALID_NUMBER_OF_CONES (7740)
 Invalid number of cones.

MSK_RES_ERR_CBF_INVALID_DIMENSION_OF_CONES (7741)
 Invalid dimension of cones.

MSK_RES_ERR_MIO_INVALID_ROOT_OPTIMIZER (7700)
 An invalid root optimizer was selected for the problem type.

MSK_RES_ERR_MIO_INVALID_NODE_OPTIMIZER (7701)
 An invalid node optimizer was selected for the problem type.

MSK_RES_ERR_TOCONIC_CONSTR_Q_NOT_PSD (7800)
 The matrix defining the quadratic part of constraint is not positive semidefinite.

MSK_RES_ERR_TOCONIC_CONSTRAINT_FX (7801)
 The quadratic constraint is an equality, thus not convex.

MSK_RES_ERR_TOCONIC_CONSTRAINT_RA (7802)
 The quadratic constraint has finite lower and upper bound, and therefore it is not convex.

MSK_RES_ERR_TOCONIC_CONSTR_NOT_CONIC (7803)
 The constraint is not conic representable.

MSK_RES_ERR_TOCONIC_OBJECTIVE_NOT_PSD (7804)
 The matrix defining the quadratic part of the objective function is not positive semidefinite.

MSK_RES_ERR_SERVER_CONNECT (8000)
 Failed to connect to remote solver server. The server string or the port string were invalid, or the server did not accept connection.

MSK_RES_ERR_SERVER_PROTOCOL (8001)
 Unexpected message or data from solver server.

MSK_RES_ERR_SERVER_STATUS (8002)
 Server returned non-ok HTTP status code

MSK_RES_ERR_SERVER_TOKEN (8003)
 The job ID specified is incorrect or invalid

15.7 Enumerations

MSKbasindtypee

Basis identification

MSK_BI_NEVER (0)

Never do basis identification.

MSK_BI_ALWAYS (1)

Basis identification is always performed even if the interior-point optimizer terminates abnormally.

MSK_BI_NO_ERROR (2)

Basis identification is performed if the interior-point optimizer terminates without an error.

MSK_BI_IF_FEASIBLE (3)

Basis identification is not performed if the interior-point optimizer terminates with a problem status saying that the problem is primal or dual infeasible.

MSK_BI_RESERVED (4)

Not currently in use.

MSKboundkeye

Bound keys

MSK_BK_LO (0)
The constraint or variable has a finite lower bound and an infinite upper bound.

MSK_BK_UP (1)
The constraint or variable has an infinite lower bound and an finite upper bound.

MSK_BK_FX (2)
The constraint or variable is fixed.

MSK_BK_FR (3)
The constraint or variable is free.

MSK_BK_RA (4)
The constraint or variable is ranged.

MSKmarke
Mark

MSK_MARK_LO (0)
The lower bound is selected for sensitivity analysis.

MSK_MARK_UP (1)
The upper bound is selected for sensitivity analysis.

MSKsimdegene
Degeneracy strategies

MSK_SIM_DEGEN_NONE (0)
The simplex optimizer should use no degeneration strategy.

MSK_SIM_DEGEN_FREE (1)
The simplex optimizer chooses the degeneration strategy.

MSK_SIM_DEGEN_AGGRESSIVE (2)
The simplex optimizer should use an aggressive degeneration strategy.

MSK_SIM_DEGEN_MODERATE (3)
The simplex optimizer should use a moderate degeneration strategy.

MSK_SIM_DEGEN_MINIMUM (4)
The simplex optimizer should use a minimum degeneration strategy.

MSKtransposee
Transposed matrix.

MSK_TRANSPOSE_NO (0)
No transpose is applied.

MSK_TRANSPOSE_YES (1)
A transpose is applied.

MSKuploe
Triangular part of a symmetric matrix.

MSK_UPLO_LO (0)
Lower part.

MSK_UPLO_UP (1)
Upper part.

MSKsimreforme
Problem reformulation.

MSK_SIM_REFORMULATION_ON (1)
Allow the simplex optimizer to reformulate the problem.

MSK_SIM_REFORMULATION_OFF (0)
Disallow the simplex optimizer to reformulate the problem.

MSK_SIM_REFORMULATION_FREE (2)
The simplex optimizer can choose freely.

MSK_SIM_REFORMULATION_AGGRESSIVE (3)
The simplex optimizer should use an aggressive reformulation strategy.

MSKsimdupvece
Exploit duplicate columns.

MSK_SIM_EXPLOIT_DUPVEC_ON (1)
 Allow the simplex optimizer to exploit duplicated columns.

MSK_SIM_EXPLOIT_DUPVEC_OFF (0)
 Disallow the simplex optimizer to exploit duplicated columns.

MSK_SIM_EXPLOIT_DUPVEC_FREE (2)
 The simplex optimizer can choose freely.

MSKsimhotstarte
 Hot-start type employed by the simplex optimizer

MSK_SIM_HOTSTART_NONE (0)
 The simplex optimizer performs a coldstart.

MSK_SIM_HOTSTART_FREE (1)
 The simplex optimizer chooses the hot-start type.

MSK_SIM_HOTSTART_STATUS_KEYS (2)
 Only the status keys of the constraints and variables are used to choose the type of hot-start.

MSKintpntshotstarte
 Hot-start type employed by the interior-point optimizers.

MSK_INTPNT_HOTSTART_NONE (0)
 The interior-point optimizer performs a coldstart.

MSK_INTPNT_HOTSTART_PRIMAL (1)
 The interior-point optimizer exploits the primal solution only.

MSK_INTPNT_HOTSTART_DUAL (2)
 The interior-point optimizer exploits the dual solution only.

MSK_INTPNT_HOTSTART_PRIMAL_DUAL (3)
 The interior-point optimizer exploits both the primal and dual solution.

MSKpurifye
 Solution purification employed optimizer.

MSK_PURIFY_NONE (0)
 The optimizer performs no solution purification.

MSK_PURIFY_PRIMAL (1)
 The optimizer purifies the primal solution.

MSK_PURIFY_DUAL (2)
 The optimizer purifies the dual solution.

MSK_PURIFY_PRIMAL_DUAL (3)
 The optimizer purifies both the primal and dual solution.

MSK_PURIFY_AUTO (4)
 TBD

MSKcallbackcodee
 Progress callback codes

MSK_CALLBACK_BEGIN_BI (0)
 The basis identification procedure has been started.

MSK_CALLBACK_BEGIN_CONIC (1)
 The callback function is called when the conic optimizer is started.

MSK_CALLBACK_BEGIN_DUAL_BI (2)
 The callback function is called from within the basis identification procedure when the dual phase is started.

MSK_CALLBACK_BEGIN_DUAL_SENSITIVITY (3)
 Dual sensitivity analysis is started.

MSK_CALLBACK_BEGIN_DUAL_SETUP_BI (4)
 The callback function is called when the dual BI phase is started.

MSK_CALLBACK_BEGIN_DUAL_SIMPLEX (5)
 The callback function is called when the dual simplex optimizer started.

MSK_CALLBACK_BEGIN_DUAL_SIMPLEX_BI (6)
The callback function is called from within the basis identification procedure when the dual simplex clean-up phase is started.

MSK_CALLBACK_BEGIN_FULL_CONVEXITY_CHECK (7)
Begin full convexity check.

MSK_CALLBACK_BEGIN_INFEAS_ANA (8)
The callback function is called when the infeasibility analyzer is started.

MSK_CALLBACK_BEGIN_INTPNT (9)
The callback function is called when the interior-point optimizer is started.

MSK_CALLBACK_BEGIN_LICENSE_WAIT (10)
Begin waiting for license.

MSK_CALLBACK_BEGIN_MIO (11)
The callback function is called when the mixed-integer optimizer is started.

MSK_CALLBACK_BEGIN_OPTIMIZER (12)
The callback function is called when the optimizer is started.

MSK_CALLBACK_BEGIN_PRESOLVE (13)
The callback function is called when the presolve is started.

MSK_CALLBACK_BEGIN_PRIMAL_BI (14)
The callback function is called from within the basis identification procedure when the primal phase is started.

MSK_CALLBACK_BEGIN_PRIMAL_REPAIR (15)
Begin primal feasibility repair.

MSK_CALLBACK_BEGIN_PRIMAL_SENSITIVITY (16)
Primal sensitivity analysis is started.

MSK_CALLBACK_BEGIN_PRIMAL_SETUP_BI (17)
The callback function is called when the primal BI setup is started.

MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX (18)
The callback function is called when the primal simplex optimizer is started.

MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX_BI (19)
The callback function is called from within the basis identification procedure when the primal simplex clean-up phase is started.

MSK_CALLBACK_BEGIN_QCQO_REFORMULATE (20)
Begin QCQO reformulation.

MSK_CALLBACK_BEGIN_READ (21)
MOSEK has started reading a problem file.

MSK_CALLBACK_BEGIN_ROOT_CUTGEN (22)
The callback function is called when root cut generation is started.

MSK_CALLBACK_BEGIN_SIMPLEX (23)
The callback function is called when the simplex optimizer is started.

MSK_CALLBACK_BEGIN_SIMPLEX_BI (24)
The callback function is called from within the basis identification procedure when the simplex clean-up phase is started.

MSK_CALLBACK_BEGIN_TO_CONIC (25)
Begin conic reformulation.

MSK_CALLBACK_BEGIN_WRITE (26)
MOSEK has started writing a problem file.

MSK_CALLBACK_CONIC (27)
The callback function is called from within the conic optimizer after the information database has been updated.

MSK_CALLBACK_DUAL_SIMPLEX (28)
The callback function is called from within the dual simplex optimizer.

MSK_CALLBACK_END_BI (29)
The callback function is called when the basis identification procedure is terminated.

MSK_CALLBACK_END_CONIC (30)
The callback function is called when the conic optimizer is terminated.

MSK_CALLBACK_END_DUAL_BI (31)
The callback function is called from within the basis identification procedure when the dual phase is terminated.

MSK_CALLBACK_END_DUAL_SENSITIVITY (32)
Dual sensitivity analysis is terminated.

MSK_CALLBACK_END_DUAL_SETUP_BI (33)
The callback function is called when the dual BI phase is terminated.

MSK_CALLBACK_END_DUAL_SIMPLEX (34)
The callback function is called when the dual simplex optimizer is terminated.

MSK_CALLBACK_END_DUAL_SIMPLEX_BI (35)
The callback function is called from within the basis identification procedure when the dual clean-up phase is terminated.

MSK_CALLBACK_END_FULL_CONVEXITY_CHECK (36)
End full convexity check.

MSK_CALLBACK_END_INFEAS_ANA (37)
The callback function is called when the infeasibility analyzer is terminated.

MSK_CALLBACK_END_INTPNT (38)
The callback function is called when the interior-point optimizer is terminated.

MSK_CALLBACK_END_LICENSE_WAIT (39)
End waiting for license.

MSK_CALLBACK_END_MIO (40)
The callback function is called when the mixed-integer optimizer is terminated.

MSK_CALLBACK_END_OPTIMIZER (41)
The callback function is called when the optimizer is terminated.

MSK_CALLBACK_END_PRESOLVE (42)
The callback function is called when the presolve is completed.

MSK_CALLBACK_END_PRIMAL_BI (43)
The callback function is called from within the basis identification procedure when the primal phase is terminated.

MSK_CALLBACK_END_PRIMAL_REPAIR (44)
End primal feasibility repair.

MSK_CALLBACK_END_PRIMAL_SENSITIVITY (45)
Primal sensitivity analysis is terminated.

MSK_CALLBACK_END_PRIMAL_SETUP_BI (46)
The callback function is called when the primal BI setup is terminated.

MSK_CALLBACK_END_PRIMAL_SIMPLEX (47)
The callback function is called when the primal simplex optimizer is terminated.

MSK_CALLBACK_END_PRIMAL_SIMPLEX_BI (48)
The callback function is called from within the basis identification procedure when the primal clean-up phase is terminated.

MSK_CALLBACK_END_QCQO_REFORMULATE (49)
End QCQO reformulation.

MSK_CALLBACK_END_READ (50)
MOSEK has finished reading a problem file.

MSK_CALLBACK_END_ROOT_CUTGEN (51)
The callback function is called when root cut generation is terminated.

MSK_CALLBACK_END_SIMPLEX (52)
The callback function is called when the simplex optimizer is terminated.

MSK_CALLBACK_END_SIMPLEX_BI (53)
The callback function is called from within the basis identification procedure when the simplex clean-up phase is terminated.

MSK_CALLBACK_END_TO_CONIC (54)
End conic reformulation.

MSK_CALLBACK_END_WRITE (55)
MOSEK has finished writing a problem file.

MSK_CALLBACK_IM_BI (56)
The callback function is called from within the basis identification procedure at an intermediate point.

MSK_CALLBACK_IM_CONIC (57)
The callback function is called at an intermediate stage within the conic optimizer where the information database has not been updated.

MSK_CALLBACK_IM_DUAL_BI (58)
The callback function is called from within the basis identification procedure at an intermediate point in the dual phase.

MSK_CALLBACK_IM_DUAL_SENSIVITY (59)
The callback function is called at an intermediate stage of the dual sensitivity analysis.

MSK_CALLBACK_IM_DUAL_SIMPLEX (60)
The callback function is called at an intermediate point in the dual simplex optimizer.

MSK_CALLBACK_IM_FULL_CONVEXITY_CHECK (61)
The callback function is called at an intermediate stage of the full convexity check.

MSK_CALLBACK_IM_INTPNT (62)
The callback function is called at an intermediate stage within the interior-point optimizer where the information database has not been updated.

MSK_CALLBACK_IM_LICENSE_WAIT (63)
MOSEK is waiting for a license.

MSK_CALLBACK_IM_LU (64)
The callback function is called from within the LU factorization procedure at an intermediate point.

MSK_CALLBACK_IM_MIO (65)
The callback function is called at an intermediate point in the mixed-integer optimizer.

MSK_CALLBACK_IM_MIO_DUAL_SIMPLEX (66)
The callback function is called at an intermediate point in the mixed-integer optimizer while running the dual simplex optimizer.

MSK_CALLBACK_IM_MIO_INTPNT (67)
The callback function is called at an intermediate point in the mixed-integer optimizer while running the interior-point optimizer.

MSK_CALLBACK_IM_MIO_PRIMAL_SIMPLEX (68)
The callback function is called at an intermediate point in the mixed-integer optimizer while running the primal simplex optimizer.

MSK_CALLBACK_IM_ORDER (69)
The callback function is called from within the matrix ordering procedure at an intermediate point.

MSK_CALLBACK_IM_PRESOLVE (70)
The callback function is called from within the presolve procedure at an intermediate stage.

MSK_CALLBACK_IM_PRIMAL_BI (71)
The callback function is called from within the basis identification procedure at an intermediate point in the primal phase.

MSK_CALLBACK_IM_PRIMAL_SENSIVITY (72)

The callback function is called at an intermediate stage of the primal sensitivity analysis.

MSK_CALLBACK_IM_PRIMAL_SIMPLEX (73)

The callback function is called at an intermediate point in the primal simplex optimizer.

MSK_CALLBACK_IM_QO_REFORMULATE (74)

The callback function is called at an intermediate stage of the conic quadratic reformulation.

MSK_CALLBACK_IM_READ (75)

Intermediate stage in reading.

MSK_CALLBACK_IM_ROOT_CUTGEN (76)

The callback is called from within root cut generation at an intermediate stage.

MSK_CALLBACK_IM_SIMPLEX (77)

The callback function is called from within the simplex optimizer at an intermediate point.

MSK_CALLBACK_IM_SIMPLEX_BI (78)

The callback function is called from within the basis identification procedure at an intermediate point in the simplex clean-up phase. The frequency of the callbacks is controlled by the *MSK_IPAR_LOG_SIM_FREQ* parameter.

MSK_CALLBACK_INTPNT (79)

The callback function is called from within the interior-point optimizer after the information database has been updated.

MSK_CALLBACK_NEW_INT_MIO (80)

The callback function is called after a new integer solution has been located by the mixed-integer optimizer.

MSK_CALLBACK_PRIMAL_SIMPLEX (81)

The callback function is called from within the primal simplex optimizer.

MSK_CALLBACK_READ_OPF (82)

The callback function is called from the OPF reader.

MSK_CALLBACK_READ_OPF_SECTION (83)

A chunk of Q non-zeros has been read from a problem file.

MSK_CALLBACK_SOLVING_REMOTE (84)

The callback function is called while the task is being solved on a remote server.

MSK_CALLBACK_UPDATE_DUAL_BI (85)

The callback function is called from within the basis identification procedure at an intermediate point in the dual phase.

MSK_CALLBACK_UPDATE_DUAL_SIMPLEX (86)

The callback function is called in the dual simplex optimizer.

MSK_CALLBACK_UPDATE_DUAL_SIMPLEX_BI (87)

The callback function is called from within the basis identification procedure at an intermediate point in the dual simplex clean-up phase. The frequency of the callbacks is controlled by the *MSK_IPAR_LOG_SIM_FREQ* parameter.

MSK_CALLBACK_UPDATE_PRESOLVE (88)

The callback function is called from within the presolve procedure.

MSK_CALLBACK_UPDATE_PRIMAL_BI (89)

The callback function is called from within the basis identification procedure at an intermediate point in the primal phase.

MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX (90)

The callback function is called in the primal simplex optimizer.

MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX_BI (91)

The callback function is called from within the basis identification procedure at an intermediate point in the primal simplex clean-up phase. The frequency of the callbacks is controlled by the *MSK_IPAR_LOG_SIM_FREQ* parameter.

MSK_CALLBACK_WRITE_OPF (92)

The callback function is called from the OPF writer.

MSKcheckconvexitytypee

Types of convexity checks.

MSK_CHECK_CONVEXITY_NONE (0)

No convexity check.

MSK_CHECK_CONVEXITY_SIMPLE (1)

Perform simple and fast convexity check.

MSK_CHECK_CONVEXITY_FULL (2)

Perform a full convexity check.

MSKcompresstypee

Compression types

MSK_COMPRESS_NONE (0)

No compression is used.

MSK_COMPRESS_FREE (1)

The type of compression used is chosen automatically.

MSK_COMPRESS_GZIP (2)

The type of compression used is gzip compatible.

MSK_COMPRESS_ZSTD (3)

The type of compression used is zstd compatible.

MSKconetypee

Cone types

MSK_CT_QUAD (0)

The cone is a quadratic cone.

MSK_CT_RQUAD (1)

The cone is a rotated quadratic cone.

MSK_CT_PEXP (2)

A primal exponential cone.

MSK_CT_DEXP (3)

A dual exponential cone.

MSK_CT_PPOW (4)

A primal power cone.

MSK_CT_DPOW (5)

A dual power cone.

MSK_CT_ZERO (6)

The zero cone.

MSKnametypee

Name types

MSK_NAME_TYPE_GEN (0)

General names. However, no duplicate and blank names are allowed.

MSK_NAME_TYPE_MPS (1)

MPS type names.

MSK_NAME_TYPE_LP (2)

LP type names.

MSKscope

SCopt operator types

MSK_OPR_ENT (0)

Entropy

MSK_OPR_EXP (1)

Exponential

MSK_OPR_LOG (2)

Logarithm

MSK_OPR_POW (3)

Power

MSK_OPR_SQRT (4)
Square root

MSKsymmattypee
Cone types

MSK_SYMMAT_TYPE_SPARSE (0)
Sparse symmetric matrix.

MSKdataformat
Data format types

MSK_DATA_FORMAT_EXTENSION (0)
The file extension is used to determine the data file format.

MSK_DATA_FORMAT_MPS (1)
The data file is MPS formatted.

MSK_DATA_FORMAT_LP (2)
The data file is LP formatted.

MSK_DATA_FORMAT_OP (3)
The data file is an optimization problem formatted file.

MSK_DATA_FORMAT_FREE_MPS (4)
The data a free MPS formatted file.

MSK_DATA_FORMAT_TASK (5)
Generic task dump file.

MSK_DATA_FORMAT_PTF (6)
(P)retty (T)ext (F)format.

MSK_DATA_FORMAT_CB (7)
Conic benchmark format,

MSK_DATA_FORMAT_JSON_TASK (8)
JSON based task format.

MSKdinfiteme
Double information items

MSK_DINF_BI_CLEAN_DUAL_TIME (0)
Time spent within the dual clean-up optimizer of the basis identification procedure since its invocation.

MSK_DINF_BI_CLEAN_PRIMAL_TIME (1)
Time spent within the primal clean-up optimizer of the basis identification procedure since its invocation.

MSK_DINF_BI_CLEAN_TIME (2)
Time spent within the clean-up phase of the basis identification procedure since its invocation.

MSK_DINF_BI_DUAL_TIME (3)
Time spent within the dual phase basis identification procedure since its invocation.

MSK_DINF_BI_PRIMAL_TIME (4)
Time spent within the primal phase of the basis identification procedure since its invocation.

MSK_DINF_BI_TIME (5)
Time spent within the basis identification procedure since its invocation.

MSK_DINF_INTPNT_DUAL_FEAS (6)
Dual feasibility measure reported by the interior-point optimizer. (For the interior-point optimizer this measure is not directly related to the original problem because a homogeneous model is employed.)

MSK_DINF_INTPNT_DUAL_OBJ (7)
Dual objective value reported by the interior-point optimizer.

MSK_DINF_INTPNT_FACTOR_NUM_FLOPS (8)
An estimate of the number of flops used in the factorization.

MSK_DINF_INTPNT_OPT_STATUS (9)

A measure of optimality of the solution. It should converge to +1 if the problem has a primal-dual optimal solution, and converge to -1 if the problem is (strictly) primal or dual infeasible. If the measure converges to another constant, or fails to settle, the problem is usually ill-posed.

MSK_DINF_INTPNT_ORDER_TIME (10)

Order time (in seconds).

MSK_DINF_INTPNT_PRIMAL_FEAS (11)

Primal feasibility measure reported by the interior-point optimizer. (For the interior-point optimizer this measure is not directly related to the original problem because a homogeneous model is employed).

MSK_DINF_INTPNT_PRIMAL_OBJ (12)

Primal objective value reported by the interior-point optimizer.

MSK_DINF_INTPNT_TIME (13)

Time spent within the interior-point optimizer since its invocation.

MSK_DINF_MIO_CLIQUE_SEPARATION_TIME (14)

Separation time for clique cuts.

MSK_DINF_MIO_CMIR_SEPARATION_TIME (15)

Separation time for CMIR cuts.

MSK_DINF_MIO_CONSTRUCT_SOLUTION_OBJ (16)

If **MOSEK** has successfully constructed an integer feasible solution, then this item contains the optimal objective value corresponding to the feasible solution.

MSK_DINF_MIO_DUAL_BOUND_AFTER_PRESOLVE (17)

Value of the dual bound after presolve but before cut generation.

MSK_DINF_MIO_GMI_SEPARATION_TIME (18)

Separation time for GMI cuts.

MSK_DINF_MIO_IMPLIED_BOUND_TIME (19)

Separation time for implied bound cuts.

MSK_DINF_MIO_KNAPSACK_COVER_SEPARATION_TIME (20)

Separation time for knapsack cover.

MSK_DINF_MIO_OBJ_ABS_GAP (21)

Given the mixed-integer optimizer has computed a feasible solution and a bound on the optimal objective value, then this item contains the absolute gap defined by

$$|(\text{objective value of feasible solution}) - (\text{objective bound})|.$$

Otherwise it has the value -1.0.

MSK_DINF_MIO_OBJ_BOUND (22)

The best known bound on the objective function. This value is undefined until at least one relaxation has been solved: To see if this is the case check that *MSK_IINF_MIO_NUM_RELAX* is strictly positive.

MSK_DINF_MIO_OBJ_INT (23)

The primal objective value corresponding to the best integer feasible solution. Please note that at least one integer feasible solution must have been located i.e. check *MSK_IINF_MIO_NUM_INT_SOLUTIONS*.

MSK_DINF_MIO_OBJ_REL_GAP (24)

Given that the mixed-integer optimizer has computed a feasible solution and a bound on the optimal objective value, then this item contains the relative gap defined by

$$\frac{|(\text{objective value of feasible solution}) - (\text{objective bound})|}{\max(\delta, |(\text{objective value of feasible solution})|)}.$$

where δ is given by the parameter *MSK_DPAR_MIO_REL_GAP_CONST*. Otherwise it has the value -1.0.

MSK_DINF_MIO_PROBING_TIME (25)
Total time for probing.

MSK_DINF_MIO_ROOT_CUTGEN_TIME (26)
Total time for cut generation.

MSK_DINF_MIO_ROOT_OPTIMIZER_TIME (27)
Time spent in the optimizer while solving the root node relaxation

MSK_DINF_MIO_ROOT_PRESOLVE_TIME (28)
Time spent presolving the problem at the root node.

MSK_DINF_MIO_TIME (29)
Time spent in the mixed-integer optimizer.

MSK_DINF_MIO_USER_OBJ_CUT (30)
If the objective cut is used, then this information item has the value of the cut.

MSK_DINF_OPTIMIZER_TIME (31)
Total time spent in the optimizer since it was invoked.

MSK_DINF_PRESOLVE_ELI_TIME (32)
Total time spent in the eliminator since the presolve was invoked.

MSK_DINF_PRESOLVE_LINDEP_TIME (33)
Total time spent in the linear dependency checker since the presolve was invoked.

MSK_DINF_PRESOLVE_TIME (34)
Total time (in seconds) spent in the presolve since it was invoked.

MSK_DINF_PRIMAL_REPAIR_PENALTY_OBJ (35)
The optimal objective value of the penalty function.

MSK_DINF_QCQO_REFORMULATE_MAX_PERTURBATION (36)
Maximum absolute diagonal perturbation occurring during the QCQO reformulation.

MSK_DINF_QCQO_REFORMULATE_TIME (37)
Time spent with conic quadratic reformulation.

MSK_DINF_QCQO_REFORMULATE_WORST_CHOLESKY_COLUMN_SCALING (38)
Worst Cholesky column scaling.

MSK_DINF_QCQO_REFORMULATE_WORST_CHOLESKY_DIAG_SCALING (39)
Worst Cholesky diagonal scaling.

MSK_DINF_RD_TIME (40)
Time spent reading the data file.

MSK_DINF_SIM_DUAL_TIME (41)
Time spent in the dual simplex optimizer since invoking it.

MSK_DINF_SIM_FEAS (42)
Feasibility measure reported by the simplex optimizer.

MSK_DINF_SIM_OBJ (43)
Objective value reported by the simplex optimizer.

MSK_DINF_SIM_PRIMAL_TIME (44)
Time spent in the primal simplex optimizer since invoking it.

MSK_DINF_SIM_TIME (45)
Time spent in the simplex optimizer since invoking it.

MSK_DINF_SOL_BAS_DUAL_OBJ (46)
Dual objective value of the basic solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_BAS_DVIOLCON (47)
Maximal dual bound violation for x^c in the basic solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_BAS_DVIOLVAR (48)
Maximal dual bound violation for x^x in the basic solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_BAS_NRM_BARX (49)
Infinity norm of \bar{X} in the basic solution.

MSK_DINF_SOL_BAS_NRM_SLC (50)
Infinity norm of s_l^c in the basic solution.

MSK_DINF_SOL_BAS_NRM_SLX (51)
Infinity norm of s_l^x in the basic solution.

MSK_DINF_SOL_BAS_NRM_SUC (52)
Infinity norm of s_u^c in the basic solution.

MSK_DINF_SOL_BAS_NRM_SUX (53)
Infinity norm of s_u^X in the basic solution.

MSK_DINF_SOL_BAS_NRM_XC (54)
Infinity norm of x^c in the basic solution.

MSK_DINF_SOL_BAS_NRM_XX (55)
Infinity norm of x^x in the basic solution.

MSK_DINF_SOL_BAS_NRM_Y (56)
Infinity norm of y in the basic solution.

MSK_DINF_SOL_BAS_PRIMAL_OBJ (57)
Primal objective value of the basic solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_BAS_PVIOLCON (58)
Maximal primal bound violation for x^c in the basic solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_BAS_PVIOLVAR (59)
Maximal primal bound violation for x^x in the basic solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITG_NRM_BARX (60)
Infinity norm of \bar{X} in the integer solution.

MSK_DINF_SOL_ITG_NRM_XC (61)
Infinity norm of x^c in the integer solution.

MSK_DINF_SOL_ITG_NRM_XX (62)
Infinity norm of x^x in the integer solution.

MSK_DINF_SOL_ITG_PRIMAL_OBJ (63)
Primal objective value of the integer solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITG_PVIOLBARVAR (64)
Maximal primal bound violation for \bar{X} in the integer solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITG_PVIOLCON (65)
Maximal primal bound violation for x^c in the integer solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITG_PVIOLCONES (66)
Maximal primal violation for primal conic constraints in the integer solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITG_PVIOLITG (67)
Maximal violation for the integer constraints in the integer solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITG_PVIOLVAR (68)
Maximal primal bound violation for x^x in the integer solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITR_DUAL_OBJ (69)
Dual objective value of the interior-point solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITR_DVIOLBARVAR (70)
Maximal dual bound violation for \bar{X} in the interior-point solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITR_DVIOLCON (71)
Maximal dual bound violation for x^c in the interior-point solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITR_DVIOLCONES (72)
Maximal dual violation for dual conic constraints in the interior-point solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITR_DVIOLVAR (73)
Maximal dual bound violation for x^x in the interior-point solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITR_NRM_BARS (74)
Infinity norm of \bar{S} in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_BARX (75)
Infinity norm of \bar{X} in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_SLC (76)
Infinity norm of s_l^c in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_SLX (77)
Infinity norm of s_l^x in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_SNX (78)
Infinity norm of s_n^x in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_SUC (79)
Infinity norm of s_u^c in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_SUX (80)
Infinity norm of s_u^X in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_XC (81)
Infinity norm of x^c in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_XX (82)
Infinity norm of x^x in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_Y (83)
Infinity norm of y in the interior-point solution.

MSK_DINF_SOL_ITR_PRIMAL_OBJ (84)
Primal objective value of the interior-point solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITR_PVIOLBARVAR (85)
Maximal primal bound violation for \bar{X} in the interior-point solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITR_PVIOLCON (86)
Maximal primal bound violation for x^c in the interior-point solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITR_PVIOLCONES (87)
Maximal primal violation for primal conic constraints in the interior-point solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_SOL_ITR_PVIOLVAR (88)
Maximal primal bound violation for x^x in the interior-point solution. Updated if *MSK_IPAR_AUTO_UPDATE_SOL_INFO* is set or by the method *MSK_updatesolutioninfo*.

MSK_DINF_TO_CONIC_TIME (89)
Time spent in the last to conic reformulation.

MSKfeatureee
License feature

MSK_FEATURE_PTS (0)
Base system.

MSK_FEATURE_PTON (1)
Conic extension.

MSKliinfiteme
Long integer information items.

MSK_LIINF_BI_CLEAN_DUAL_DEG_ITER (0)
Number of dual degenerate clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_DUAL_ITER (1)
Number of dual clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_DEG_ITER (2)
Number of primal degenerate clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_ITER (3)
Number of primal clean iterations performed in the basis identification.

MSK_LIINF_BI_DUAL_ITER (4)
Number of dual pivots performed in the basis identification.

MSK_LIINF_BI_PRIMAL_ITER (5)
Number of primal pivots performed in the basis identification.

MSK_LIINF_INTPNT_FACTOR_NUM_NZ (6)
Number of non-zeros in factorization.

MSK_LIINF_MIO_ANZ (7)
Number of non-zero entries in the constraint matrix of the problem to be solved by the mixed-integer optimizer.

MSK_LIINF_MIO_INTPNT_ITER (8)
Number of interior-point iterations performed by the mixed-integer optimizer.

MSK_LIINF_MIO_PRESOLVED_ANZ (9)
Number of non-zero entries in the constraint matrix of the problem after the mixed-integer optimizer's presolve.

MSK_LIINF_MIO_SIMPLEX_ITER (10)
Number of simplex iterations performed by the mixed-integer optimizer.

MSK_LIINF_RD_NUMANZ (11)
Number of non-zeros in A that is read.

MSK_LIINF_RD_NUMQNZ (12)
Number of Q non-zeros.

MSKiinfiteme
Integer information items.

MSK_IINF_ANA_PRO_NUM_CON (0)
Number of constraints in the problem. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_CON_EQ (1)
Number of equality constraints. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_CON_FR (2)
Number of unbounded constraints. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_CON_LO (3)
Number of constraints with a lower bound and an infinite upper bound. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_CON_RA (4)
Number of constraints with finite lower and upper bounds. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_CON_UP (5)
Number of constraints with an upper bound and an infinite lower bound. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_VAR (6)
 Number of variables in the problem. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_VAR_BIN (7)
 Number of binary (0-1) variables. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_VAR_CONT (8)
 Number of continuous variables. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_VAR_EQ (9)
 Number of fixed variables. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_VAR_FR (10)
 Number of free variables. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_VAR_INT (11)
 Number of general integer variables. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_VAR_LO (12)
 Number of variables with a lower bound and an infinite upper bound. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_VAR_RA (13)
 Number of variables with finite lower and upper bounds. This value is set by *MSK_analyzeproblem*.

MSK_IINF_ANA_PRO_NUM_VAR_UP (14)
 Number of variables with an upper bound and an infinite lower bound. This value is set by *MSK_analyzeproblem*.

MSK_IINF_INTPNT_FACTOR_DIM_DENSE (15)
 Dimension of the dense sub system in factorization.

MSK_IINF_INTPNT_ITER (16)
 Number of interior-point iterations since invoking the interior-point optimizer.

MSK_IINF_INTPNT_NUM_THREADS (17)
 Number of threads that the interior-point optimizer is using.

MSK_IINF_INTPNT_SOLVE_DUAL (18)
 Non-zero if the interior-point optimizer is solving the dual problem.

MSK_IINF_MIO_ABSGAP_SATISFIED (19)
 Non-zero if absolute gap is within tolerances.

MSK_IINF_MIO_CLIQUE_TABLE_SIZE (20)
 Size of the clique table.

MSK_IINF_MIO_CONSTRUCT_SOLUTION (21)
 This item informs if **MOSEK** constructed an initial integer feasible solution.

- -1: tried, but failed,
- 0: no partial solution supplied by the user,
- 1: constructed feasible solution.

MSK_IINF_MIO_NODE_DEPTH (22)
 Depth of the last node solved.

MSK_IINF_MIO_NUM_ACTIVE_NODES (23)
 Number of active branch and bound nodes.

MSK_IINF_MIO_NUM_BRANCH (24)
 Number of branches performed during the optimization.

MSK_IINF_MIO_NUM_CLIQUE_CUTS (25)
 Number of clique cuts.

MSK_IINF_MIO_NUM_CMIR_CUTS (26)
 Number of Complemented Mixed Integer Rounding (CMIR) cuts.

MSK_IINF_MIO_NUM_GOMORY_CUTS (27)
 Number of Gomory cuts.

MSK_IINF_MIO_NUM_IMPLIED_BOUND_CUTS (28)
 Number of implied bound cuts.

MSK_IINF_MIO_NUM_INT_SOLUTIONS (29)
 Number of integer feasible solutions that have been found.

MSK_IINF_MIO_NUM_KNAPSACK_COVER_CUTS (30)
 Number of clique cuts.

MSK_IINF_MIO_NUM_RELAX (31)
 Number of relaxations solved during the optimization.

MSK_IINF_MIO_NUM_REPEATED_PRESOLVE (32)
 Number of times presolve was repeated at root.

MSK_IINF_MIO_NUMBIN (33)
 Number of binary variables in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMBINCONEVAR (34)
 Number of binary cone variables in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMCON (35)
 Number of constraints in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMCONE (36)
 Number of cones in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMCONEVAR (37)
 Number of cone variables in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMCONT (38)
 Number of continuous variables in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMCONTCONEVAR (39)
 Number of continuous cone variables in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMDEXPCONES (40)
 Number of dual exponential cones in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMDPOWCONES (41)
 Number of dual power cones in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMINT (42)
 Number of integer variables in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMINTCONEVAR (43)
 Number of integer cone variables in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMPEXPONES (44)
 Number of primal exponential cones in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMPPOWCONES (45)
 Number of primal power cones in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMQCONES (46)
 Number of quadratic cones in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMRQCONES (47)
 Number of rotated quadratic cones in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMVAR (48)
 Number of variables in the problem to be solved by the mixed-integer optimizer.

MSK_IINF_MIO_OBJ_BOUND_DEFINED (49)
 Non-zero if a valid objective bound has been found, otherwise zero.

MSK_IINF_MIO_PRESOLVED_NUMBIN (50)
 Number of binary variables in the problem after the mixed-integer optimizer's presolve.

MSK_IINF_MIO_PRESOLVED_NUMBINCONEVAR (51)
 Number of binary cone variables in the problem after the mixed-integer optimizer's presolve.

MSK_IINF_MIO_PRE SOLVED_NUMCON (52)
Number of constraints in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMCONE (53)
Number of cones in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMCONEVAR (54)
Number of cone variables in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMCONT (55)
Number of continuous variables in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMCONTCONEVAR (56)
Number of continuous cone variables in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMDEXPCONES (57)
Number of dual exponential cones in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMDPOWCONES (58)
Number of dual power cones in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMINT (59)
Number of integer variables in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMINTCONEVAR (60)
Number of integer cone variables in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMPEXP CONES (61)
Number of primal exponential cones in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMPPOWCONES (62)
Number of primal power cones in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMQCONES (63)
Number of quadratic cones in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMRQCONES (64)
Number of rotated quadratic cones in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_PRE SOLVED_NUMVAR (65)
Number of variables in the problem after the mixed-integer optimizer’s presolve.

MSK_IINF_MIO_RELGAP_SATISFIED (66)
Non-zero if relative gap is within tolerances.

MSK_IINF_MIO_TOTAL_NUM_CUTS (67)
Total number of cuts generated by the mixed-integer optimizer.

MSK_IINF_MIO_USER_OBJ_CUT (68)
If it is non-zero, then the objective cut is used.

MSK_IINF_OPT_NUMCON (69)
Number of constraints in the problem solved when the optimizer is called.

MSK_IINF_OPT_NUMVAR (70)
Number of variables in the problem solved when the optimizer is called

MSK_IINF_OPTIMIZE_RESPONSE (71)
The response code returned by optimize.

MSK_IINF_PURIFY_DUAL_SUCCESS (72)
Is nonzero if the dual solution is purified.

MSK_IINF_PURIFY_PRIMAL_SUCCESS (73)
Is nonzero if the primal solution is purified.

MSK_IINF_RD_NUMBARVAR (74)
Number of symmetric variables read.

MSK_IINF_RD_NUMCON (75)
Number of constraints read.

MSK_IINF_RD_NUMCONE (76)
Number of conic constraints read.

MSK_IINF_RD_NUMINTVAR (77)
Number of integer-constrained variables read.

MSK_IINF_RD_NUMQ (78)
Number of nonempty Q matrices read.

MSK_IINF_RD_NUMVAR (79)
Number of variables read.

MSK_IINF_RD_PROTOTYPE (80)
Problem type.

MSK_IINF_SIM_DUAL_DEG_ITER (81)
The number of dual degenerate iterations.

MSK_IINF_SIM_DUAL_HOTSTART (82)
If 1 then the dual simplex algorithm is solving from an advanced basis.

MSK_IINF_SIM_DUAL_HOTSTART_LU (83)
If 1 then a valid basis factorization of full rank was located and used by the dual simplex algorithm.

MSK_IINF_SIM_DUAL_INF_ITER (84)
The number of iterations taken with dual infeasibility.

MSK_IINF_SIM_DUAL_ITER (85)
Number of dual simplex iterations during the last optimization.

MSK_IINF_SIM_NUMCON (86)
Number of constraints in the problem solved by the simplex optimizer.

MSK_IINF_SIM_NUMVAR (87)
Number of variables in the problem solved by the simplex optimizer.

MSK_IINF_SIM_PRIMAL_DEG_ITER (88)
The number of primal degenerate iterations.

MSK_IINF_SIM_PRIMAL_HOTSTART (89)
If 1 then the primal simplex algorithm is solving from an advanced basis.

MSK_IINF_SIM_PRIMAL_HOTSTART_LU (90)
If 1 then a valid basis factorization of full rank was located and used by the primal simplex algorithm.

MSK_IINF_SIM_PRIMAL_INF_ITER (91)
The number of iterations taken with primal infeasibility.

MSK_IINF_SIM_PRIMAL_ITER (92)
Number of primal simplex iterations during the last optimization.

MSK_IINF_SIM_SOLVE_DUAL (93)
Is non-zero if dual problem is solved.

MSK_IINF_SOL_BAS_PROSTA (94)
Problem status of the basic solution. Updated after each optimization.

MSK_IINF_SOL_BAS_SOLSTA (95)
Solution status of the basic solution. Updated after each optimization.

MSK_IINF_SOL_ITG_PROSTA (96)
Problem status of the integer solution. Updated after each optimization.

MSK_IINF_SOL_ITG_SOLSTA (97)
Solution status of the integer solution. Updated after each optimization.

MSK_IINF_SOL_ITR_PROSTA (98)
Problem status of the interior-point solution. Updated after each optimization.

MSK_IINF_SOL_ITR_SOLSTA (99)
Solution status of the interior-point solution. Updated after each optimization.

MSK_IINF_STO_NUM_A_REALLOC (100)
 Number of times the storage for storing A has been changed. A large value may indicate that memory fragmentation may occur.

MSKinfypee
 Information item types

MSK_INF_DOU_TYPE (0)
 Is a double information type.

MSK_INF_INT_TYPE (1)
 Is an integer.

MSK_INF_LINT_TYPE (2)
 Is a long integer.

MSKiomodee
 Input/output modes

MSK_IOMODE_READ (0)
 The file is read-only.

MSK_IOMODE_WRITE (1)
 The file is write-only. If the file exists then it is truncated when it is opened. Otherwise it is created when it is opened.

MSK_IOMODE_READWRITE (2)
 The file is to read and write.

MSKbranchdire
 Specifies the branching direction.

MSK_BRANCH_DIR_FREE (0)
 The mixed-integer optimizer decides which branch to choose.

MSK_BRANCH_DIR_UP (1)
 The mixed-integer optimizer always chooses the up branch first.

MSK_BRANCH_DIR_DOWN (2)
 The mixed-integer optimizer always chooses the down branch first.

MSK_BRANCH_DIR_NEAR (3)
 Branch in direction nearest to selected fractional variable.

MSK_BRANCH_DIR_FAR (4)
 Branch in direction farthest from selected fractional variable.

MSK_BRANCH_DIR_ROOT_LP (5)
 Chose direction based on root lp value of selected variable.

MSK_BRANCH_DIR_GUIDED (6)
 Branch in direction of current incumbent.

MSK_BRANCH_DIR_PSEUDOCOST (7)
 Branch based on the pseudocost of the variable.

MSKmiocontsoltypee
 Continuous mixed-integer solution type

MSK_MIO_CONT_SOL_NONE (0)
 No interior-point or basic solution are reported when the mixed-integer optimizer is used.

MSK_MIO_CONT_SOL_ROOT (1)
 The reported interior-point and basic solutions are a solution to the root node problem when mixed-integer optimizer is used.

MSK_MIO_CONT_SOL_ITG (2)
 The reported interior-point and basic solutions are a solution to the problem with all integer variables fixed at the value they have in the integer solution. A solution is only reported in case the problem has a primal feasible solution.

MSK_MIO_CONT_SOL_ITG_REL (3)
 In case the problem is primal feasible then the reported interior-point and basic solutions are a solution to the problem with all integer variables fixed at the value they have in the integer

solution. If the problem is primal infeasible, then the solution to the root node problem is reported.

MSKmiomodee

Integer restrictions

MSK_MIO_MODE_IGNORED (0)

The integer constraints are ignored and the problem is solved as a continuous problem.

MSK_MIO_MODE_SATISFIED (1)

Integer restrictions should be satisfied.

MSKmionodeseltypee

Mixed-integer node selection types

MSK_MIO_NODE_SELECTION_FREE (0)

The optimizer decides the node selection strategy.

MSK_MIO_NODE_SELECTION_FIRST (1)

The optimizer employs a depth first node selection strategy.

MSK_MIO_NODE_SELECTION_BEST (2)

The optimizer employs a best bound node selection strategy.

MSK_MIO_NODE_SELECTION_PSEUDO (3)

The optimizer employs selects the node based on a pseudo cost estimate.

MSKmpsformate

MPS file format type

MSK_MPS_FORMAT_STRICT (0)

It is assumed that the input file satisfies the MPS format strictly.

MSK_MPS_FORMAT_RELAXED (1)

It is assumed that the input file satisfies a slightly relaxed version of the MPS format.

MSK_MPS_FORMAT_FREE (2)

It is assumed that the input file satisfies the free MPS format. This implies that spaces are not allowed in names. Otherwise the format is free.

MSK_MPS_FORMAT_CPLEX (3)

The CPLEX compatible version of the MPS format is employed.

MSKobjsensee

Objective sense types

MSK_OBJECTIVE_SENSE_MINIMIZE (0)

The problem should be minimized.

MSK_OBJECTIVE_SENSE_MAXIMIZE (1)

The problem should be maximized.

MSKonoffkeye

On/off

MSK_ON (1)

Switch the option on.

MSK_OFF (0)

Switch the option off.

MSKoptimizertypee

Optimizer types

MSK_OPTIMIZER_CONIC (0)

The optimizer for problems having conic constraints.

MSK_OPTIMIZER_DUAL_SIMPLEX (1)

The dual simplex optimizer is used.

MSK_OPTIMIZER_FREE (2)

The optimizer is chosen automatically.

MSK_OPTIMIZER_FREE_SIMPLEX (3)

One of the simplex optimizers is used.

MSK_OPTIMIZER_INTPNT (4)
The interior-point optimizer is used.

MSK_OPTIMIZER_MIXED_INT (5)
The mixed-integer optimizer.

MSK_OPTIMIZER_PRIMAL_SIMPLEX (6)
The primal simplex optimizer is used.

MSKorderingtypee
Ordering strategies

MSK_ORDER_METHOD_FREE (0)
The ordering method is chosen automatically.

MSK_ORDER_METHOD_APPMINLOC (1)
Approximate minimum local fill-in ordering is employed.

MSK_ORDER_METHOD_EXPERIMENTAL (2)
This option should not be used.

MSK_ORDER_METHOD_TRY_GRAPHPAR (3)
Always try the graph partitioning based ordering.

MSK_ORDER_METHOD_FORCE_GRAPHPAR (4)
Always use the graph partitioning based ordering even if it is worse than the approximate minimum local fill ordering.

MSK_ORDER_METHOD_NONE (5)
No ordering is used.

MSKpresolvemodee
Presolve method.

MSK_PRESOLVE_MODE_OFF (0)
The problem is not presolved before it is optimized.

MSK_PRESOLVE_MODE_ON (1)
The problem is presolved before it is optimized.

MSK_PRESOLVE_MODE_FREE (2)
It is decided automatically whether to presolve before the problem is optimized.

MSKparametertypee
Parameter type

MSK_PAR_INVALID_TYPE (0)
Not a valid parameter.

MSK_PAR_DOUB_TYPE (1)
Is a double parameter.

MSK_PAR_INT_TYPE (2)
Is an integer parameter.

MSK_PAR_STR_TYPE (3)
Is a string parameter.

MSKproblemiteme
Problem data items

MSK_PI_VAR (0)
Item is a variable.

MSK_PI_CON (1)
Item is a constraint.

MSK_PI_CONE (2)
Item is a cone.

MSKproblemtypede
Problem types

MSK_PROBTYPE_LO (0)
The problem is a linear optimization problem.

MSK_PROBTYPE_Q0 (1)
The problem is a quadratic optimization problem.

MSK_PROBTYPE_QCQ0 (2)
The problem is a quadratically constrained optimization problem.

MSK_PROBTYPE_CONIC (3)
A conic optimization.

MSK_PROBTYPE_MIXED (4)
General nonlinear constraints and conic constraints. This combination can not be solved by **MOSEK**.

MSKprostae
Problem status keys

MSK_PRO_STA_UNKNOWN (0)
Unknown problem status.

MSK_PRO_STA_PRIM_AND_DUAL_FEAS (1)
The problem is primal and dual feasible.

MSK_PRO_STA_PRIM_FEAS (2)
The problem is primal feasible.

MSK_PRO_STA_DUAL_FEAS (3)
The problem is dual feasible.

MSK_PRO_STA_PRIM_INFEAS (4)
The problem is primal infeasible.

MSK_PRO_STA_DUAL_INFEAS (5)
The problem is dual infeasible.

MSK_PRO_STA_PRIM_AND_DUAL_INFEAS (6)
The problem is primal and dual infeasible.

MSK_PRO_STA_ILL_POSED (7)
The problem is ill-posed. For example, it may be primal and dual feasible but have a positive duality gap.

MSK_PRO_STA_PRIM_INFEAS_OR_UNBOUNDED (8)
The problem is either primal infeasible or unbounded. This may occur for mixed-integer problems.

MSKxmlwriteroutputtypee
XML writer output mode

MSK_WRITE_XML_MODE_ROW (0)
Write in row order.

MSK_WRITE_XML_MODE_COL (1)
Write in column order.

MSKrescodetypee
Response code type

MSK_RESPONSE_OK (0)
The response code is OK.

MSK_RESPONSE_WRN (1)
The response code is a warning.

MSK_RESPONSE_TRM (2)
The response code is an optimizer termination status.

MSK_RESPONSE_ERR (3)
The response code is an error.

MSK_RESPONSE_UNK (4)
The response code does not belong to any class.

MSKscalingtypee
Scaling type

MSK_SCALING_FREE (0)
The optimizer chooses the scaling heuristic.

MSK_SCALING_NONE (1)
No scaling is performed.

MSK_SCALING_MODERATE (2)
A conservative scaling is performed.

MSK_SCALING_AGGRESSIVE (3)
A very aggressive scaling is performed.

MSKscalingmethode
Scaling method

MSK_SCALING_METHOD_POW2 (0)
Scales only with power of 2 leaving the mantissa untouched.

MSK_SCALING_METHOD_FREE (1)
The optimizer chooses the scaling heuristic.

MSKsensitivitytypee
Sensitivity types

MSK_SENSITIVITY_TYPE_BASIS (0)
Basis sensitivity analysis is performed.

MSKsimseltypee
Simplex selection strategy

MSK_SIM_SELECTION_FREE (0)
The optimizer chooses the pricing strategy.

MSK_SIM_SELECTION_FULL (1)
The optimizer uses full pricing.

MSK_SIM_SELECTION_ASE (2)
The optimizer uses approximate steepest-edge pricing.

MSK_SIM_SELECTION_DEVEK (3)
The optimizer uses devex steepest-edge pricing (or if it is not available an approximate steep-edge selection).

MSK_SIM_SELECTION_SE (4)
The optimizer uses steepest-edge selection (or if it is not available an approximate steep-edge selection).

MSK_SIM_SELECTION_PARTIAL (5)
The optimizer uses a partial selection approach. The approach is usually beneficial if the number of variables is much larger than the number of constraints.

MSKsoliteme
Solution items

MSK_SOL_ITEM_XC (0)
Solution for the constraints.

MSK_SOL_ITEM_XX (1)
Variable solution.

MSK_SOL_ITEM_Y (2)
Lagrange multipliers for equations.

MSK_SOL_ITEM_SLC (3)
Lagrange multipliers for lower bounds on the constraints.

MSK_SOL_ITEM_SUC (4)
Lagrange multipliers for upper bounds on the constraints.

MSK_SOL_ITEM_SLX (5)
Lagrange multipliers for lower bounds on the variables.

MSK_SOL_ITEM_SUX (6)
Lagrange multipliers for upper bounds on the variables.

MSK_SOL_ITEM_SNX (7)
 Lagrange multipliers corresponding to the conic constraints on the variables.

MSKsolstae
 Solution status keys

MSK_SOL_STA_UNKNOWN (0)
 Status of the solution is unknown.

MSK_SOL_STA_OPTIMAL (1)
 The solution is optimal.

MSK_SOL_STA_PRIM_FEAS (2)
 The solution is primal feasible.

MSK_SOL_STA_DUAL_FEAS (3)
 The solution is dual feasible.

MSK_SOL_STA_PRIM_AND_DUAL_FEAS (4)
 The solution is both primal and dual feasible.

MSK_SOL_STA_PRIM_INFEAS_CER (5)
 The solution is a certificate of primal infeasibility.

MSK_SOL_STA_DUAL_INFEAS_CER (6)
 The solution is a certificate of dual infeasibility.

MSK_SOL_STA_PRIM_ILLPOSED_CER (7)
 The solution is a certificate that the primal problem is illposed.

MSK_SOL_STA_DUAL_ILLPOSED_CER (8)
 The solution is a certificate that the dual problem is illposed.

MSK_SOL_STA_INTEGER_OPTIMAL (9)
 The primal solution is integer optimal.

MSKsoltypee
 Solution types

MSK_SOL_BAS (1)
 The basic solution.

MSK_SOL_ITR (0)
 The interior solution.

MSK_SOL_ITG (2)
 The integer solution.

MSKsolveforme
 Solve primal or dual form

MSK_SOLVE_FREE (0)
 The optimizer is free to solve either the primal or the dual problem.

MSK_SOLVE_PRIMAL (1)
 The optimizer should solve the primal problem.

MSK_SOLVE_DUAL (2)
 The optimizer should solve the dual problem.

MSKstakeye
 Status keys

MSK_SK_UNK (0)
 The status for the constraint or variable is unknown.

MSK_SK_BAS (1)
 The constraint or variable is in the basis.

MSK_SK_SUPBAS (2)
 The constraint or variable is super basic.

MSK_SK_LOW (3)
 The constraint or variable is at its lower bound.

MSK_SK_UPR (4)
 The constraint or variable is at its upper bound.

MSK_SK_FIX (5)
The constraint or variable is fixed.

MSK_SK_INF (6)
The constraint or variable is infeasible in the bounds.

MSKstartpointtypee
Starting point types

MSK_STARTING_POINT_FREE (0)
The starting point is chosen automatically.

MSK_STARTING_POINT_GUESS (1)
The optimizer guesses a starting point.

MSK_STARTING_POINT_CONSTANT (2)
The optimizer constructs a starting point by assigning a constant value to all primal and dual variables. This starting point is normally robust.

MSK_STARTING_POINT_SATISFY_BOUNDS (3)
The starting point is chosen to satisfy all the simple bounds on nonlinear variables. If this starting point is employed, then more care than usual should be employed when choosing the bounds on the nonlinear variables. In particular very tight bounds should be avoided.

MSKstreamtypee
Stream types

MSK_STREAM_LOG (0)
Log stream. Contains the aggregated contents of all other streams. This means that a message written to any other stream will also be written to this stream.

MSK_STREAM_MSG (1)
Message stream. Log information relating to performance and progress of the optimization is written to this stream.

MSK_STREAM_ERR (2)
Error stream. Error messages are written to this stream.

MSK_STREAM_WRN (3)
Warning stream. Warning messages are written to this stream.

MSKvaluee
Integer values

MSK_MAX_STR_LEN (1024)
Maximum string length allowed in **MOSEK**.

MSK_LICENSE_BUFFER_LENGTH (21)
The length of a license key buffer.

MSKvariabletypee
Variable types

MSK_VAR_TYPE_CONT (0)
Is a continuous variable.

MSK_VAR_TYPE_INT (1)
Is an integer variable.

15.8 Data Types

MSKenv_t
The **MOSEK** Environment type.

MSKtask_t
The **MOSEK** Task type.

MSKuserhandle_t
A pointer to a user-defined structure.

MSKboolean_t
A signed integer interpreted as a boolean value.

MSKint32t
Signed 32bit integer.

MSKint64t

Signed 64bit integer.

MSKwchar_t

Wide char type. The actual type may differ depending on the platform; it is either a 16 or 32 bits signed or unsigned integer.

MSKrealt

The floating point type used by **MOSEK**.

MSKstring_t

The string type used by **MOSEK**. This is an UTF-8 encoded zero-terminated char string.

15.9 Function Types

MSKcallbackfunc

```
MSKint32t (MSKAPI * MSKcallbackfunc) (  
    MSKtask_t task,  
    MSKuserhandle_t usrptr,  
    MSKcallbackcodee caller,  
    const MSKrealt * douinf,  
    const MSKint32t * intinf,  
    const MSKint64t * lintinf)
```

The progress callback function is a user-defined function which will be called by **MOSEK** occasionally during the optimization process. In particular, the callback function is called at the beginning of each iteration in the interior-point optimizer. For the simplex optimizers *MSK_IPAR_LOG_SIM_FREQ* controls how frequently the callback is called. The callback provides an code denoting the point in the solver from which the call happened, and a set of arrays containing information items related to the current state of the solver. Typically the user-defined callback function displays information about the solution process. The callback function can also be used to terminate the optimization process by returning a non-zero value.

The user *must not* call any **MOSEK** function directly or indirectly from the callback function. The only exception is the possibility to retrieve a current best integer solution from the mixed-integer optimizer, see Section *Progress and data callback*.

Parameters

- **task** (*MSKtask_t*) – An optimization task. (input)
- **usrptr** (*MSKuserhandle_t*) – A pointer to a user-defined structure. (input/output)
- **caller** (*MSKcallbackcodee*) – The caller key indicating the current progress of the solver. (input)
- **douinf** (*MSKrealt**) – An array of double information items. The elements correspond to the definitions in *MSKdinfiteme*. (input)
- **intinf** (*MSKint32t**) – An array of integer information items. The elements correspond to the definitions in *MSKiinfiteme*. (input)
- **lintinf** (*MSKint64t**) – An array of long information items. The elements correspond to the definitions in *MSKliinfiteme*. (input)

Return (*MSKint32t*) – If the return value is non-zero, **MOSEK** terminates whatever it is doing and returns control to the calling application.

MSKcallocfunc

```
void * (MSKAPI * MSKcallocfunc) (  
    MSKuserhandle_t usrptr,  
    const size_t num,  
    const size_t size)
```


A user-defined memory allocation function. The function must be compatible with the C `calloc` function.

Parameters

- `usrptr` (*MSKuserhandle_t*) – A pointer to a user-defined structure. (input)
- `num` (`size_t`) – The number of elements. (input)
- `size` (`size_t`) – The size of an element. (input)

Return (`void*`) – A pointer to the allocated memory.

MSKexitfunc

```
void (MSKAPI * MSKexitfunc) (  
    MSKuserhandle_t usrptr,  
    const char * file,  
    MSKint32t line,  
    const char * msg)
```

A user-defined exit function which is called in case of fatal errors to handle an error message and terminate the program. The function should never return.

Parameters

- `usrptr` (*MSKuserhandle_t*) – A pointer to a user-defined structure. (input/output)
- `file` (*MSKstring_t*) – The name of the file where the fatal error occurred. (input)
- `line` (*MSKint32t*) – The line number in the file where the fatal error occurred. (input)
- `msg` (*MSKstring_t*) – A message about the error. (input)

Return (`void`)

MSKfreefunc

```
void (MSKAPI * MSKfreefunc) (  
    MSKuserhandle_t usrptr,  
    void * buffer)
```

A user-defined memory freeing function.

Parameters

- `usrptr` (*MSKuserhandle_t*) – A pointer to a user-defined structure. (input)
- `buffer` (`void*`) – A pointer to the buffer which should be freed. (input/output)

Return (`void`)

MSKhreadfunc

```
size_t (MSKAPI * MSKhreadfunc) (  
    MSKuserhandle_t handle,  
    void * dest,  
    const size_t count)
```

Behaves similarly to system read function. Returns the number of bytes read.

Parameters

- `handle` (*MSKuserhandle_t*) – A pointer to a user-defined data structure (or a null pointer). (input/output)
- `dest` (`void*`) – Read into this destination (output)
- `count` (`size_t`) – Number of bytes to read. (input)

Return (`size_t`) – The function response code.

MSKwritefunc

```
size_t (MSKAPI * MSKwritefunc) (  
    MSKuserhandle_t handle,  
    void * src,  
    const size_t count)
```

Behaves similarly to system read function. Returns the number of bytes written.

Parameters

- `handle` (*MSKuserhandle_t*) – A pointer to a user-defined data structure (or a null pointer). (input/output)
- `src` (`void*`) – Write from this location (output)
- `count` (`size_t`) – Number of bytes to write. (input)

Return (`size_t`) – The function response code.

MSKmallocfunc

```
void * (MSKAPI * MSKmallocfunc) (  
    MSKuserhandle_t usrptr,  
    const size_t size)
```

A user-defined memory allocation function. The function must be compatible with the C `malloc` function.

Parameters

- `usrptr` (*MSKuserhandle_t*) – A pointer to a user-defined structure. (input)
- `size` (`size_t`) – The number of characters to allocate. (input)

Return (`void*`) – A pointer to the allocated memory.

MSKreallocfunc

```
void * (MSKAPI * MSKreallocfunc) (  
    MSKuserhandle_t usrptr,  
    void * ptr,  
    const size_t size)
```

A user-defined memory reallocation function. The function must be compatible with the C `realloc` function.

Parameters

- `usrptr` (*MSKuserhandle_t*) – A pointer to a user-defined structure. (input)
- `ptr` (`void*`) – The pointer to the allocated memory. (input/output)
- `size` (`size_t`) – Size of the new block. (input)

Return (`void*`) – A pointer to the allocated memory.

MSKresponsefunc

```
MSKrescodee (MSKAPI * MSKresponsefunc) (  
    MSKuserhandle_t handle,  
    MSKrescodee r,  
    const char * msg)
```

Whenever **MOSEK** generates a warning or an error this function is called. The argument `r` contains the code of the error/warning and the argument `msg` contains the corresponding error/warning message. This function should always return *MSK_RES_OK*.

Parameters

- `handle` (*MSKuserhandle_t*) – A pointer to a user-defined data structure (or a null pointer). (input/output)
- `r` (*MSKrescodee*) – The response code corresponding to the exception. (input)
- `msg` (*MSKstring_t*) – A string containing the exception message. (input)

Return (*MSKrescodee*) – The function response code.

MSKstreamfunc

```
void (MSKAPI * MSKstreamfunc) (  
    MSKuserhandle_t handle,  
    const char * str)
```

The message-stream callback function is a user-defined function which can be linked to any of the **MOSEK** streams. Doing so, the function is called whenever **MOSEK** sends a message to the stream.

The user *must not* call any **MOSEK** function directly or indirectly from the callback function.

Parameters

- `handle` (*MSKuserhandle_t*) – A pointer to a user-defined data structure (or a null pointer). (input/output)
- `str` (*MSKstring_t*) – A string containing a message to a stream. (input)

Return (void)

15.10 Nonlinear interfaces (obsolete)

Important: This is a legacy document for users familiar with SCopt, DGopt, EXPopt, mskenopt, mskscopt and mskgpopt from previous versions of **MOSEK**. These interfaces have now been removed. We assume familiarity with documentation included in version 8. All problems expressible with this interface can (and should) be reformulated using the exponential cone and power cones.

New users should formulate problems involving powers, logarithms and exponentials directly in conic form.

Conversion tutorial

We recommend converting all nonlinear problems using SCopt, DGopt, EXPopt, mskenopt, mskscopt and mskgpopt into conic form. Depending on the values of f, g, h either the epigraph or hypograph of a SCopt function if convex, and a bounding variable can be introduced following the basic rules below. We assume all variables are within safe bounds where the SCopt operators are defined and convex. We also assume $f > 0$.

A more comprehensive modeling guide for these types of problems can be found in the **MOSEK Modeling Cookbook**.

Powers

Consider $f(x + h)^g$. This can be reformulated using the power cone.

- If $g > 1$ then $t \geq f(x + h)^g$ is equivalent to $(t/f)^{1/g} \geq |x + h|$, that is $(t/f, 1, x + h) \in \mathcal{P}_3^{1/g, 1-1/g}$.
- If $0 < g < 1$ then $|t| \leq f(x + h)^g$ is equivalent to $(x + h, 1, t/f) \in \mathcal{P}_3^{g, 1-g}$.
- If $g < 0$ then $t \geq f(x + h)^g$ is equivalent to $(t/f)(x + h)^{-g} \geq 1$, that is $(t/f, x + h, 1) \in \mathcal{P}_3^{1/(1-g), -g/(1-g)}$.

Logarithm

The bound $t \leq f \log(gx + h)$ is equivalent to $(gx + h, 1, t/f) \in K_{\text{exp}}$.

Entropy

The bound $t \geq fx \log x$ is equivalent to $(1, x, -t/f) \in K_{\text{exp}}$.

Exponential

The bound $t \geq f \exp(gx + h)$ is equivalent to $(t/f, 1, gx + h) \in K_{\text{exp}}$.

Exponential optimization (EXPopt), Geometric programming (mskgpopt)

For a basic tutorial in geometric programming (GP) see [Sec. 6.8](#).

An exponential optimization problem in standard form consists of constraints of the type:

$$t \geq \log \left(\sum_i \exp(a_i^T x + b_i) \right).$$

This log-sum-exp bound is equivalent to

$$\sum_i \exp(a_i^T x + b_i - t) \leq 1$$

and requires bounding each exponential function as explained above.

Dual geometric optimization (DGopt)

The objective function of a dual geometric problem involves maximizing expressions of the form

$$x \log \frac{c}{x} \quad \text{and} \quad x_i \log \frac{e^T x}{x_i},$$

which can be achieved using bounds $t \leq x \log \frac{y}{x}$, that is $(t, x, y) \in K_{\text{exp}}$.

Chapter 16

Supported File Formats

MOSEK supports a range of problem and solution formats listed in [Table 16.1](#) and [Table 16.2](#). The **Task format** is **MOSEK**'s native binary format and it supports all features that **MOSEK** supports. The **OPF format** is **MOSEK**'s human-readable alternative that supports nearly all features (everything except semidefinite problems). In general, text formats are significantly slower to read, but can be examined and edited directly in any text editor.

Problem formats

Table 16.1: List of supported file formats for optimization problems. The column *Conic* refers to conic problems involving the quadratic, rotated quadratic, power or exponential cone. The last two columns indicate if the format supports solutions and optimizer parameters.

Format Type	Ext.	Binary/Text	LP	QO	Conic	SDP	Sol	Param
<i>LP</i>	lp	plain text	X	X				
<i>MPS</i>	mps	plain text	X	X	X			
<i>OPF</i>	opf	plain text	X	X	X		X	X
<i>PTF</i>	ptf	plain text	X	X	X	X	X	
<i>CBF</i>	cbf	plain text	X		X	X		
<i>Task format</i>	task	binary	X	X	X	X	X	X
<i>Jtask format</i>	jtask	text	X	X	X	X	X	X

Solution formats

Table 16.2: List of supported solution formats.

Format Type	Ext.	Binary/Text	Description
<i>SOL</i>	sol	plain text	Interior Solution
	bas	plain text	Basic Solution
	int	plain text	Integer
<i>Jsol format</i>	jsol	text	Solution

Compression

MOSEK supports GZIP and Zstandard compression. Problem files with extension `.gz` (for GZIP) and `.zst` (for Zstandard) are assumed to be compressed when read, and are automatically compressed when written. For example, a file called

problem.mps.gz

will be considered as a GZIP compressed MPS file.

16.1 The LP File Format

MOSEK supports the LP file format with some extensions. The LP format is not a completely well-defined standard and hence different optimization packages may interpret the same LP file in slightly different ways. **MOSEK** tries to emulate as closely as possible CPLEX's behavior, but tries to stay backward compatible.

The LP file format can specify problems of the form

$$\begin{array}{ll} \text{minimize/maximize} & c^T x + \frac{1}{2} q^o(x) \\ \text{subject to} & l^c \leq Ax + \frac{1}{2} q(x) \leq u^c, \\ & l^x \leq x \leq u^x, \\ & x_{\mathcal{J}} \text{ integer,} \end{array}$$

where

- $x \in \mathbb{R}^n$ is the vector of decision variables.
- $c \in \mathbb{R}^n$ is the linear term in the objective.
- $q^o : \mathbb{R}^n \rightarrow \mathbb{R}$ is the quadratic term in the objective where

$$q^o(x) = x^T Q^o x$$

and it is assumed that

$$Q^o = (Q^o)^T.$$

- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.
- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.
- $q : \mathbb{R}^n \rightarrow \mathbb{R}$ is a vector of quadratic functions. Hence,

$$q_i(x) = x^T Q^i x$$

where it is assumed that

$$Q^i = (Q^i)^T.$$

- $\mathcal{J} \subseteq \{1, 2, \dots, n\}$ is an index set of the integer constrained variables.

16.1.1 File Sections

An LP formatted file contains a number of sections specifying the objective, constraints, variable bounds, and variable types. The section keywords may be any mix of upper and lower case letters.

Objective Function

The first section beginning with one of the keywords

```
max
maximum
maximize
min
minimum
minimize
```

defines the objective sense and the objective function, i.e.

$$c^T x + \frac{1}{2} x^T Q^o x.$$

The objective may be given a name by writing

```
myname:
```

before the expressions. If no name is given, then the objective is named **obj**.

The objective function contains linear and quadratic terms. The linear terms are written as

```
4 x1 + x2 - 0.1 x3
```

and so forth. The quadratic terms are written in square brackets (`[]/2`) and are either squared or multiplied as in the examples

```
x1^2
```

and

```
x1 * x2
```

There may be zero or more pairs of brackets containing quadratic expressions.

An example of an objective section is

```
minimize
myobj: 4 x1 + x2 - 0.1 x3 + [ x1^2 + 2.1 x1 * x2 ]/2
```

Please note that the quadratic expressions are multiplied with $\frac{1}{2}$, so that the above expression means

$$\text{minimize } 4x_1 + x_2 - 0.1 \cdot x_3 + \frac{1}{2}(x_1^2 + 2.1 \cdot x_1 \cdot x_2)$$

If the same variable occurs more than once in the linear part, the coefficients are added, so that `4 x1 + 2 x1` is equivalent to `6 x1`. In the quadratic expressions `x1 * x2` is equivalent to `x2 * x1` and, as in the linear part, if the same variables multiplied or squared occur several times their coefficients are added.

Constraints

The second section beginning with one of the keywords

```
subj to
subject to
s.t.
st
```

defines the linear constraint matrix A and the quadratic matrices Q^i .

A constraint contains a name (optional), expressions adhering to the same rules as in the objective and a bound:

```
subject to
con1: x1 + x2 + [ x3^2 ]/2 <= 5.1
```

The bound type (here `<=`) may be any of `<`, `<=`, `=`, `>`, `>=` (`<` and `<=` mean the same), and the bound may be any number.

In the standard LP format it is not possible to define more than one bound per line, but **MOSEK** supports defining ranged constraints by using double-colon (`::`) instead of a single-colon (`:`) after the constraint name, i.e.

$$-5 \leq x_1 + x_2 \leq 5 \tag{16.1}$$

may be written as

```
con:: -5 < x_1 + x_2 < 5
```

By default **MOSEK** writes ranged constraints this way.

If the files must adhere to the LP standard, ranged constraints must either be split into upper bounded and lower bounded constraints or be written as an equality with a slack variable. For example the expression (16.1) may be written as

$$x_1 + x_2 - sl_1 = 0, \quad -5 \leq sl_1 \leq 5.$$

Bounds

Bounds on the variables can be specified in the bound section beginning with one of the keywords

```
bound
bounds
```

The bounds section is optional but should, if present, follow the **subject to** section. All variables listed in the bounds section must occur in either the objective or a constraint.

The default lower and upper bounds are 0 and $+\infty$. A variable may be declared free with the keyword **free**, which means that the lower bound is $-\infty$ and the upper bound is $+\infty$. Furthermore it may be assigned a finite lower and upper bound. The bound definitions for a given variable may be written in one or two lines, and bounds can be any number or $\pm\infty$ (written as **+inf/-inf/+infinity/-infinity**) as in the example

```
bounds
x1 free
x2 <= 5
0.1 <= x2
x3 = 42
2 <= x4 < +inf
```

Variable Types

The final two sections are optional and must begin with one of the keywords

```
bin
binaries
binary
```

and

```
gen
general
```

Under **general** all integer variables are listed, and under **binary** all binary (integer variables with bounds 0 and 1) are listed:

```
general
x1 x2
binary
x3 x4
```

Again, all variables listed in the binary or general sections must occur in either the objective or a constraint.

Terminating Section

Finally, an LP formatted file must be terminated with the keyword

```
end
```


16.1.2 LP File Examples

Linear example `lo1.lp`

```
\ File: lo1.lp
maximize
obj: 3 x1 + x2 + 5 x3 + x4
subject to
c1: 3 x1 + x2 + 2 x3 = 30
c2: 2 x1 + x2 + 3 x3 + x4 >= 15
c3: 2 x2 + 3 x4 <= 25
bounds
0 <= x1 <= +infinity
0 <= x2 <= 10
0 <= x3 <= +infinity
0 <= x4 <= +infinity
end
```

Mixed integer example `mil01.lp`

```
maximize
obj: x1 + 6.4e-01 x2
subject to
c1: 5e+01 x1 + 3.1e+01 x2 <= 2.5e+02
c2: 3e+00 x1 - 2e+00 x2 >= -4e+00
bounds
0 <= x1 <= +infinity
0 <= x2 <= +infinity
general
x1 x2
end
```

16.1.3 LP Format peculiarities

Comments

Anything on a line after a `\` is ignored and is treated as a comment.

Names

A name for an objective, a constraint or a variable may contain the letters `a-z`, `A-Z`, the digits `0-9` and the characters

```
!"#$%&()/,.;?@_`'|~
```

The first character in a name must not be a number, a period or the letter `e` or `E`. Keywords must not be used as names.

MOSEK accepts any character as valid for names, except `\0`. A name that is not allowed in LP file will be changed and a warning will be issued.

The algorithm for making names LP valid works as follows: The name is interpreted as an `utf-8` string. For a Unicode character `c`:

- If `c==_` (underscore), the output is `__` (two underscores).
- If `c` is a valid LP name character, the output is just `c`.
- If `c` is another character in the ASCII range, the output is `_XX`, where `XX` is the hexadecimal code for the character.
- If `c` is a character in the range `127-65535`, the output is `_uXXXX`, where `XXXX` is the hexadecimal code for the character.

- If `c` is a character above 65535, the output is `_XXXXXXXX`, where `XXXXXXXX` is the hexadecimal code for the character.

Invalid `utf-8` substrings are escaped as `_XX'`, and if a name starts with a period, `e` or `E`, that character is escaped as `_XX`.

Variable Bounds

Specifying several upper or lower bounds on one variable is possible but **MOSEK** uses only the tightest bounds. If a variable is fixed (with `=`), then it is considered the tightest bound.

MOSEK Extensions to the LP Format

Some optimization software packages employ a more strict definition of the LP format than the one used by **MOSEK**. The limitations imposed by the strict LP format are the following:

- Quadratic terms in the constraints are not allowed.
- Names can be only 16 characters long.
- Lines must not exceed 255 characters in length.

To get around some of the inconveniences converting from other problem formats, **MOSEK** allows lines to contain 1024 characters and names may have any length (shorter than the 1024 characters).

If an LP formatted file created by **MOSEK** should satisfy the strict definition, then the parameter `MSK_IPAR_WRITE_LP_STRICT_FORMAT` should be set; note, however, that some problems cannot be written correctly as a strict LP formatted file. For instance, all names are truncated to 16 characters and hence they may lose their uniqueness and change the problem.

Internally in **MOSEK** names may contain any (printable) character, many of which cannot be used in LP names. Setting the parameters `MSK_IPAR_READ_LP_QUOTED_NAMES` and `MSK_IPAR_WRITE_LP_QUOTED_NAMES` allows **MOSEK** to use quoted names. The first parameter tells **MOSEK** to remove quotes from quoted names e.g. `"x1"`, when reading LP formatted files. The second parameter tells **MOSEK** to put quotes around any semi-illegal name (names beginning with a number or a period) and fully illegal name (containing illegal characters). As double quote is a legal character in the LP format, quoting semi-illegal names makes them legal in the pure LP format as long as they are still shorter than 16 characters. Fully illegal names are still illegal in a pure LP file.

The strict LP format

The LP format is not a formal standard and different vendors have slightly different interpretations of the LP format. To make **MOSEK**'s definition of the LP format more compatible with the definitions of other vendors set the parameter `MSK_IPAR_WRITE_LP_STRICT_FORMAT` to `MSK_ON`.

This setting may lead to truncation of some names and hence to an invalid LP file. The simple solution to this problem is to set the parameter `MSK_IPAR_WRITE_GENERIC_NAMES` to `MSK_ON` which will cause all names to be renamed systematically in the output file.

Formatting of an LP File

A few parameters control the visual formatting of LP files written by **MOSEK** in order to make it easier to read the files. These parameters are

- `MSK_IPAR_WRITE_LP_LINE_WIDTH` sets the maximum number of characters on a single line. The default value is 80 corresponding roughly to the width of a standard text document.
- `MSK_IPAR_WRITE_LP_TERMS_PER_LINE` sets the maximum number of terms per line; a term means a sign, a coefficient, and a name (for example `+ 42 elephants`). The default value is 0, meaning that there is no maximum.

Unnamed Constraints

Reading and writing an LP file with **MOSEK** may change it superficially. If an LP file contains unnamed constraints or objective these are given their generic names when the file is read (however unnamed constraints in **MOSEK** are written without names).

16.2 The MPS File Format

MOSEK supports the standard MPS format with some extensions. For a detailed description of the MPS format see the book by Nazareth [Naz87].

16.2.1 MPS File Structure

The version of the MPS format supported by **MOSEK** allows specification of an optimization problem of the form

$$\begin{aligned} & \text{maximize/minimize} && c^T x + q_0(x) \\ & l^c \leq && Ax + q(x) \leq u^c, \\ & l^x \leq && x \leq u^x, \\ & && x \in \mathcal{K}, \\ & && x_{\mathcal{J}} \text{ integer}, \end{aligned} \tag{16.2}$$

where

- $x \in \mathbb{R}^n$ is the vector of decision variables.
- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.
- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.
- $q : \mathbb{R}^n \rightarrow \mathbb{R}$ is a vector of quadratic functions. Hence,

$$q_i(x) = \frac{1}{2} x^T Q^i x$$

where it is assumed that $Q^i = (Q^i)^T$. Please note the explicit $\frac{1}{2}$ in the quadratic term and that Q^i is required to be symmetric. The same applies to q_0 .

- \mathcal{K} is a convex cone.
- $\mathcal{J} \subseteq \{1, 2, \dots, n\}$ is an index set of the integer-constrained variables.
- c is the vector of objective coefficients.

An MPS file with one row and one column can be illustrated like this:

```
*          1          2          3          4          5          6
*23456789012345678901234567890123456789012345678901234567890
NAME          [name]
OBJSENSE
    [objsense]
OBJNAME          [objname]
ROWS
    ?  [cname1]
COLUMNS
    [vname1]  [cname1]  [value1]          [cname2]  [value2]
RHS
    [name]    [cname1]  [value1]          [cname2]  [value2]
RANGES
    [name]    [cname1]  [value1]          [cname2]  [value2]
QSECTION
    [vname1]  [vname2]  [value1]          [vname3]  [value2]
QMATRIX
    [vname1]  [vname2]  [value1]
```

(continues on next page)

```

QUADOBJ
  [vname1]  [vname2]  [value1]
QCMATRIX   [cname1]
  [vname1]  [vname2]  [value1]
BOUNDS
  ?? [name]  [vname1]  [value1]
CSECTION   [kname1]  [value1]      [ktype]
  [vname1]
ENDATA

```

Here the names in capitals are keywords of the MPS format and names in brackets are custom defined names or values. A couple of notes on the structure:

- Fields: All items surrounded by brackets appear in *fields*. The fields named “valueN” are numerical values. Hence, they must have the format

```
[+|-]XXXXXXX.XXXXXX[e|E][+|-]XXX]
```

where

```
X = [0|1|2|3|4|5|6|7|8|9].
```

- Sections: The MPS file consists of several sections where the names in capitals indicate the beginning of a new section. For example, COLUMNS denotes the beginning of the columns section.
- Comments: Lines starting with an * are comment lines and are ignored by **MOSEK**.
- Keys: The question marks represent keys to be specified later.
- Extensions: The sections QSECTION and CSECTION are specific **MOSEK** extensions of the MPS format. The sections QMATRIX, QUADOBJ and QCMATRIX are included for sake of compatibility with other vendors extensions to the MPS format.
- The standard MPS format is a fixed format, i.e. everything in the MPS file must be within certain fixed positions. **MOSEK** also supports a *free format*. See [Sec. 16.2.5](#) for details.

Linear example lo1.mps

A concrete example of a MPS file is presented below:

```

* File: lo1.mps
NAME          lo1
OBJSENSE
  MAX
ROWS
  N  obj
  E  c1
  G  c2
  L  c3
COLUMNS
  x1      obj      3
  x1      c1       3
  x1      c2       2
  x2      obj      1
  x2      c1       1
  x2      c2       1
  x2      c3       2
  x3      obj      5
  x3      c1       2
  x3      c2       3
  x4      obj      1
  x4      c2       1

```

(continues on next page)

(continued from previous page)

x4	c3	3
RHS		
rhs	c1	30
rhs	c2	15
rhs	c3	25
RANGES		
BOUNDS		
UP bound	x2	10
ENDATA		

Subsequently each individual section in the MPS format is discussed.

NAME (optional)

In this section a name ([name]) is assigned to the problem.

OBJSENSE (optional)

This is an optional section that can be used to specify the sense of the objective function. The **OBJSENSE** section contains one line at most which can be one of the following:

```
MIN
MINIMIZE
MAX
MAXIMIZE
```

It should be obvious what the implication is of each of these four lines.

OBJNAME (optional)

This is an optional section that can be used to specify the name of the row that is used as objective function. **objname** should be a valid row name.

ROWS

A record in the **ROWS** section has the form

```
? [cname1]
```

where the requirements for the fields are as follows:

Field	Starting Position	Max Width	required	Description
?	2	1	Yes	Constraint key
[cname1]	5	8	Yes	Constraint name

Hence, in this section each constraint is assigned a unique name denoted by [cname1]. Please note that [cname1] starts in position 5 and the field can be at most 8 characters wide. An initial key ? must be present to specify the type of the constraint. The key can have values E, G, L, or N with the following interpretation:

Constraint type	l_i^c	u_i^c
E (equal)	finite	$= l_i^c$
G (greater)	finite	∞
L (lower)	$-\infty$	finite
N (none)	$-\infty$	∞

In the MPS format the objective vector is not specified explicitly, but one of the constraints having the key N will be used as the objective vector c . In general, if multiple N type constraints are specified, then the first will be used as the objective vector c , unless something else was specified in the section **OBJNAME**.

COLUMNS

In this section the elements of A are specified using one or more records having the form:

[vname1]	[cname1]	[value1]	[cname2]	[value2]
----------	----------	----------	----------	----------

where the requirements for each field are as follows:

Field	Starting Position	Max Width	required	Description
[vname1]	5	8	Yes	Variable name
[cname1]	15	8	Yes	Constraint name
[value1]	25	12	Yes	Numerical value
[cname2]	40	8	No	Constraint name
[value2]	50	12	No	Numerical value

Hence, a record specifies one or two elements a_{ij} of A using the principle that [vname1] and [cname1] determines j and i respectively. Please note that [cname1] must be a constraint name specified in the ROWS section. Finally, [value1] denotes the numerical value of a_{ij} . Another optional element is specified by [cname2], and [value2] for the variable specified by [vname1]. Some important comments are:

- All elements belonging to one variable must be grouped together.
- Zero elements of A should not be specified.
- At least one element for each variable should be specified.

RHS (optional)

A record in this section has the format

[name]	[cname1]	[value1]	[cname2]	[value2]
--------	----------	----------	----------	----------

where the requirements for each field are as follows:

Field	Starting Position	Max Width	required	Description
[name]	5	8	Yes	Name of the RHS vector
[cname1]	15	8	Yes	Constraint name
[value1]	25	12	Yes	Numerical value
[cname2]	40	8	No	Constraint name
[value2]	50	12	No	Numerical value

The interpretation of a record is that [name] is the name of the RHS vector to be specified. In general, several vectors can be specified. [cname1] denotes a constraint name previously specified in the ROWS section. Now, assume that this name has been assigned to the i -th constraint and v_1 denotes the value specified by [value1], then the interpretation of v_1 is:

Constraint	l_i^c	u_i^c
E	v_1	v_1
G	v_1	
L		v_1
N		

An optional second element is specified by [cname2] and [value2] and is interpreted in the same way. Please note that it is not necessary to specify zero elements, because elements are assumed to be zero.

RANGES (optional)

A record in this section has the form

[name]	[cname1]	[value1]	[cname2]	[value2]
--------	----------	----------	----------	----------

where the requirements for each fields are as follows:

Field	Starting Position	Max Width	required	Description
[name]	5	8	Yes	Name of the RANGE vector
[cname1]	15	8	Yes	Constraint name
[value1]	25	12	Yes	Numerical value
[cname2]	40	8	No	Constraint name
[value2]	50	12	No	Numerical value

The records in this section are used to modify the bound vectors for the constraints, i.e. the values in l^c and u^c . A record has the following interpretation: [name] is the name of the RANGE vector and [cname1] is a valid constraint name. Assume that [cname1] is assigned to the i -th constraint and let v_1 be the value specified by [value1], then a record has the interpretation:

Constraint type	Sign of v_1	l_i^c	u_i^c
E	—	$u_i^c + v_1$	
E	+		$l_i^c + v_1$
G	— or +		$l_i^c + v_1 $
L	— or +	$u_i^c - v_1 $	
N			

Another constraint bound can optionally be modified using [cname2] and [value2] the same way.

QSECTION (optional)

Within the QSECTION the label [cname1] must be a constraint name previously specified in the ROWS section. The label [cname1] denotes the constraint to which the quadratic terms belong. A record in the QSECTION has the form

[vname1]	[vname2]	[value1]	[vname3]	[value2]
----------	----------	----------	----------	----------

where the requirements for each field are:

Field	Starting Position	Max Width	required	Description
[vname1]	5	8	Yes	Variable name
[vname2]	15	8	Yes	Variable name
[value1]	25	12	Yes	Numerical value
[vname3]	40	8	No	Variable name
[value2]	50	12	No	Numerical value

A record specifies one or two elements in the lower triangular part of the Q^i matrix where [cname1] specifies the i . Hence, if the names [vname1] and [vname2] have been assigned to the k -th and j -th variable, then Q_{kj}^i is assigned the value given by [value1]. An optional second element is specified in the same way by the fields [vname1], [vname3], and [value2].

The example

$$\begin{aligned}
 &\text{minimize} && -x_2 + \frac{1}{2}(2x_1^2 - 2x_1x_3 + 0.2x_2^2 + 2x_3^2) \\
 &\text{subject to} && x_1 + x_2 + x_3 \geq 1, \\
 &&& x \geq 0
 \end{aligned}$$

has the following MPS file representation

* File: qo1.mps		
NAME	qo1	
ROWS		
N obj		
G c1		
COLUMNS		
x1	c1	1.0
x2	obj	-1.0
x2	c1	1.0

(continues on next page)

(continued from previous page)

x3	c1	1.0
RHS		
rhs	c1	1.0
QSECTION	obj	
x1	x1	2.0
x1	x3	-1.0
x2	x2	0.2
x3	x3	2.0
ENDATA		

Regarding the QSECTIONS please note that:

- Only one QSECTION is allowed for each constraint.
- The QSECTIONS can appear in an arbitrary order after the COLUMNS section.
- All variable names occurring in the QSECTION must already be specified in the COLUMNS section.
- All entries specified in a QSECTION are assumed to belong to the lower triangular part of the quadratic term of Q .

QMATRIX/QUADOBJ (optional)

The QMATRIX and QUADOBJ sections allow to define the quadratic term of the objective function. They differ in how the quadratic term of the objective function is stored:

- QMATRIX stores all the nonzeros coefficients, without taking advantage of the symmetry of the Q matrix.
- QUADOBJ stores the upper diagonal nonzero elements of the Q matrix.

A record in both sections has the form:

[vname1]	[vname2]	[value1]
----------	----------	----------

where the requirements for each field are:

Field	Starting Position	Max Width	required	Description
[vname1]	5	8	Yes	Variable name
[vname2]	15	8	Yes	Variable name
[value1]	25	12	Yes	Numerical value

A record specifies one elements of the Q matrix in the objective function. Hence, if the names [vname1] and [vname2] have been assigned to the k -th and j -th variable, then Q_{kj} is assigned the value given by [value1]. Note that a line must appear for each off-diagonal coefficient if using a QMATRIX section, while only one entry is required in a QUADOBJ section. The quadratic part of the objective function will be evaluated as $1/2x^T Qx$.

The example

$$\begin{aligned}
 &\text{minimize} && -x_2 + \frac{1}{2}(2x_1^2 - 2x_1x_3 + 0.2x_2^2 + 2x_3^2) \\
 &\text{subject to} && x_1 + x_2 + x_3 \geq 1, \\
 &&& x \geq 0
 \end{aligned}$$

has the following MPS file representation using QMATRIX

* File: qo1_matrix.mps			
NAME	qo1_qmatrix		
ROWS			
N	obj		
G	c1		
COLUMNS			
x1	c1	1.0	
x2	obj	-1.0	

(continues on next page)

(continued from previous page)

	x2	c1	1.0
	x3	c1	1.0
RHS			
	rhs	c1	1.0
QMATRIX			
	x1	x1	2.0
	x1	x3	-1.0
	x3	x1	-1.0
	x2	x2	0.2
	x3	x3	2.0
ENDATA			

or the following using QUADOBJ

* File: qo1_quadobj.mps			
NAME	qo1_quadobj		
ROWS			
	N	obj	
	G	c1	
COLUMNS			
	x1	c1	1.0
	x2	obj	-1.0
	x2	c1	1.0
	x3	c1	1.0
RHS			
	rhs	c1	1.0
QUADOBJ			
	x1	x1	2.0
	x1	x3	-1.0
	x2	x2	0.2
	x3	x3	2.0
ENDATA			

Please also note that:

- A QMATRIX/QUADOBJ section can appear in an arbitrary order after the COLUMNS section.
- All variable names occurring in the QMATRIX/QUADOBJ section must already be specified in the COLUMNS section.

QCMATRIX (optional)

A QCMATRIX section allows to specify the quadratic part of a given constraint. Within the QCMATRIX the label [cname1] must be a constraint name previously specified in the ROWS section. The label [cname1] denotes the constraint to which the quadratic term belongs. A record in the QSECTION has the form

[vname1]	[vname2]	[value1]
----------	----------	----------

where the requirements for each field are:

Field	Starting Position	Max Width	required	Description
[vname1]	5	8	Yes	Variable name
[vname2]	15	8	Yes	Variable name
[value1]	25	12	Yes	Numerical value

A record specifies an entry of the Q^i matrix where [cname1] specifies the i . Hence, if the names [vname1] and [vname2] have been assigned to the k -th and j -th variable, then Q_{kj}^i is assigned the value given by [value1]. Moreover, the quadratic term is represented as $1/2x^T Qx$.

The example

$$\begin{aligned}
&\text{minimize} && x_2 \\
&\text{subject to} && x_1 + x_2 + x_3 \geq 1, \\
&&& \frac{1}{2}(-2x_1x_3 + 0.2x_2^2 + 2x_3^2) \leq 10, \\
&&& x \geq 0
\end{aligned}$$

has the following MPS file representation

```
* File: qo1.mps
NAME          qo1
ROWS
  N  obj
  G  c1
  L  q1
COLUMNS
  x1      c1      1.0
  x2      obj     -1.0
  x2      c1      1.0
  x3      c1      1.0
RHS
  rhs     c1      1.0
  rhs     q1     10.0
QCMATRIX  q1
  x1      x1      2.0
  x1      x3     -1.0
  x3      x1     -1.0
  x2      x2      0.2
  x3      x3      2.0
ENDATA
```

Regarding the QCMATRIXs please note that:

- Only one QCMATRIX is allowed for each constraint.
- The QCMATRIXs can appear in an arbitrary order after the COLUMNS section.
- All variable names occurring in the QSECTION must already be specified in the COLUMNS section.
- QCMATRIX does not exploit the symmetry of Q : an off-diagonal entry (i, j) should appear twice.

BOUNDS (optional)

In the BOUNDS section changes to the default bounds vectors l^x and u^x are specified. The default bounds vectors are $l^x = 0$ and $u^x = \infty$. Moreover, it is possible to specify several sets of bound vectors. A record in this section has the form

```
?? [name]      [vname1]      [value1]
```

where the requirements for each field are:

Field	Starting Position	Max Width	Required	Description
??	2	2	Yes	Bound key
[name]	5	8	Yes	Name of the BOUNDS vector
[vname1]	15	8	Yes	Variable name
[value1]	25	12	No	Numerical value

Hence, a record in the BOUNDS section has the following interpretation: [name] is the name of the bound vector and [vname1] is the name of the variable for which the bounds are modified by the record. ?? and [value1] are used to modify the bound vectors according to the following table:

??	l_j^x	u_j^x	Made integer (added to \mathcal{J})
FR	$-\infty$	∞	No
FX	v_1	v_1	No
LO	v_1	unchanged	No
MI	$-\infty$	unchanged	No
PL	unchanged	∞	No
UP	unchanged	v_1	No
BV	0	1	Yes
LI	$\lceil v_1 \rceil$	unchanged	Yes
UI	unchanged	$\lfloor v_1 \rfloor$	Yes

Here v_1 is the value specified by `[value1]`.

CSECTION (optional)

The purpose of the CSECTION is to specify the conic constraint

$$x \in \mathcal{K}$$

in (16.2). It is assumed that \mathcal{K} satisfies the following requirements. Let

$$x^t \in \mathbb{R}^{n^t}, \quad t = 1, \dots, k$$

be vectors comprised of parts of the decision variables x so that each decision variable is a member of exactly **one** vector x^t , for example

$$x^1 = \begin{bmatrix} x_1 \\ x_4 \\ x_7 \end{bmatrix} \quad \text{and} \quad x^2 = \begin{bmatrix} x_6 \\ x_5 \\ x_3 \\ x_2 \end{bmatrix}.$$

Next define

$$\mathcal{K} := \{x \in \mathbb{R}^n : x^t \in \mathcal{K}_t, \quad t = 1, \dots, k\}$$

where \mathcal{K}_t must have one of the following forms:

- \mathbb{R} set:

$$\mathcal{K}_t = \mathbb{R}^{n^t}.$$

- Zero cone:

$$\mathcal{K}_t = \{0\} \subseteq \mathbb{R}^{n^t}. \quad (16.3)$$

- Quadratic cone:

$$\mathcal{K}_t = \left\{ x \in \mathbb{R}^{n^t} : x_1 \geq \sqrt{\sum_{j=2}^{n^t} x_j^2} \right\}. \quad (16.4)$$

- Rotated quadratic cone:

$$\mathcal{K}_t = \left\{ x \in \mathbb{R}^{n^t} : 2x_1x_2 \geq \sum_{j=3}^{n^t} x_j^2, \quad x_1, x_2 \geq 0 \right\}. \quad (16.5)$$

- Primal exponential cone:

$$\mathcal{K}_t = \{x \in \mathbb{R}^3 : x_1 \geq x_2 \exp(x_3/x_2), \quad x_1, x_2 \geq 0\}. \quad (16.6)$$

- Primal power cone (with parameter $0 < \alpha < 1$):

$$\mathcal{K}_t = \left\{ x \in \mathbb{R}^{n^t} : x_1^\alpha x_2^{1-\alpha} \geq \sqrt{\sum_{j=3}^{n^t} x_j^2}, \quad x_1, x_2 \geq 0 \right\}. \quad (16.7)$$

- Dual exponential cone:

$$\mathcal{K}_t = \{x \in \mathbb{R}^3 : x_1 \geq -x_3 e^{-1} \exp(x_2/x_3), \quad x_3 \leq 0, x_1 \geq 0\}. \quad (16.8)$$

- Dual power cone (with parameter $0 < \alpha < 1$):

$$\mathcal{K}_t = \left\{ x \in \mathbb{R}^{n^t} : \left(\frac{x_1}{\alpha} \right)^\alpha \left(\frac{x_2}{1-\alpha} \right)^{1-\alpha} \geq \sqrt{\sum_{j=3}^{n^t} x_j^2}, \quad x_1, x_2 \geq 0 \right\}. \quad (16.9)$$

In general, membership in the \mathbb{R} set is not specified. If a variable is not a member of any other cone then it is assumed to be a member of the \mathbb{R} cone.

Next, let us study an example. Assume that the power cone

$$x_4^{1/3} x_5^{2/3} \geq |x_8|$$

and the rotated quadratic cone

$$2x_3x_7 \geq x_1^2 + x_0^2, \quad x_3, x_7 \geq 0,$$

should be specified in the MPS file. One CSECTION is required for each cone and they are specified as follows:

*	1	2	3	4	5	6
*23456789012345678901234567890123456789012345678901234567890						
CSECTION	konea	3e-1		PPOW		
x4						
x5						
x8						
CSECTION	koneb	0.0		RQUAD		
x7						
x3						
x1						
x0						

In general, a CSECTION header has the format

CSECTION	[kname1]	[value1]	[ktype]
----------	----------	----------	---------

where the requirements for each field are as follows:

Field	Starting Position	Max Width	Required	Description
[kname1]	15	8	Yes	Name of the cone
[value1]	25	12	No	Cone parameter
[ktype]	40		Yes	Type of the cone.

The possible cone type keys are:

[ktype]	Members	[value1]	Interpretation.
ZERO	≥ 0	unused	Zero cone (16.3).
QUAD	≥ 1	unused	Quadratic cone (16.4).
RQUAD	≥ 2	unused	Rotated quadratic cone (16.5).
PEXP	3	unused	Primal exponential cone (16.6).
PPOW	≥ 2	α	Primal power cone (16.7).
DEXP	3	unused	Dual exponential cone (16.8).
DPOW	≥ 2	α	Dual power cone (16.9).

A record in the CSECTION has the format

[vname1]

where the requirements for each field are

Field	Starting Position	Max Width	required	Description
[vname1]	5	8	Yes	A valid variable name

A variable must occur in at most one CSECTION.

ENDATA

This keyword denotes the end of the MPS file.

16.2.2 Integer Variables

Using special bound keys in the **BOUNDS** section it is possible to specify that some or all of the variables should be integer-constrained i.e. be members of \mathcal{J} . However, an alternative method is available. This method is available only for backward compatibility and we recommend that it is not used. This method requires that markers are placed in the **COLUMNS** section as in the example:

COLUMNS				
x1	obj	-10.0	c1	0.7
x1	c2	0.5	c3	1.0
x1	c4	0.1		
* Start of integer-constrained variables.				
MARK000	'MARKER'		'INTORG'	
x2	obj	-9.0	c1	1.0
x2	c2	0.8333333333	c3	0.66666667
x2	c4	0.25		
x3	obj	1.0	c6	2.0
MARK001	'MARKER'		'INTEND'	
* End of integer-constrained variables.				

Please note that special marker lines are used to indicate the start and the end of the integer variables. Furthermore be aware of the following

- All variables between the markers are assigned a default lower bound of 0 and a default upper bound of 1. **This may not be what is intended.** If it is not intended, the correct bounds should be defined in the **BOUNDS** section of the MPS formatted file.
- **MOSEK** ignores field 1, i.e. MARK0001 and MARK001, however, other optimization systems require them.
- Field 2, i.e. **MARKER**, must be specified including the single quotes. This implies that no row can be assigned the name **MARKER**.
- Field 3 is ignored and should be left blank.
- Field 4, i.e. **INTORG** and **INTEND**, must be specified.
- It is possible to specify several such integer marker sections within the **COLUMNS** section.

16.2.3 General Limitations

- An MPS file should be an ASCII file.

16.2.4 Interpretation of the MPS Format

Several issues related to the MPS format are not well-defined by the industry standard. However, **MOSEK** uses the following interpretation:

- If a matrix element in the **COLUMNS** section is specified multiple times, then the multiple entries are added together.
- If a matrix element in a **QSECTION** section is specified multiple times, then the multiple entries are added together.

16.2.5 The Free MPS Format

MOSEK supports a free format variation of the MPS format. The free format is similar to the MPS file format but less restrictive, e.g. it allows longer names. However, a name must not contain any blanks.

Moreover, by default a line in the MPS file must not contain more than 1024 characters. By modifying the parameter `MSK_IPAR_READ_MPS_WIDTH` an arbitrary large line width will be accepted.

The free MPS format is default. To change to the strict and other formats use the parameter `MSK_IPAR_READ_MPS_FORMAT`.

16.3 The OPF Format

The *Optimization Problem Format (OPF)* is an alternative to LP and MPS files for specifying optimization problems. It is row-oriented, inspired by the CPLEX LP format.

Apart from containing objective, constraints, bounds etc. it may contain complete or partial solutions, comments and extra information relevant for solving the problem. It is designed to be easily read and modified by hand and to be forward compatible with possible future extensions.

Intended use

The OPF file format is meant to replace several other files:

- The LP file format: Any problem that can be written as an LP file can be written as an OPF file too; furthermore it naturally accommodates ranged constraints and variables as well as arbitrary characters in names, fixed expressions in the objective, empty constraints, and conic constraints.
- Parameter files: It is possible to specify integer, double and string parameters along with the problem (or in a separate OPF file).
- Solution files: It is possible to store a full or a partial solution in an OPF file and later reload it.

16.3.1 The File Format

The format uses tags to structure data. A simple example with the basic sections may look like this:

```
[comment]
This is a comment. You may write almost anything here...
[/comment]

# This is a single-line comment.

[objective min 'myobj']
x + 3 y + x^2 + 3 y^2 + z + 1
[/objective]

[constraints]
[con 'con01'] 4 <= x + y  [/con]
[/constraints]

[bounds]
[b] -10 <= x,y <= 10  [/b]

[cone quad] x,y,z [/cone]
[/bounds]
```

A scope is opened by a tag of the form `[tag]` and closed by a tag of the form `[/tag]`. An opening tag may accept a list of unnamed and named arguments, for examples:

```
[tag value] tag with one unnamed argument [/tag]
[tag arg=value] tag with one named argument [/tag]
```

Unnamed arguments are identified by their order, while named arguments may appear in any order, but never before an unnamed argument. The `value` can be a quoted, single-quoted or double-quoted text string, i.e.

```
[tag 'value']      single-quoted value [/tag]
[tag arg='value']  single-quoted value [/tag]
[tag "value"]      double-quoted value [/tag]
[tag arg="value"]  double-quoted value [/tag]
```

16.3.2 Sections

The recognized tags are

`[comment]`

A comment section. This can contain *almost* any text: Between single quotes (') or double quotes (") any text may appear. Outside quotes the markup characters ([and]) must be prefixed by backslashes. Both single and double quotes may appear alone or inside a pair of quotes if it is prefixed by a backslash.

`[objective]`

The objective function: This accepts one or two parameters, where the first one (in the above example `min`) is either `min` or `max` (regardless of case) and defines the objective sense, and the second one (above `myobj`), if present, is the objective name. The section may contain linear and quadratic expressions.

If several objectives are specified, all but the last are ignored.

`[constraints]`

This does not directly contain any data, but may contain subsections `con` defining a linear constraint.

`[con]`

Defines a single constraint; if an argument is present (`[con NAME]`) this is used as the name of the constraint, otherwise it is given a null-name. The section contains a constraint definition written as linear and quadratic expressions with a lower bound, an upper bound, with both or with an equality. Examples:

```
[constraints]
[con 'con1'] 0 <= x + y      [/con]
[con 'con2'] 0 >= x + y      [/con]
[con 'con3'] 0 <= x + y <= 10 [/con]
[con 'con4']      x + y = 10 [/con]
[/constraints]
```

Constraint names are unique. If a constraint is specified which has the same name as a previously defined constraint, the new constraint replaces the existing one.

`[bounds]`

This does not directly contain any data, but may contain subsections `b` (linear bounds on variables) and `cone` (cones).

`[b]`

Bound definition on one or several variables separated by comma (,). An upper or lower bound on a variable replaces any earlier defined bound on that variable. If only one bound (upper or lower) is given only this bound is replaced. This means that upper and lower bounds can be specified separately. So the OPF bound definition:

```
[b] x,y >= -10 [/b]
[b] x,y <= 10  [/b]
```

results in the bound $-10 \leq x, y \leq 10$.

[cone]

Specifies a cone. A cone is defined as a sequence of variables which belong to a single unique cone. The supported cone types are:

- **quad**: a quadratic cone of n variables x_1, \dots, x_n defines a constraint of the form

$$x_1^2 \geq \sum_{i=2}^n x_i^2, \quad x_1 \geq 0.$$

- **rquad**: a rotated quadratic cone of n variables x_1, \dots, x_n defines a constraint of the form

$$2x_1x_2 \geq \sum_{i=3}^n x_i^2, \quad x_1, x_2 \geq 0.$$

- **pexp**: primal exponential cone of 3 variables x_1, x_2, x_3 defines a constraint of the form

$$x_1 \geq x_2 \exp(x_3/x_2), \quad x_1, x_2 \geq 0.$$

- **ppow** with parameter $0 < \alpha < 1$: primal power cone of n variables x_1, \dots, x_n defines a constraint of the form

$$x_1^\alpha x_2^{1-\alpha} \geq \sqrt{\sum_{j=3}^n x_j^2}, \quad x_1, x_2 \geq 0.$$

- **dexp**: dual exponential cone of 3 variables x_1, x_2, x_3 defines a constraint of the form

$$x_1 \geq -x_3 e^{-1} \exp(x_2/x_3), \quad x_3 \leq 0, x_1 \geq 0.$$

- **dpow** with parameter $0 < \alpha < 1$: dual power cone of n variables x_1, \dots, x_n defines a constraint of the form

$$\left(\frac{x_1}{\alpha}\right)^\alpha \left(\frac{x_2}{1-\alpha}\right)^{1-\alpha} \geq \sqrt{\sum_{j=3}^n x_j^2}, \quad x_1, x_2 \geq 0.$$

- **zero**: zero cone of n variables x_1, \dots, x_n defines a constraint of the form

$$x_1 = \dots = x_n = 0$$

A [bounds]-section example:

```
[bounds]
[b]  0 <= x,y <= 10  [/b] # ranged bound
[b]  10 >= x,y >=  0  [/b] # ranged bound
[b]  0 <= x,y <= inf  [/b] # using inf
[b]      x,y free    [/b] # free variables
# Let (x,y,z,w) belong to the cone K
[cone rquad] x,y,z,w [/cone] # rotated quadratic cone
[cone ppow '3e-01' 'a'] x1, x2, x3 [/cone] # power cone with alpha=1/3 and name 'a'
[/bounds]
```

By default all variables are free.

[variables]

This defines an ordering of variables as they should appear in the problem. This is simply a space-separated list of variable names.

[integer]

This contains a space-separated list of variables and defines the constraint that the listed variables must be integer-valued.

[hints]

This may contain only non-essential data; for example estimates of the number of variables, constraints and non-zeros. Placed before all other sections containing data this may reduce the time spent reading the file.

In the `hints` section, any subsection which is not recognized by **MOSEK** is simply ignored. In this section a hint is defined as follows:

```
[hint ITEM] value [/hint]
```

The hints recognized by **MOSEK** are:

- `numvar` (number of variables),
- `numcon` (number of linear/quadratic constraints),
- `numanz` (number of linear non-zeros in constraints),
- `numqnz` (number of quadratic non-zeros in constraints).

[solutions]

This section can contain a set of full or partial solutions to a problem. Each solution must be specified using a `[solution]`-section, i.e.

```
[solutions]
[solution]...[/solution] #solution 1
[solution]...[/solution] #solution 2
#other solutions....
[solution]...[/solution] #solution n
[/solutions]
```

The syntax of a `[solution]`-section is the following:

```
[solution SOLTYPE status=STATUS]...[/solution]
```

where `SOLTYPE` is one of the strings

- `interior`, a non-basic solution,
- `basic`, a basic solution,
- `integer`, an integer solution,

and `STATUS` is one of the strings

- `UNKNOWN`,
- `OPTIMAL`,
- `INTEGER_OPTIMAL`,
- `PRIM_FEAS`,
- `DUAL_FEAS`,
- `PRIM_AND_DUAL_FEAS`,
- `NEAR_OPTIMAL`,
- `NEAR_PRIM_FEAS`,

- NEAR_DUAL_FEAS,
- NEAR_PRIM_AND_DUAL_FEAS,
- PRIM_INFEAS_CER,
- DUAL_INFEAS_CER,
- NEAR_PRIM_INFEAS_CER,
- NEAR_DUAL_INFEAS_CER,
- NEAR_INTEGER_OPTIMAL.

Most of these values are irrelevant for input solutions; when constructing a solution for simplex hot-start or an initial solution for a mixed integer problem the safe setting is **UNKNOWN**.

A **[solution]**-section contains **[con]** and **[var]** sections. Each **[con]** and **[var]** section defines solution information for a single variable or constraint, specified as list of **KEYWORD/value** pairs, in any order, written as

```
KEYWORD=value
```

Allowed keywords are as follows:

- **sk**. The status of the item, where the **value** is one of the following strings:
 - **LOW**, the item is on its lower bound.
 - **UPR**, the item is on its upper bound.
 - **FIX**, it is a fixed item.
 - **BAS**, the item is in the basis.
 - **SUPBAS**, the item is super basic.
 - **UNK**, the status is unknown.
 - **INF**, the item is outside its bounds (infeasible).
- **lv1** Defines the level of the item.
- **s1** Defines the level of the dual variable associated with its lower bound.
- **su** Defines the level of the dual variable associated with its upper bound.
- **sn** Defines the level of the variable associated with its cone.
- **y** Defines the level of the corresponding dual variable (for constraints only).

A **[var]** section should always contain the items **sk**, **lv1**, **s1** and **su**. Items **s1** and **su** are not required for **integer** solutions.

A **[con]** section should always contain **sk**, **lv1**, **s1**, **su** and **y**.

An example of a solution section

```
[solution basic status=UNKNOWN]
[var x0] sk=LOW    lv1=5.0    [/var]
[var x1] sk=UPR    lv1=10.0   [/var]
[var x2] sk=SUPBAS lv1=2.0    s1=1.5 su=0.0 [/var]

[con c0] sk=LOW    lv1=3.0 y=0.0 [/con]
[con c0] sk=UPR    lv1=0.0 y=5.0 [/con]
[/solution]
```

- **[vendor]** This contains solver/vendor specific data. It accepts one argument, which is a vendor ID – for **MOSEK** the ID is simply **mosek** – and the section contains the subsection **parameters** defining solver parameters. When reading a vendor section, any unknown vendor can be safely ignored. This is described later.

Comments using the **#** may appear anywhere in the file. Between the **#** and the following line-break any text may be written, including markup characters.

16.3.3 Numbers

Numbers, when used for parameter values or coefficients, are written in the usual way by the `printf` function. That is, they may be prefixed by a sign (+ or -) and may contain an integer part, decimal part and an exponent. The decimal point is always `.` (a dot). Some examples are

```
1
1.0
.0
1.
1e10
1e+10
1e-10
```

Some *invalid* examples are

```
e10 # invalid, must contain either integer or decimal part
. # invalid
.e10 # invalid
```

More formally, the following standard regular expression describes numbers as used:

```
[+|-]?([0-9]+|[.][0-9]*|.[0-9]+)([eE][+|-]?[0-9]+)?
```

16.3.4 Names

Variable names, constraint names and objective name may contain arbitrary characters, which in some cases must be enclosed by quotes (single or double) that in turn must be preceded by a backslash. Unquoted names must begin with a letter (`a-z` or `A-Z`) and contain only the following characters: the letters `a-z` and `A-Z`, the digits `0-9`, braces (`{` and `}`) and underscore (`_`).

Some examples of legal names:

```
an_unquoted_name
another_name{123}
'single quoted name'
"double quoted name"
"name with \"quote\" in it"
"name with []s in it"
```

16.3.5 Parameters Section

In the `vendor` section solver parameters are defined inside the `parameters` subsection. Each parameter is written as

```
[p PARAMETER_NAME] value [/p]
```

where `PARAMETER_NAME` is replaced by a **MOSEK** parameter name, usually of the form `MSK_IPAR_...`, `MSK_DPAR_...` or `MSK_SPAR_...`, and the `value` is replaced by the value of that parameter; both integer values and named values may be used. Some simple examples are

```
[vendor mosek]
[parameters]
[p MSK_IPAR_OPF_MAX_TERMS_PER_LINE] 10 [/p]
[p MSK_IPAR_OPF_WRITE_PARAMETERS] MSK_ON [/p]
[p MSK_DPAR_DATA_TOL_BOUND_INF] 1.0e18 [/p]
[/parameters]
[/vendor]
```

16.3.6 Writing OPF Files from MOSEK

To write an OPF file then make sure the file extension is `.opf`.

Then modify the following parameters to define what the file should contain:

<i>MSK_IPAR_OPF_WRITE_SOL_BAS</i>	Include basic solution, if defined.
<i>MSK_IPAR_OPF_WRITE_SOL_ITG</i>	Include integer solution, if defined.
<i>MSK_IPAR_OPF_WRITE_SOL_ITR</i>	Include interior solution, if defined.
<i>MSK_IPAR_OPF_WRITE_SOLUTIONS</i>	Include solutions if they are defined. If this is off, no solutions are included.
<i>MSK_IPAR_OPF_WRITE_HEADER</i>	Include a small header with comments.
<i>MSK_IPAR_OPF_WRITE_PROBLEM</i>	Include the problem itself — objective, constraints and bounds.
<i>MSK_IPAR_OPF_WRITE_PARAMETERS</i>	Include all parameter settings.
<i>MSK_IPAR_OPF_WRITE_HINTS</i>	Include hints about the size of the problem.

16.3.7 Examples

This section contains a set of small examples written in OPF and describing how to formulate linear, quadratic and conic problems.

Linear Example lo1.opf

Consider the example:

$$\begin{aligned}
 &\text{maximize} && 3x_0 &+& 1x_1 &+& 5x_2 &+& 1x_3 \\
 &\text{subject to} && 3x_0 &+& 1x_1 &+& 2x_2 && = 30, \\
 &&& 2x_0 &+& 1x_1 &+& 3x_2 &+& 1x_3 \geq 15, \\
 &&& && 2x_1 && &+& 3x_3 \leq 25,
 \end{aligned}$$

having the bounds

$$\begin{aligned}
 0 &\leq x_0 \leq \infty, \\
 0 &\leq x_1 \leq 10, \\
 0 &\leq x_2 \leq \infty, \\
 0 &\leq x_3 \leq \infty.
 \end{aligned}$$

In the OPF format the example is displayed as shown in [Listing 16.1](#).

Listing 16.1: Example of an OPF file for a linear problem.

```

[comment]
  The lo1 example in OPF format
[/comment]

[hints]
  [hint NUMVAR] 4 [/hint]
  [hint NUMCON] 3 [/hint]
  [hint NUMANZ] 9 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2 x3 x4
[/variables]

[objective maximize 'obj']
  3 x1 + x2 + 5 x3 + x4
[/objective]

[constraints]
  [con 'c1'] 3 x1 +   x2 + 2 x3           = 30 [/con]
  [con 'c2'] 2 x1 +   x2 + 3 x3 +   x4 >= 15 [/con]
  [con 'c3']      2 x2           + 3 x4 <= 25 [/con]
[/constraints]

[bounds]

```

(continues on next page)

```
[b] 0 <= * [/b]
[b] 0 <= x2 <= 10 [/b]
[/bounds]
```

Quadratic Example qo1.opf

An example of a quadratic optimization problem is

$$\begin{aligned} & \text{minimize} && x_1^2 + 0.1x_2^2 + x_3^2 - x_1x_3 - x_2 \\ & \text{subject to} && 1 \leq x_1 + x_2 + x_3, \\ & && x \geq 0. \end{aligned}$$

This can be formulated in `opf` as shown below.

Listing 16.2: Example of an OPF file for a quadratic problem.

```
[comment]
  The qo1 example in OPF format
[/comment]

[hints]
  [hint NUMVAR] 3 [/hint]
  [hint NUMCON] 1 [/hint]
  [hint NUMANZ] 3 [/hint]
  [hint NUMQNZ] 4 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2 x3
[/variables]

[objective minimize 'obj']
  # The quadratic terms are often written with a factor of 1/2 as here,
  # but this is not required.

  - x2 + 0.5 ( 2.0 x1 ^ 2 - 2.0 x3 * x1 + 0.2 x2 ^ 2 + 2.0 x3 ^ 2 )
[/objective]

[constraints]
  [con 'c1'] 1.0 <= x1 + x2 + x3 [/con]
[/constraints]

[bounds]
  [b] 0 <= * [/b]
[/bounds]
```

Conic Quadratic Example cqo1.opf

Consider the example:

$$\begin{aligned} & \text{minimize} && x_3 + x_4 + x_5 \\ & \text{subject to} && x_0 + x_1 + 2x_2 = 1, \\ & && x_0, x_1, x_2 \geq 0, \\ & && x_3 \geq \sqrt{x_0^2 + x_1^2}, \\ & && 2x_4x_5 \geq x_2^2. \end{aligned}$$

Please note that the type of the cones is defined by the parameter to `[cone ...]`; the content of the `cone`-section is the names of variables that belong to the cone. The resulting OPF file is in [Listing 16.3](#).

Listing 16.3: Example of an OPF file for a conic quadratic problem.

```
[comment]
  The cqo1 example in OPF format.
[/comment]

[hints]
  [hint NUMVAR] 6 [/hint]
  [hint NUMCON] 1 [/hint]
  [hint NUMANZ] 3 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2 x3 x4 x5 x6
[/variables]

[objective minimize 'obj']
  x4 + x5 + x6
[/objective]

[constraints]
  [con 'c1'] x1 + x2 + 2e+00 x3 = 1e+00 [/con]
[/constraints]

[bounds]
  # We let all variables default to the positive orthant
  [b] 0 <= * [/b]

  # ...and change those that differ from the default
  [b] x4,x5,x6 free [/b]

  # Define quadratic cone:  $x_4 \geq \sqrt{x_1^2 + x_2^2}$ 
  [cone quad 'k1'] x4, x1, x2 [/cone]

  # Define rotated quadratic cone:  $2 x_5 x_6 \geq x_3^2$ 
  [cone rquad 'k2'] x5, x6, x3 [/cone]
[/bounds]
```

Mixed Integer Example milo1.opf

Consider the mixed integer problem:

$$\begin{aligned} & \text{maximize} && x_0 + 0.64x_1 \\ & \text{subject to} && 50x_0 + 31x_1 \leq 250, \\ & && 3x_0 - 2x_1 \geq -4, \\ & && x_0, x_1 \geq 0 \quad \text{and integer} \end{aligned}$$

This can be implemented in OPF with the file in [Listing 16.4](#).

Listing 16.4: Example of an OPF file for a mixed-integer linear problem.

```
[comment]
  The milo1 example in OPF format
[/comment]

[hints]
  [hint NUMVAR] 2 [/hint]
  [hint NUMCON] 2 [/hint]
  [hint NUMANZ] 4 [/hint]
[/hints]
```

(continues on next page)

```

[variables disallow_new_variables]
  x1 x2
[/variables]

[objective maximize 'obj']
  x1 + 6.4e-1 x2
[/objective]

[constraints]
  [con 'c1'] 5e+1 x1 + 3.1e+1 x2 <= 2.5e+2 [/con]
  [con 'c2'] -4 <= 3 x1 - 2 x2 [/con]
[/constraints]

[bounds]
  [b] 0 <= * [/b]
[/bounds]

[integer]
  x1 x2
[/integer]

```

16.4 The CBF Format

This document constitutes the technical reference manual of the *Conic Benchmark Format* with file extension: `.cbf` or `.CBF`. It unifies linear, second-order cone (also known as conic quadratic) and semidefinite optimization with mixed-integer variables. The format has been designed with benchmark libraries in mind, and therefore focuses on compact and easily parsable representations. The problem structure is separated from the problem data, and the format moreover facilitates benchmarking of hotstart capability through sequences of changes.

16.4.1 How Instances Are Specified

This section defines the spectrum of conic optimization problems that can be formulated in terms of the keywords of the CBF format.

In the CBF format, conic optimization problems are considered in the following form:

$$\begin{aligned}
 & \min / \max && g^{obj} \\
 \text{s.t.} &&& g_i \in \mathcal{K}_i, \quad i \in \mathcal{I}, \\
 &&& G_i \in \mathcal{K}_i, \quad i \in \mathcal{I}^{PSD}, \\
 &&& x_j \in \mathcal{K}_j, \quad j \in \mathcal{J}, \\
 &&& \overline{X}_j \in \mathcal{K}_j, \quad j \in \mathcal{J}^{PSD}.
 \end{aligned} \tag{16.10}$$

- **Variables** are either scalar variables, x_j for $j \in \mathcal{J}$, or variables, \overline{X}_j for $j \in \mathcal{J}^{PSD}$. Scalar variables can also be declared as integer.
- **Constraints** are affine expressions of the variables, either scalar-valued g_i for $i \in \mathcal{I}$, or matrix-valued G_i for $i \in \mathcal{I}^{PSD}$

$$\begin{aligned}
 g_i &= \sum_{j \in \mathcal{J}^{PSD}} \langle F_{ij}, X_j \rangle + \sum_{j \in \mathcal{J}} a_{ij} x_j + b_i, \\
 G_i &= \sum_{j \in \mathcal{J}} x_j H_{ij} + D_i.
 \end{aligned}$$

- The **objective function** is a scalar-valued affine expression of the variables, either to be minimized or maximized. We refer to this expression as g^{obj}

$$g^{obj} = \sum_{j \in \mathcal{J}^{PSD}} \langle F_j^{obj}, X_j \rangle + \sum_{j \in \mathcal{J}} a_j^{obj} x_j + b^{obj}.$$

CBF format can represent the following cones \mathcal{K} :

- **Free domain** - A cone in the linear family defined by

$$\{x \in \mathbb{R}^n\}, \text{ for } n \geq 1.$$

- **Positive orthant** - A cone in the linear family defined by

$$\{x \in \mathbb{R}^n \mid x_j \geq 0 \text{ for } j = 1, \dots, n\}, \text{ for } n \geq 1.$$

- **Negative orthant** - A cone in the linear family defined by

$$\{x \in \mathbb{R}^n \mid x_j \leq 0 \text{ for } j = 1, \dots, n\}, \text{ for } n \geq 1.$$

- **Fixpoint zero** - A cone in the linear family defined by

$$\{x \in \mathbb{R}^n \mid x_j = 0 \text{ for } j = 1, \dots, n\}, \text{ for } n \geq 1.$$

- **Quadratic cone** - A cone in the second-order cone family defined by

$$\left\{ \begin{pmatrix} p \\ x \end{pmatrix} \in \mathbb{R} \times \mathbb{R}^{n-1}, p^2 \geq x^T x, p \geq 0 \right\}, \text{ for } n \geq 2.$$

- **Rotated quadratic cone** - A cone in the second-order cone family defined by

$$\left\{ \begin{pmatrix} p \\ q \\ x \end{pmatrix} \in \mathbb{R} \times \mathbb{R} \times \mathbb{R}^{n-2}, 2pq \geq x^T x, p \geq 0, q \geq 0 \right\}, \text{ for } n \geq 3.$$

16.4.2 The Structure of CBF Files

This section defines how information is written in the CBF format, without being specific about the type of information being communicated.

All information items belong to exactly one of the three groups of information. These information groups, and the order they must appear in, are:

1. File format.
2. Problem structure.
3. Problem data.

The first group, file format, provides information on how to interpret the file. The second group, problem structure, provides the information needed to deduce the type and size of the problem instance. Finally, the third group, problem data, specifies the coefficients and constants of the problem instance.

Information items

The format is composed as a list of information items. The first line of an information item is the **KEYWORD**, revealing the type of information provided. The second line - of some keywords only - is the **HEADER**, typically revealing the size of information that follows. The remaining lines are the **BODY** holding the actual information to be specified.

KEYWORD BODY
KEYWORD HEADER BODY

The **KEYWORD** determines how each line in the **HEADER** and **BODY** is structured. Moreover, the number of lines in the **BODY** follows either from the **KEYWORD**, the **HEADER**, or from another information item required to precede it.

Embedded hotstart-sequences

A sequence of problem instances, based on the same problem structure, is within a single file. This is facilitated via the **CHANGE** within the problem data information group, as a separator between the information items of each instance. The information items following a **CHANGE** keyword are appending to, or changing (e.g., setting coefficients back to their default value of zero), the problem data of the preceding instance.

The sequence is intended for benchmarking of hotstart capability, where the solvers can reuse their internal state and solution (subject to the achieved accuracy) as warmpoint for the succeeding instance. Whenever this feature is unsupported or undesired, the keyword **CHANGE** should be interpreted as the end of file.

File encoding and line width restrictions

The format is based on the US-ASCII printable character set with two extensions as listed below. Note, by definition, that none of these extensions can be misinterpreted as printable US-ASCII characters:

- A line feed marks the end of a line, carriage returns are ignored.
- Comment-lines may contain unicode characters in UTF-8 encoding.

The line width is restricted to 512 bytes, with 3 bytes reserved for the potential carriage return, line feed and null-terminator.

Integers and floating point numbers must follow the ISO C decimal string representation in the standard C locale. The format does not impose restrictions on the magnitude of, or number of significant digits in numeric data, but the use of 64-bit integers and 64-bit IEEE 754 floating point numbers should be sufficient to avoid loss of precision.

Comment-line and whitespace rules

The format allows single-line comments respecting the following rule:

- Lines having first byte equal to '#' (US-ASCII 35) are comments, and should be ignored. Comments are only allowed between information items.

Given that a line is not a comment-line, whitespace characters should be handled according to the following rules:

- Leading and trailing whitespace characters should be ignored.
 - The separator between multiple pieces of information on one line, is either one or more whitespace characters.
- Lines containing only whitespace characters are empty, and should be ignored. Empty lines are only allowed between information items.

16.4.3 Problem Specification

The problem structure

The problem structure defines the objective sense, whether it is minimization and maximization. It also defines the index sets, \mathcal{J} , \mathcal{J}^{PSD} , \mathcal{I} and \mathcal{I}^{PSD} , which are all numbered from zero, $\{0, 1, \dots\}$, and empty until explicitly constructed.

- **Scalar variables** are constructed in vectors restricted to a conic domain, such as $(x_0, x_1) \in \mathbb{R}_+^2$, $(x_2, x_3, x_4) \in \mathcal{Q}^3$, etc. In terms of the Cartesian product, this generalizes to

$$x \in \mathcal{K}_1^{n_1} \times \mathcal{K}_2^{n_2} \times \dots \times \mathcal{K}_k^{n_k}$$

which in the CBF format becomes:

```
VAR
n k
K1 n1
K2 n2
...
Kk nk
```

where $\sum_i n_i = n$ is the total number of scalar variables. The list of supported cones is found in [Table 16.3](#). Integrality of scalar variables can be specified afterwards.

- **PSD variables** are constructed one-by-one. That is, $X_j \succeq \mathbf{0}^{n_j \times n_j}$ for $j \in \mathcal{J}^{PSD}$, constructs a matrix-valued variable of size $n_j \times n_j$ restricted to be symmetric positive semidefinite. In the CBF format, this list of constructions becomes:

```
PSDVAR
N
n1
n2
...
nN
```

where N is the total number of PSD variables.

- **Scalar constraints** are constructed in vectors restricted to a conic domain, such as $(g_0, g_1) \in \mathbb{R}_+^2$, $(g_2, g_3, g_4) \in \mathcal{Q}^3$, etc. In terms of the Cartesian product, this generalizes to

$$g \in \mathcal{K}_1^{m_1} \times \mathcal{K}_2^{m_2} \times \dots \times \mathcal{K}_k^{m_k}$$

which in the CBF format becomes:

```
CON
m k
K1 m1
K2 m2
..
Kk mk
```

where $\sum_i m_i = m$ is the total number of scalar constraints. The list of supported cones is found in [Table 16.3](#).

- **PSD constraints** are constructed one-by-one. That is, $G_i \succeq \mathbf{0}^{m_i \times m_i}$ for $i \in \mathcal{I}^{PSD}$, constructs a matrix-valued affine expressions of size $m_i \times m_i$ restricted to be symmetric positive semidefinite. In the CBF format, this list of constructions becomes

```
PSDCON
M
m1
m2
..
mM
```

where M is the total number of PSD constraints.

With the objective sense, variables (with integer indications) and constraints, the definitions of the many affine expressions follow in problem data.

Problem data

The problem data defines the coefficients and constants of the affine expressions of the problem instance. These are considered zero until explicitly defined, implying that instances with no keywords from this information group are, in fact, valid. Duplicating or conflicting information is a failure to comply with the standard. Consequently, two coefficients written to the same position in a matrix (or to transposed positions in a symmetric matrix) is an error.

The affine expressions of the objective, g^{obj} , of the scalar constraints, g_i , and of the PSD constraints, G_i , are defined separately. The following notation uses the standard trace inner product for matrices, $\langle X, Y \rangle = \sum_{i,j} X_{ij}Y_{ij}$.

- The affine expression of the objective is defined as

$$g^{obj} = \sum_{j \in \mathcal{J}^{PSD}} \langle F_j^{obj}, X_j \rangle + \sum_{j \in \mathcal{J}} a_j^{obj} x_j + b^{obj},$$

in terms of the symmetric matrices, F_j^{obj} , and scalars, a_j^{obj} and b^{obj} .

- The affine expressions of the scalar constraints are defined, for $i \in \mathcal{I}$, as

$$g_i = \sum_{j \in \mathcal{J}^{PSD}} \langle F_{ij}, X_j \rangle + \sum_{j \in \mathcal{J}} a_{ij} x_j + b_i,$$

in terms of the symmetric matrices, F_{ij} , and scalars, a_{ij} and b_i .

- The affine expressions of the PSD constraints are defined, for $i \in \mathcal{I}^{PSD}$, as

$$G_i = \sum_{j \in \mathcal{J}} x_j H_{ij} + D_i,$$

in terms of the symmetric matrices, H_{ij} and D_i .

List of cones

The format uses an explicit syntax for symmetric positive semidefinite cones as shown above. For scalar variables and constraints, constructed in vectors, the supported conic domains and their minimum sizes are given as follows.

Table 16.3: Cones available in the CBF format

Name	CBF keyword	Cone family
Free domain	F	linear
Positive orthant	L+	linear
Negative orthant	L-	linear
Fixpoint zero	L=	linear
Quadratic cone	Q	second-order
Rotated quadratic cone	QR	second-order

16.4.4 File Format Keywords

VER

Description: The version of the Conic Benchmark Format used to write the file.

HEADER: None

BODY: One line formatted as:

INT

This is the version number.
Must appear exactly once in a file, as the first keyword.

OBJSENSE

Description: Define the objective sense.

HEADER: None

BODY: One line formatted as:

STR

having MIN indicates minimize, and MAX indicates maximize. Capital letters are required.
Must appear exactly once in a file.

PSDVAR

Description: Construct the PSD variables.

HEADER: One line formatted as:

INT

This is the number of PSD variables in the problem.
BODY: A list of lines formatted as:

INT

This indicates the number of rows (equal to the number of columns) in the matrix-valued PSD variable. The number of lines should match the number stated in the header.

VAR

Description: Construct the scalar variables.

HEADER: One line formatted as:

INT INT

This is the number of scalar variables, followed by the number of conic domains they are restricted to.

BODY: A list of lines formatted as:

STR INT

This indicates the cone name (see [Table 16.3](#)), and the number of scalar variables restricted to this cone. These numbers should add up to the number of scalar variables stated first in the header. The number of lines should match the second number stated in the header.

INT

Description: Declare integer requirements on a selected subset of scalar variables.

HEADER: one line formatted as:

INT

This is the number of integer scalar variables in the problem.
BODY: a list of lines formatted as:

INT

This indicates the scalar variable index $j \in \mathcal{J}$. The number of lines should match the number stated in the header.

Can only be used after the keyword VAR.

PSDCON

Description: Construct the PSD constraints.

HEADER: One line formatted as:

INT

This is the number of PSD constraints in the problem.

BODY: A list of lines formatted as:

INT

This indicates the number of rows (equal to the number of columns) in the matrix-valued affine expression of the PSD constraint. The number of lines should match the number stated in the header.

Can only be used after these keywords: PSDVAR, VAR.

CON

Description: Construct the scalar constraints.

HEADER: One line formatted as:

INT INT

This is the number of scalar constraints, followed by the number of conic domains they restrict to.

BODY: A list of lines formatted as:

STR INT

This indicates the cone name (see Table 16.3), and the number of affine expressions restricted to this cone. These numbers should add up to the number of scalar constraints stated first in the header. The number of lines should match the second number stated in the header.

Can only be used after these keywords: PSDVAR, VAR

OBJFCOORD

Description: Input sparse coordinates (quadruplets) to define the symmetric matrices F_j^{obj} , as used in the objective.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT INT INT REAL

This indicates the PSD variable index $j \in \mathcal{J}^{PSD}$, the row index, the column index and the coefficient value. The number of lines should match the number stated in the header.

OBJACOORD

Description: Input sparse coordinates (pairs) to define the scalars, a_j^{obj} , as used in the objective.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT REAL

This indicates the scalar variable index $j \in \mathcal{J}$ and the coefficient value. The number of lines should match the number stated in the header.

OBJCOORD

Description: Input the scalar, b^{obj} , as used in the objective.

HEADER: None.

BODY: One line formatted as:

REAL

This indicates the coefficient value.

FCOORD

Description: Input sparse coordinates (quintuplets) to define the symmetric matrices, F_{ij} , as used in the scalar constraints.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT INT INT INT REAL

This indicates the scalar constraint index $i \in \mathcal{I}$, the PSD variable index $j \in \mathcal{J}^{PSD}$, the row index, the column index and the coefficient value. The number of lines should match the number stated in the header.

ACCOORD

Description: Input sparse coordinates (triplets) to define the scalars, a_{ij} , as used in the scalar constraints.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT INT REAL

This indicates the scalar constraint index $i \in \mathcal{I}$, the scalar variable index $j \in \mathcal{J}$ and the coefficient value. The number of lines should match the number stated in the header.

BCOORD

Description: Input sparse coordinates (pairs) to define the scalars, b_i , as used in the scalar constraints.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT REAL

This indicates the scalar constraint index $i \in \mathcal{I}$ and the coefficient value. The number of lines should match the number stated in the header.

HCOORD

Description: Input sparse coordinates (quintuplets) to define the symmetric matrices, H_{ij} , as used in the PSD constraints.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as

INT INT INT INT REAL

This indicates the PSD constraint index $i \in \mathcal{I}^{PSD}$, the scalar variable index $j \in \mathcal{J}$, the row index, the column index and the coefficient value. The number of lines should match the number stated in the header.

DCOORD

Description: Input sparse coordinates (quadruplets) to define the symmetric matrices, D_i , as used in the PSD constraints.

HEADER: One line formatted as

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT INT INT REAL

This indicates the PSD constraint index $i \in \mathcal{I}^{PSD}$, the row index, the column index and the coefficient value. The number of lines should match the number stated in the header.

CHANGE

Start of a new instance specification based on changes to the previous. Can be interpreted as the end of file when the hotstart-sequence is unsupported or undesired.

BODY: None

Header: None

16.4.5 CBF Format Examples

Minimal Working Example

The conic optimization problem (16.11), has three variables in a quadratic cone - first one is integer - and an affine expression in domain 0 (equality constraint).

$$\begin{aligned} &\text{minimize} && 5.1 x_0 \\ &\text{subject to} && 6.2 x_1 + 7.3 x_2 - 8.4 \in \{0\} \\ & && x \in \mathcal{Q}^3, x_0 \in \mathbb{Z}. \end{aligned} \tag{16.11}$$

Its formulation in the Conic Benchmark Format begins with the version of the CBF format used, to safeguard against later revisions.

VER
1

Next follows the problem structure, consisting of the objective sense, the number and domain of variables, the indices of integer variables, and the number and domain of scalar-valued affine expressions (i.e., the equality constraint).

OBJSENSE
MIN
VAR
3 1
Q 3
INT
1
0

(continues on next page)

(continued from previous page)

```

CON
1 1
L= 1

```

Finally follows the problem data, consisting of the coefficients of the objective, the coefficients of the constraints, and the constant terms of the constraints. All data is specified on a sparse coordinate form.

```

OBJCOORD
1
0 5.1

ACCOORD
2
0 1 6.2
0 2 7.3

BCCOORD
1
0 -8.4

```

This concludes the example.

Mixing Linear, Second-order and Semidefinite Cones

The conic optimization problem (16.12), has a semidefinite cone, a quadratic cone over unordered subindices, and two equality constraints.

$$\begin{aligned}
 & \text{minimize} && \left\langle \begin{bmatrix} 2 & 1 & 0 \\ 1 & 2 & 1 \\ 0 & 1 & 2 \end{bmatrix}, X_1 \right\rangle + x_1 \\
 & \text{subject to} && \left\langle \begin{bmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 1 \end{bmatrix}, X_1 \right\rangle + x_1 &= 1.0, \\
 & && \left\langle \begin{bmatrix} 1 & 1 & 1 \\ 1 & 1 & 1 \\ 1 & 1 & 1 \end{bmatrix}, X_1 \right\rangle + x_0 + x_2 &= 0.5, \\
 & && x_1 \geq \sqrt{x_0^2 + x_2^2}, \\
 & && X_1 \succeq \mathbf{0}.
 \end{aligned} \tag{16.12}$$

The equality constraints are easily rewritten to the conic form, $(g_0, g_1) \in \{0\}^2$, by moving constants such that the right-hand-side becomes zero. The quadratic cone does not fit under the VAR keyword in this variable permutation. Instead, it takes a scalar constraint $(g_2, g_3, g_4) = (x_1, x_0, x_2) \in \mathcal{Q}^3$, with scalar variables constructed as $(x_0, x_1, x_2) \in \mathbb{R}^3$. Its formulation in the CBF format is reported in the following list

```

# File written using this version of the Conic Benchmark Format:
# | Version 1.
VER
1

# The sense of the objective is:
# | Minimize.
OBJSENSE
MIN

# One PSD variable of this size:
# | Three times three.
PSDVAR
1
3

```

(continues on next page)


```

# Three scalar variables in this one conic domain:
#   | Three are free.
VAR
3 1
F 3

# Five scalar constraints with affine expressions in two conic domains:
#   | Two are fixed to zero.
#   | Three are in conic quadratic domain.
CON
5 2
L= 2
Q 3

# Five coordinates in  $F^{\text{obj}}_j$  coefficients:
#   |  $F^{\text{obj}}[0][0,0] = 2.0$ 
#   |  $F^{\text{obj}}[0][1,0] = 1.0$ 
#   | and more...
OBJFCOORD
5
0 0 0 2.0
0 1 0 1.0
0 1 1 2.0
0 2 1 1.0
0 2 2 2.0

# One coordinate in  $a^{\text{obj}}_j$  coefficients:
#   |  $a^{\text{obj}}[1] = 1.0$ 
OBJACOORD
1
1 1.0

# Nine coordinates in  $F_{ij}$  coefficients:
#   |  $F[0,0][0,0] = 1.0$ 
#   |  $F[0,0][1,1] = 1.0$ 
#   | and more...
FCOORD
9
0 0 0 0 1.0
0 0 1 1 1.0
0 0 2 2 1.0
1 0 0 0 1.0
1 0 1 0 1.0
1 0 2 0 1.0
1 0 1 1 1.0
1 0 2 1 1.0
1 0 2 2 1.0

# Six coordinates in  $a_{ij}$  coefficients:
#   |  $a[0,1] = 1.0$ 
#   |  $a[1,0] = 1.0$ 
#   | and more...
ACOORD
6
0 1 1.0
1 0 1.0
1 2 1.0
2 1 1.0
3 0 1.0
4 2 1.0

```

(continued from previous page)

```
# Two coordinates in b_i coefficients:
#      | b[0] = -1.0
#      | b[1] = -0.5
BCOORD
2
0 -1.0
1 -0.5
```

Mixing Semidefinite Variables and Linear Matrix Inequalities

The standard forms in semidefinite optimization are usually based either on semidefinite variables or linear matrix inequalities. In the CBF format, both forms are supported and can even be mixed as shown in.

$$\begin{aligned} & \text{minimize} && \left\langle \begin{bmatrix} 1 & 0 \\ 0 & 1 \end{bmatrix}, X_1 \right\rangle + x_1 + x_2 + 1 \\ & \text{subject to} && \left\langle \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix}, X_1 \right\rangle - x_1 - x_2 && \geq 0.0, \\ & && x_1 \begin{bmatrix} 0 & 1 \\ 1 & 3 \end{bmatrix} + x_2 \begin{bmatrix} 3 & 1 \\ 1 & 0 \end{bmatrix} - \begin{bmatrix} 1 & 0 \\ 0 & 1 \end{bmatrix} && \succeq \mathbf{0}, \\ & && X_1 \succeq \mathbf{0}. \end{aligned} \tag{16.13}$$

Its formulation in the CBF format is written in what follows

```
# File written using this version of the Conic Benchmark Format:
#      | Version 1.
VER
1

# The sense of the objective is:
#      | Minimize.
OBJSENSE
MIN

# One PSD variable of this size:
#      | Two times two.
PSDVAR
1
2

# Two scalar variables in this one conic domain:
#      | Two are free.
VAR
2 1
F 2

# One PSD constraint of this size:
#      | Two times two.
PSDCON
1
2

# One scalar constraint with an affine expression in this one conic domain:
#      | One is greater than or equal to zero.
CON
1 1
L+ 1

# Two coordinates in F^{obj}_j coefficients:
```

(continues on next page)

```

#      | F^{obj}[0][0,0] = 1.0
#      | F^{obj}[0][1,1] = 1.0
OBJFCOORD
2
0 0 0 1.0
0 1 1 1.0

# Two coordinates in a^{obj}_j coefficients:
#      | a^{obj}[0] = 1.0
#      | a^{obj}[1] = 1.0
OBJACOORD
2
0 1.0
1 1.0

# One coordinate in b^{obj} coefficient:
#      | b^{obj} = 1.0
OBJBCOORD
1.0

# One coordinate in F_ij coefficients:
#      | F[0,0][1,0] = 1.0
FCOORD
1
0 0 1 0 1.0

# Two coordinates in a_ij coefficients:
#      | a[0,0] = -1.0
#      | a[0,1] = -1.0
ACCOORD
2
0 0 -1.0
0 1 -1.0

# Four coordinates in H_ij coefficients:
#      | H[0,0][1,0] = 1.0
#      | H[0,0][1,1] = 3.0
#      | and more...
HCOORD
4
0 0 1 0 1.0
0 0 1 1 3.0
0 1 0 0 3.0
0 1 1 0 1.0

# Two coordinates in D_i coefficients:
#      | D[0][0,0] = -1.0
#      | D[0][1,1] = -1.0
DCCOORD
2
0 0 0 -1.0
0 1 1 -1.0

```

Optimization Over a Sequence of Objectives

The linear optimization problem (16.14), is defined for a sequence of objectives such that hotstarting from one to the next might be advantages.

$$\begin{aligned}
 & \text{maximize}_k && g_k^{obj} \\
 & \text{subject to} && 50x_0 + 31 \leq 250, \\
 & && 3x_0 - 2x_1 \geq -4, \\
 & && x \in \mathbb{R}_+^2,
 \end{aligned} \tag{16.14}$$

given,

1. $g_0^{obj} = x_0 + 0.64x_1$.
2. $g_1^{obj} = 1.11x_0 + 0.76x_1$.
3. $g_2^{obj} = 1.11x_0 + 0.85x_1$.

Its formulation in the CBF format is reported in [Listing 16.5](#).

Listing 16.5: Problem (16.14) in CBF format.

```
# File written using this version of the Conic Benchmark Format:
#   | Version 1.
VER
1

# The sense of the objective is:
#   | Maximize.
OBJSENSE
MAX

# Two scalar variables in this one conic domain:
#   | Two are nonnegative.
VAR
2 1
L+ 2

# Two scalar constraints with affine expressions in these two conic domains:
#   | One is in the nonpositive domain.
#   | One is in the nonnegative domain.
CON
2 2
L- 1
L+ 1

# Two coordinates in a^{obj}_j coefficients:
#   | a^{obj}[0] = 1.0
#   | a^{obj}[1] = 0.64
OBJCOORD
2
0 1.0
1 0.64

# Four coordinates in a_ij coefficients:
#   | a[0,0] = 50.0
#   | a[1,0] = 3.0
#   | and more...
ACCOORD
4
0 0 50.0
1 0 3.0
0 1 31.0
1 1 -2.0

# Two coordinates in b_i coefficients:
#   | b[0] = -250.0
#   | b[1] = 4.0
BCCOORD
2
0 -250.0
1 4.0
```

(continues on next page)

```
# New problem instance defined in terms of changes.
CHANGE

# Two coordinate changes in a^{obj}_j coefficients. Now it is:
#   | a^{obj}[0] = 1.11
#   | a^{obj}[1] = 0.76
OBJCOORD
2
0 1.11
1 0.76

# New problem instance defined in terms of changes.
CHANGE

# One coordinate change in a^{obj}_j coefficients. Now it is:
#   | a^{obj}[0] = 1.11
#   | a^{obj}[1] = 0.85
OBJCOORD
1
1 0.85
```

16.5 The PTF Format

The PTF format is a new human-readable, natural text format. Its features and structure are similar to the *OPF* format, with the difference that the PTF format **does** support semidefinite terms.

16.5.1 The overall format

The format is indentation based, where each section is started by a head line and followed by a section body with deeper indentation than the head line. For example:

```
Header line
  Body line 1
  Body line 1
  Body line 1
```

Section can also be nested:

```
Header line A
  Body line in A
  Header line A.1
    Body line in A.1
    Body line in A.1
  Body line in A
```

The indentation of blank lines is ignored, so a subsection can contain a blank line with no indentation. The character # defines a line comment and anything between the # character and the end of the line is ignored.

In a PTF file, the first section must be a **Task** section. The order of the remaining section is arbitrary, and sections may occur multiple times or not at all.

MOSEK will ignore any top-level section it does not recognize.

Names

In the description of the format we use following definitions for name strings:

```
NAME: PLAIN_NAME | QUOTED_NAME
PLAIN_NAME: [a-zA-Z_] [a-zA-Z0-9_-.!|]
QUOTED_NAME: '"' ( [^'\\r\n] | "\\" ( [\\rn] | "x" [0-9a-fA-F] [0-9a-fA-F] ) ) * '"'
```

Expressions

An expression is a sum of terms. A term is either a linear term (a coefficient and a variable name, where the coefficient can be left out if it is 1.0), or a matrix inner product.

An expression:

```
EXPR: EMPTY | [+ -]? TERM ( [+ -] TERM )*  
TERM: LINEAR_TERM | MATRIX_TERM
```

A linear term

```
LINEAR_TERM: FLOAT? NAME
```

A matrix term

```
MATRIX_TERM: "<" FLOAT? NAME ( [+ -] FLOAT? NAME)* ";" NAME ">"
```

Here the right-hand name is the name of a (semidefinite) matrix variable, and the left-hand side is a sum of symmetric matrixes. The actual matrixes are defined in a separate section.

Expressions can span multiple lines by giving subsequent lines a deeper indentation.

For example following two section are equivalent:

```
# Everything on one line:  
x1 + x2 + x3 + x4  
  
# Split into multiple lines:  
x1  
  + x2  
  + x3  
  + x4
```

16.5.2 Task section

The first section of the file must be a **Task**. The text in this section is not used and may contain comments, or meta-information from the writer or about the content.

Format:

```
Task NAME  
  Anything goes here...
```

NAME is a the task name.

16.5.3 Objective section

The **Objective** section defines the objective name, sense and function. The format:

```
"Objective" NAME?  
( "Minimize" | "Maximize" ) EXPR
```

For example:

```
Objective 'obj'  
  Minimize x1 + 0.2 x2 + < M1 ; X1 >
```

16.5.4 Constraints section

The constraints section defines a series of constraints. A constraint defines a term $A \cdot x + b \in K$. For linear constraints A is just one row, while for conic constraints it can be multiple rows. If a constraint spans multiple rows these can either be written inline separated by semi-colons, or each expression in a separate sub-section.

Simple linear constraints:

```
"Constraints"
NAME? "[" [-+] (FLOAT | "Inf") (";" [-+] (FLOAT | "Inf"))? "]" EXPR
```

If the brackets contain two values, they are used as upper and lower bounds. If they contain one value the constraint is an equality.

For example:

```
Constraints
'c1' [0;10] x1 + x2 + x3
[0] x1 + x2 + x3
```

Constraint blocks put the expression either in a subsection or inline. The cone type (domain) is written in the brackets, and **MOSEK** currently supports following types:

- SOC(N) Second order cone of dimension N
- RSOC(N) Rotated second order cone of dimension N
- PSD(N) Symmetric positive semidefinite cone of dimension N. This contains $N*(N+1)/2$ elements.
- PEXP Primal exponential cone of dimension 3
- DEXP Dual exponential cone of dimension 3
- PPOW(N,P) Primal power cone of dimension N with parameter P
- DPOW(N,P) Dual power cone of dimension N with parameter P
- ZERO(N) The zero-cone of dimension N.

```
"Constraints"
NAME? "[" DOMAIN "]" EXPR_LIST
```

For example:

```
Constraints
'K1' [SOC(3)] x1 + x2 ; x2 + x3 ; x3 + x1
'K2' [RSOC(3)]
    x1 + x2
    x2 + x3
    x3 + x1
```

16.5.5 Variables section

Any variable used in an expression must be defined in a variable section. The variable section defines each variable domain.

```
"Variables"
NAME "[" [-+] (FLOAT | "Inf") (";" [-+] (FLOAT | "Inf"))? "]"
NAME "[" DOMAIN "]" NAMES
```

For example, a linear variable

```
Variables
x1 [0;Inf]
```

As with constraints, members of a conic domain can be listed either inline or in a subsection:

```
Variables
k1 [SOC(3)] x1 ; x2 ; x3
k2 [RSOC(3)]
    x1
    x2
    x3
```

16.5.6 Integer section

This section contains a list of variables that are integral. For example:

```
Integer
  x1 x2 x3
```

16.5.7 SymmetricMatrixes section

This section defines the symmetric matrixes used for matrix coefficients in matrix inner product terms. The section lists named matrixes, each with a size and a number of non-zeros. Only non-zeros in the lower triangular part should be defined.

```
"SymmetricMatrixes"
  NAME "SYMMAT" "(" INT ")" ( "(" INT "," INT "," FLOAT ")" ) *
  ...
```

For example:

```
SymmetricMatrixes
M1 SYMMAT(3) (0,0,1.0) (1,1,2.0) (2,1,0.5)
M2 SYMMAT(3)
  (0,0,1.0)
  (1,1,2.0)
  (2,1,0.5)
```

16.5.8 Solutions section

Each subsection defines a solution. A solution defines for each constraint and for each variable exactly one primal value and either one (for conic domains) or two (for linear domains) dual values. The values follow the same logic as in the **MOSEK C API**. A primal and a dual solution status defines the meaning of the values primal and dual (solution, certificate, unknown, etc.)

The format is this:

```
"Solutions"
  "Solution" WHICHSOL
    "ProblemStatus" PROSTA PROSTA?
    "SolutionStatus" SOLSTA SOLSTA?
    "Objective" FLOAT FLOAT
    "Variables"
      # Linear variable status: level, slx, sux
      NAME "[" STATUS "]" FLOAT (FLOAT FLOAT)?
      # Conic variable status: level, snx
      NAME
        "[" STATUS "]" FLOAT FLOAT?
      ...
    "Constraints"
      # Linear variable status: level, slx, sux
      NAME "[" STATUS "]" FLOAT (FLOAT FLOAT)?
      # Conic variable status: level, snx
      NAME
        "[" STATUS "]" FLOAT FLOAT?
      ...
```

Following values for WHICHSOL are supported:

- **interior** Interior solution, the result of an interior-point solver.
- **basic** Basic solution, as produced by a simplex solver.
- **integer** Integer solution, the solution to a mixed-integer problem. This does not define a dual solution.

Following values for PROSTA are supported:

- **unknown** The problem status is unknown
- **feasible** The problem has been proven feasible
- **infeasible** The problem has been proven infeasible
- **illposed** The problem has been proved to be ill posed
- **infeasible_or_unbounded** The problem is infeasible or unbounded

Following values for **SOLSTA** are supported:

- **unknown** The solution status is unknown
- **feasible** The solution is feasible
- **optimal** The solution is optimal
- **infeas_cert** The solution is a certificate of infeasibility
- **illposed_cert** The solution is a certificate of illposedness

Following values for **STATUS** are supported:

- **unknown** The value is unknown
- **super_basic** The value is super basic
- **at_lower** The value is basic and at its lower bound
- **at_upper** The value is basic and at its upper bound
- **fixed** The value is basic fixed
- **infinite** The value is at infinity

16.6 The Task Format

The Task format is **MOSEK**'s native binary format. It contains a complete image of a **MOSEK** task, i.e.

- Problem data: Linear, conic, semidefinite and quadratic data
- Problem item names: Variable names, constraints names, cone names etc.
- Parameter settings
- Solutions

There are a few things to be aware of:

- Status of a solution read from a file will *always* be unknown.
- Parameter settings in a task file *always override* any parameters set on the command line or in a parameter file.

The format is based on the *TAR* (USTar) file format. This means that the individual pieces of data in a **.task** file can be examined by unpacking it as a *TAR* file. Please note that the inverse may not work: Creating a file using *TAR* will most probably not create a valid **MOSEK** Task file since the order of the entries is important.

16.7 The JSON Format

MOSEK provides the possibility to read/write problems in valid JSON format.

JSON (JavaScript Object Notation) is a lightweight data-interchange format. It is easy for humans to read and write. It is easy for machines to parse and generate. It is based on a subset of the JavaScript Programming Language, Standard ECMA-262 3rd Edition - December 1999. JSON is a text format that is completely language independent but uses conventions that are familiar to programmers of the C-family of languages, including C, C++, C#, Java, JavaScript, Perl, Python, and many others. These properties make JSON an ideal data-interchange language.

The official JSON website <http://www.json.org> provides plenty of information along with the format definition.

MOSEK defines two JSON-like formats:

- *jtask*
- *jsol*

Despite being text-based human-readable formats, *jtask* and *jsol* files will include no indentation and no new-lines, in order to keep the files as compact as possible. We therefore strongly advise to use JSON viewer tools to inspect *jtask* and *jsol* files.

16.7.1 *jtask* format

It stores a problem instance. The *jtask* format contains the same information as a *task format*. Even though a *jtask* file is human-readable, we do not recommend users to create it by hand, but to rely on **MOSEK**.

You can read and write *jtask* files using *MSK_readdata* and *MSK_writedata* specifying the extension *.jtask*.

16.7.2 *jsol* format

It stores a problem solution. The *jsol* format contains all solutions and information items.

You can write a *jsol* file using *MSK_writejsonsol*. You **can not** read a *jsol* file into **MOSEK**.

16.7.3 A *jtask* example

In [Listing 16.6](#) we present a file in the *jtask* format that corresponds to the sample problem from `1o1.1p`. The listing has been formatted for readability.

Listing 16.6: A formatted *jtask* file for the `1o1.1p` example.

```
{
  "$schema": "http://mosek.com/json/schema#",
  "Task/INFO": {
    "taskname": "1o1",
    "numvar": 4,
    "numcon": 3,
    "numcone": 0,
    "numbarvar": 0,
    "numanz": 9,
    "numsymmat": 0,
    "mosekver": [
      8,
      0,
      0,
      9
    ]
  },
  "Task/data": {
    "var": {
      "name": [
```

(continues on next page)

```

        "x1",
        "x2",
        "x3",
        "x4"
    ],
    "bk": [
        "lo",
        "ra",
        "lo",
        "lo"
    ],
    "b1": [
        0.0,
        0.0,
        0.0,
        0.0
    ],
    "bu": [
        1e+30,
        1e+1,
        1e+30,
        1e+30
    ],
    "type": [
        "cont",
        "cont",
        "cont",
        "cont"
    ]
    ],
    "con": {
        "name": [
            "c1",
            "c2",
            "c3"
        ],
        "bk": [
            "fx",
            "lo",
            "up"
        ],
        "b1": [
            3e+1,
            1.5e+1,
            -1e+30
        ],
        "bu": [
            3e+1,
            1e+30,
            2.5e+1
        ]
    ],
    "objective": {
        "sense": "max",
        "name": "obj",
        "c": {
            "subj": [
                0,
                1,
                2,
                3
            ]
        }
    }
}

```

```

    ],
    "val": [
        3e+0,
        1e+0,
        5e+0,
        1e+0
    ]
},
"cfix": 0.0
},
"A": {
    "subi": [
        0,
        0,
        0,
        1,
        1,
        1,
        1,
        1,
        2,
        2
    ],
    "subj": [
        0,
        1,
        2,
        0,
        1,
        2,
        3,
        1,
        3
    ],
    "val": [
        3e+0,
        1e+0,
        2e+0,
        2e+0,
        1e+0,
        3e+0,
        1e+0,
        2e+0,
        3e+0
    ]
}
},
"Task/parameters": {
    "iparam": {
        "ANA_SOL_BASIS": "ON",
        "ANA_SOL_PRINT_VIOLATED": "OFF",
        "AUTO_SORT_A_BEFORE_OPT": "OFF",
        "AUTO_UPDATE_SOL_INFO": "OFF",
        "BASIS_SOLVE_USE_PLUS_ONE": "OFF",
        "BI_CLEAN_OPTIMIZER": "OPTIMIZER_FREE",
        "BI_IGNORE_MAX_ITER": "OFF",
        "BI_IGNORE_NUM_ERROR": "OFF",
        "BI_MAX_ITERATIONS": 1000000,
        "CACHE_LICENSE": "ON",
        "CHECK_CONVEXITY": "CHECK_CONVEXITY_FULL",
        "COMPRESS_STATFILE": "ON",
        "CONCURRENT_NUM_OPTIMIZERS": 2,

```

```

"CONCURRENT_PRIORITY_DUAL_SIMPLEX":2,
"CONCURRENT_PRIORITY_FREE_SIMPLEX":3,
"CONCURRENT_PRIORITY_INTPNT":4,
"CONCURRENT_PRIORITY_PRIMAL_SIMPLEX":1,
"FEASREPAIR_OPTIMIZE":"FEASREPAIR_OPTIMIZE_NONE",
"INFEAS_GENERIC_NAMES":"OFF",
"INFEAS_PREFER_PRIMAL":"ON",
"INFEAS_REPORT_AUTO":"OFF",
"INFEAS_REPORT_LEVEL":1,
"INTPNT_BASIS":"BI_ALWAYS",
"INTPNT_DIFF_STEP":"ON",
"INTPNT_FACTOR_DEBUG_LVL":0,
"INTPNT_FACTOR_METHOD":0,
"INTPNT_HOTSTART":"INTPNT_HOTSTART_NONE",
"INTPNT_MAX_ITERATIONS":400,
"INTPNT_MAX_NUM_COR":-1,
"INTPNT_MAX_NUM_REFINEMENT_STEPS":-1,
"INTPNT_OFF_COL_TRH":40,
"INTPNT_ORDER_METHOD":"ORDER_METHOD_FREE",
"INTPNT_REGULARIZATION_USE":"ON",
"INTPNT_SCALING":"SCALING_FREE",
"INTPNT_SOLVE_FORM":"SOLVE_FREE",
"INTPNT_STARTING_POINT":"STARTING_POINT_FREE",
"LIC_TRH_EXPIRY_WRN":7,
"LICENSE_DEBUG":"OFF",
"LICENSE_PAUSE_TIME":0,
"LICENSE_SUPPRESS_EXPIRE_WRNS":"OFF",
"LICENSE_WAIT":"OFF",
"LOG":10,
"LOG_ANA_PRO":1,
"LOG_BI":4,
"LOG_BI_FREQ":2500,
"LOG_CHECK_CONVEXITY":0,
"LOG_CONCURRENT":1,
"LOG_CUT_SECOND_OPT":1,
"LOG_EXPAND":0,
"LOG_FACTOR":1,
"LOG_FEAS_REPAIR":1,
"LOG_FILE":1,
"LOG_HEAD":1,
"LOG_INFEAS_ANA":1,
"LOG_INTPNT":4,
"LOG_MIO":4,
"LOG_MIO_FREQ":1000,
"LOG_OPTIMIZER":1,
"LOG_ORDER":1,
"LOG_PRESOLVE":1,
"LOG_RESPONSE":0,
"LOG_SENSITIVITY":1,
"LOG_SENSITIVITY_OPT":0,
"LOG_SIM":4,
"LOG_SIM_FREQ":1000,
"LOG_SIM_MINOR":1,
"LOG_STORAGE":1,
"MAX_NUM_WARNINGS":10,
"MIO_BRANCH_DIR":"BRANCH_DIR_FREE",
"MIO_CONSTRUCT_SOL":"OFF",
"MIO_CUT_CLIQUE":"ON",
"MIO_CUT_CMIR":"ON",
"MIO_CUT_GMI":"ON",
"MIO_CUT_KNAPSACK_COVER":"OFF",

```

```

"MIO_HEURISTIC_LEVEL":-1,
"MIO_MAX_NUM_BRANCHES":-1,
"MIO_MAX_NUM_RELAXS":-1,
"MIO_MAX_NUM_SOLUTIONS":-1,
"MIO_MODE":"MIO_MODE_SATISFIED",
"MIO_MT_USER_CB":"ON",
"MIO_NODE_OPTIMIZER":"OPTIMIZER_FREE",
"MIO_NODE_SELECTION":"MIO_NODE_SELECTION_FREE",
"MIO_PERSPECTIVE_REFORMULATE":"ON",
"MIO_PROBING_LEVEL":-1,
"MIO_RINS_MAX_NODES":-1,
"MIO_ROOT_OPTIMIZER":"OPTIMIZER_FREE",
"MIO_ROOT_REPEAT_PRESOLVE_LEVEL":-1,
"MT_SPINCOUNT":0,
"NUM_THREADS":0,
"OPF_MAX_TERMS_PER_LINE":5,
"OPF_WRITE_HEADER":"ON",
"OPF_WRITE_HINTS":"ON",
"OPF_WRITE_PARAMETERS":"OFF",
"OPF_WRITE_PROBLEM":"ON",
"OPF_WRITE_SOL_BAS":"ON",
"OPF_WRITE_SOL_ITG":"ON",
"OPF_WRITE_SOL_ITR":"ON",
"OPF_WRITE_SOLUTIONS":"OFF",
"OPTIMIZER":"OPTIMIZER_FREE",
"PARAM_READ_CASE_NAME":"ON",
"PARAM_READ_IGN_ERROR":"OFF",
"PRESOLVE_ELIMINATOR_MAX_FILL":-1,
"PRESOLVE_ELIMINATOR_MAX_NUM_TRIES":-1,
"PRESOLVE_LEVEL":-1,
"PRESOLVE_LINDEP_ABS_WORK_TRH":100,
"PRESOLVE_LINDEP_REL_WORK_TRH":100,
"PRESOLVE_LINDEP_USE":"ON",
"PRESOLVE_MAX_NUM_REDUCATIONS":-1,
"PRESOLVE_USE":"PRESOLVE_MODE_FREE",
"PRIMAL_REPAIR_OPTIMIZER":"OPTIMIZER_FREE",
"QO_SEPARABLE_REFORMULATION":"OFF",
"READ_DATA_COMPRESSED":"COMPRESS_FREE",
"READ_DATA_FORMAT":"DATA_FORMAT_EXTENSION",
"READ_DEBUG":"OFF",
"READ_KEEP_FREE_CON":"OFF",
"READ_LP_DROP_NEW_VARS_IN_BOU":"OFF",
"READ_LP_QUOTED_NAMES":"ON",
"READ_MPS_FORMAT":"MPS_FORMAT_FREE",
"READ_MPS_WIDTH":1024,
"READ_TASK_IGNORE_PARAM":"OFF",
"SENSITIVITY_ALL":"OFF",
"SENSITIVITY_OPTIMIZER":"OPTIMIZER_FREE_SIMPLEX",
"SENSITIVITY_TYPE":"SENSITIVITY_TYPE_BASIS",
"SIM_BASIS_FACTOR_USE":"ON",
"SIM_DEGEN":"SIM_DEGEN_FREE",
"SIM_DUAL_CRASH":90,
"SIM_DUAL_PHASEONE_METHOD":0,
"SIM_DUAL_RESTRICT_SELECTION":50,
"SIM_DUAL_SELECTION":"SIM_SELECTION_FREE",
"SIM_EXPLOIT_DUPVEC":"SIM_EXPLOIT_DUPVEC_OFF",
"SIM_HOTSTART":"SIM_HOTSTART_FREE",
"SIM_HOTSTART_LU":"ON",
"SIM_INTEGER":0,
"SIM_MAX_ITERATIONS":10000000,
"SIM_MAX_NUM_SETBACKS":250,

```

```

    "SIM_NON_SINGULAR": "ON",
    "SIM_PRIMAL_CRASH": 90,
    "SIM_PRIMAL_PHASEONE_METHOD": 0,
    "SIM_PRIMAL_RESTRICT_SELECTION": 50,
    "SIM_PRIMAL_SELECTION": "SIM_SELECTION_FREE",
    "SIM_REFACTOR_FREQ": 0,
    "SIM_REFORMULATION": "SIM_REFORMULATION_OFF",
    "SIM_SAVE_LU": "OFF",
    "SIM_SCALING": "SCALING_FREE",
    "SIM_SCALING_METHOD": "SCALING_METHOD_POW2",
    "SIM_SOLVE_FORM": "SOLVE_FREE",
    "SIM_STABILITY_PRIORITY": 50,
    "SIM_SWITCH_OPTIMIZER": "OFF",
    "SOL_FILTER_KEEP_BASIC": "OFF",
    "SOL_FILTER_KEEP_RANGED": "OFF",
    "SOL_READ_NAME_WIDTH": -1,
    "SOL_READ_WIDTH": 1024,
    "SOLUTION_CALLBACK": "OFF",
    "TIMING_LEVEL": 1,
    "WRITE_BAS_CONSTRAINTS": "ON",
    "WRITE_BAS_HEAD": "ON",
    "WRITE_BAS_VARIABLES": "ON",
    "WRITE_DATA_COMPRESSED": 0,
    "WRITE_DATA_FORMAT": "DATA_FORMAT_EXTENSION",
    "WRITE_DATA_PARAM": "OFF",
    "WRITE_FREE_CON": "OFF",
    "WRITE_GENERIC_NAMES": "OFF",
    "WRITE_GENERIC_NAMES_IO": 1,
    "WRITE_IGNORE_INCOMPATIBLE_CONIC_ITEMS": "OFF",
    "WRITE_IGNORE_INCOMPATIBLE_ITEMS": "OFF",
    "WRITE_IGNORE_INCOMPATIBLE_NL_ITEMS": "OFF",
    "WRITE_IGNORE_INCOMPATIBLE_PSD_ITEMS": "OFF",
    "WRITE_INT_CONSTRAINTS": "ON",
    "WRITE_INT_HEAD": "ON",
    "WRITE_INT_VARIABLES": "ON",
    "WRITE_LP_FULL_OBJ": "ON",
    "WRITE_LP_LINE_WIDTH": 80,
    "WRITE_LP_QUOTED_NAMES": "ON",
    "WRITE_LP_STRICT_FORMAT": "OFF",
    "WRITE_LP_TERMS_PER_LINE": 10,
    "WRITE_MPS_FORMAT": "MPS_FORMAT_FREE",
    "WRITE_MPS_INT": "ON",
    "WRITE_PRECISION": 15,
    "WRITE_SOL_BARVARIABLES": "ON",
    "WRITE_SOL_CONSTRAINTS": "ON",
    "WRITE_SOL_HEAD": "ON",
    "WRITE_SOL_IGNORE_INVALID_NAMES": "OFF",
    "WRITE_SOL_VARIABLES": "ON",
    "WRITE_TASK_INC_SOL": "ON",
    "WRITE_XML_MODE": "WRITE_XML_MODE_ROW"
},
"dparam": {
    "ANA_SOL_INFEAS_TOL": 1e-6,
    "BASIS_REL_TOL_S": 1e-12,
    "BASIS_TOL_S": 1e-6,
    "BASIS_TOL_X": 1e-6,
    "CHECK_CONVEXITY_REL_TOL": 1e-10,
    "DATA_TOL_AIJ": 1e-12,
    "DATA_TOL_AIJ_HUGE": 1e+20,
    "DATA_TOL_AIJ_LARGE": 1e+10,
    "DATA_TOL_BOUND_INF": 1e+16,

```

```

"DATA_TOL_BOUND_WRN":1e+8,
"DATA_TOL_C_HUGE":1e+16,
"DATA_TOL_CJ_LARGE":1e+8,
"DATA_TOL_QIJ":1e-16,
"DATA_TOL_X":1e-8,
"FEASREPAIR_TOL":1e-10,
"INTPNT_CO_TOL_DFEAS":1e-8,
"INTPNT_CO_TOL_INFEAS":1e-10,
"INTPNT_CO_TOL_MU_RED":1e-8,
"INTPNT_CO_TOL_NEAR_REL":1e+3,
"INTPNT_CO_TOL_PFEAS":1e-8,
"INTPNT_CO_TOL_REL_GAP":1e-7,
"INTPNT_NL_MERIT_BAL":1e-4,
"INTPNT_NL_TOL_DFEAS":1e-8,
"INTPNT_NL_TOL_MU_RED":1e-12,
"INTPNT_NL_TOL_NEAR_REL":1e+3,
"INTPNT_NL_TOL_PFEAS":1e-8,
"INTPNT_NL_TOL_REL_GAP":1e-6,
"INTPNT_NL_TOL_REL_STEP":9.95e-1,
"INTPNT_QO_TOL_DFEAS":1e-8,
"INTPNT_QO_TOL_INFEAS":1e-10,
"INTPNT_QO_TOL_MU_RED":1e-8,
"INTPNT_QO_TOL_NEAR_REL":1e+3,
"INTPNT_QO_TOL_PFEAS":1e-8,
"INTPNT_QO_TOL_REL_GAP":1e-8,
"INTPNT_TOL_DFEAS":1e-8,
"INTPNT_TOL_DSAFE":1e+0,
"INTPNT_TOL_INFEAS":1e-10,
"INTPNT_TOL_MU_RED":1e-16,
"INTPNT_TOL_PATH":1e-8,
"INTPNT_TOL_PFEAS":1e-8,
"INTPNT_TOL_PSAFE":1e+0,
"INTPNT_TOL_REL_GAP":1e-8,
"INTPNT_TOL_REL_STEP":9.999e-1,
"INTPNT_TOL_STEP_SIZE":1e-6,
"LOWER_OBJ_CUT":-1e+30,
"LOWER_OBJ_CUT_FINITE_TRH":-5e+29,
"MIO_DISABLE_TERM_TIME":-1e+0,
"MIO_MAX_TIME":-1e+0,
"MIO_MAX_TIME_APRX_OPT":6e+1,
"MIO_NEAR_TOL_ABS_GAP":0.0,
"MIO_NEAR_TOL_REL_GAP":1e-3,
"MIO_REL_GAP_CONST":1e-10,
"MIO_TOL_ABS_GAP":0.0,
"MIO_TOL_ABS_RELAX_INT":1e-5,
"MIO_TOL_FEAS":1e-6,
"MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT":0.0,
"MIO_TOL_REL_GAP":1e-4,
"MIO_TOL_X":1e-6,
"OPTIMIZER_MAX_TIME":-1e+0,
"PRESOLVE_TOL_ABS_LINDEP":1e-6,
"PRESOLVE_TOL_AIJ":1e-12,
"PRESOLVE_TOL_REL_LINDEP":1e-10,
"PRESOLVE_TOL_S":1e-8,
"PRESOLVE_TOL_X":1e-8,
"QCQO_REFORMULATE_REL_DROP_TOL":1e-15,
"SEMIDEFINITE_TOL_APPROX":1e-10,
"SIM_LU_TOL_REL_PIV":1e-2,
"SIMPLEX_ABS_TOL_PIV":1e-7,
"UPPER_OBJ_CUT":1e+30,
"UPPER_OBJ_CUT_FINITE_TRH":5e+29

```



```

    },
    "sparam":{
        "BAS_SOL_FILE_NAME": "",
        "DATA_FILE_NAME": "examples/tools/data/lo1.mps",
        "DEBUG_FILE_NAME": "",
        "INT_SOL_FILE_NAME": "",
        "ITR_SOL_FILE_NAME": "",
        "MIO_DEBUG_STRING": "",
        "PARAM_COMMENT_SIGN": "%%",
        "PARAM_READ_FILE_NAME": "",
        "PARAM_WRITE_FILE_NAME": "",
        "READ_MPS_BOU_NAME": "",
        "READ_MPS_OBJ_NAME": "",
        "READ_MPS_RAN_NAME": "",
        "READ_MPS_RHS_NAME": "",
        "SENSITIVITY_FILE_NAME": "",
        "SENSITIVITY_RES_FILE_NAME": "",
        "SOL_FILTER_XC_LOW": "",
        "SOL_FILTER_XC_UPR": "",
        "SOL_FILTER_XX_LOW": "",
        "SOL_FILTER_XX_UPR": "",
        "STAT_FILE_NAME": "",
        "STAT_KEY": "",
        "STAT_NAME": "",
        "WRITE_LP_GEN_VAR_NAME": "XMSKGEN"
    }
}
}

```

16.8 The Solution File Format

MOSEK provides several solution files depending on the problem type and the optimizer used:

- *basis solution file* (extension `.bas`) if the problem is optimized using the simplex optimizer or basis identification is performed,
- *interior solution file* (extension `.sol`) if a problem is optimized using the interior-point optimizer and no basis identification is required,
- *integer solution file* (extension `.int`) if the problem contains integer constrained variables.

All solution files have the format:

NAME	: <problem name>						
PROBLEM STATUS	: <status of the problem>						
SOLUTION STATUS	: <status of the solution>						
OBJECTIVE NAME	: <name of the objective function>						
PRIMAL OBJECTIVE	: <primal objective value corresponding to the solution>						
DUAL OBJECTIVE	: <dual objective value corresponding to the solution>						
CONSTRAINTS							
INDEX	NAME	AT ACTIVITY	LOWER LIMIT	UPPER LIMIT	DUAL LOWER	DUAL UPPER	
?	<name>	?? <a value>	<a value>	<a value>	<a value>	<a value>	
VARIABLES							
INDEX	NAME	AT ACTIVITY	LOWER LIMIT	UPPER LIMIT	DUAL LOWER	DUAL UPPER	CONIC
↪DUAL							
?	<name>	?? <a value>	<a value>	<a value>	<a value>	<a value>	<a value>

In the example the fields ? and <> will be filled with problem and solution specific information. As can be observed a solution report consists of three sections, i.e.

- **HEADER** In this section, first the name of the problem is listed and afterwards the problem and solution status are shown. Next the primal and dual objective values are displayed.

- **CONSTRAINTS** For each constraint i of the form

$$l_i^c \leq \sum_{j=1}^n a_{ij}x_j \leq u_i^c, \quad (16.15)$$

the following information is listed:

- **INDEX**: A sequential index assigned to the constraint by **MOSEK**
- **NAME**: The name of the constraint assigned by the user.
- **AT**: The status of the constraint. In Table 16.4 the possible values of the status keys and their interpretation are shown.

Table 16.4: Status keys.

Status key	Interpretation
UN	Unknown status
BS	Is basic
SB	Is superbasic
LL	Is at the lower limit (bound)
UL	Is at the upper limit (bound)
EQ	Lower limit is identical to upper limit
**	Is infeasible i.e. the lower limit is greater than the upper limit.

- **ACTIVITY**: the quantity $\sum_{j=1}^n a_{ij}x_j^*$, where x^* is the value of the primal solution.
- **LOWER LIMIT**: the quantity l_i^c (see (16.15).)
- **UPPER LIMIT**: the quantity u_i^c (see (16.15).)
- **DUAL LOWER**: the dual multiplier corresponding to the lower limit on the constraint.
- **DUAL UPPER**: the dual multiplier corresponding to the upper limit on the constraint.

- **VARIABLES** The last section of the solution report lists information about the variables. This information has a similar interpretation as for the constraints. However, the column with the header **CONIC DUAL** is included for problems having one or more conic constraints. This column shows the dual variables corresponding to the conic constraints.

Example: 1o1.sol

In Listing 16.7 we show the solution file for the 1o1.opf problem.

Listing 16.7: An example of .sol file.

NAME	:				
PROBLEM STATUS	:	PRIMAL_AND_DUAL_FEASIBLE			
SOLUTION STATUS	:	OPTIMAL			
OBJECTIVE NAME	:	obj			
PRIMAL OBJECTIVE	:	8.33333333e+01			
DUAL OBJECTIVE	:	8.33333332e+01			
CONSTRAINTS					
INDEX	NAME	AT	ACTIVITY	LOWER LIMIT	UPPER LIMIT
			DUAL LOWER		DUAL UPPER
0	c1	EQ	3.00000000000000e+01	3.00000000e+01	3.00000000e+01
			-2.49999999741653e+00		-0.
1	c2	SB	5.33333333049187e+01	1.50000000e+01	NONE
			-0.00000000000000e+00		2.
2	c3	UL	2.49999999842049e+01	NONE	2.50000000e+01
			-3.33333332895108e-01		-0.
VARIABLES					
INDEX	NAME	AT	ACTIVITY	LOWER LIMIT	UPPER LIMIT
			DUAL LOWER		DUAL UPPER
0	x1	LL	1.67020427038537e-09	0.00000000e+00	NONE
			-0.00000000000000e+00		-4.

(continues on next page)

(continued from previous page)

1	x2	LL 2.93510446211883e-09	0.00000000e+00	1.00000000e+01	-2.
↪	16666666494915e+00	6.20868657679896e-10			
2	x3	SB 1.49999999899424e+01	0.00000000e+00	NONE	-8.
↪	79123177245553e-10	-0.00000000000000e+00			
3	x4	SB 8.33333332273115e+00	0.00000000e+00	NONE	-1.
↪	69795978848200e-09	-0.00000000000000e+00			

Chapter 17

List of examples

List of examples shipped in the distribution of Optimizer API for C:

Table 17.1: List of distributed examples

File	Description
blas_lapack.c	Demonstrates the MOSEK interface to BLAS/LAPACK linear algebra routines
callback.c	An example of data/progress callback
ceo1.c	A simple conic exponential problem
concurrent.cc	Implementation of a concurrent optimizer for linear and mixed-integer problems
cqo1.c	A simple conic quadratic problem
errorreporting.c	Demonstrates how error reporting can be customized
feasrepairex1.c	A simple example of how to repair an infeasible problem
gp1.c	A simple geometric program (GP) in conic form
lo1.c	A simple linear problem
lo2.c	A simple linear problem
logistic.c	Implements logistic regression and simple log-sum-exp (CEO)
mico1.c	A simple mixed-integer conic problem
milol.c	A simple mixed-integer linear problem
miointsol.c	A simple mixed-integer linear problem with an initial guess
modelLib.c	Library of implementations of basic functions
opt_server_async.c	Uses MOSEK OptServer to solve an optimization problem asynchronously
opt_server_sync.c	Uses MOSEK OptServer to solve an optimization problem synchronously
parallel.cc	Demonstrates parallel optimization
parameters.c	Shows how to set optimizer parameters and read information items
portfolio_1_basic.c	Portfolio optimization - basic Markowitz model
portfolio_2_frontier.c	Portfolio optimization - efficient frontier
portfolio_3_impact.c	Portfolio optimization - market impact costs
portfolio_4_transaction.c	Portfolio optimization - transaction costs
portfolio_5_cardinality.c	Portfolio optimization - cardinality constraints
pow1.c	A simple power cone problem
qcqo1.c	A simple quadratically constrained quadratic problem
qo1.c	A simple quadratic problem

Continued on next page

Table 17.1 – continued from previous page

File	Description
<code>reoptimization.c</code>	Demonstrate how to modify and re-optimize a linear problem
<code>response.c</code>	Demonstrates proper response handling
<code>sdo1.c</code>	A simple semidefinite optimization problem
<code>sensitivity.c</code>	Sensitivity analysis performed on a small linear problem
<code>simple.c</code>	A simple I/O example: read problem from a file, solve and write solutions
<code>solutionquality.c</code>	Demonstrates how to examine the quality of a solution
<code>solvebasis.c</code>	Demonstrates solving a linear system with the basis matrix
<code>solvelinear.c</code>	Demonstrates solving a general linear system
<code>sparsecholesky.c</code>	Shows how to find a Cholesky factorization of a sparse matrix
<code>unicode.c</code>	Demonstrates string conversion to Unicode

Additional examples can be found on the **MOSEK** website and in other **MOSEK** publications.

Chapter 18

Interface changes

The section shows interface-specific changes to the **MOSEK** Optimizer API for C in version 9.0. See the [release notes](#) for general changes and new features of the **MOSEK** Optimization Suite.

18.1 Backwards compatibility

- **Parameters.** Users who set parameters to tune the performance and numerical properties of the solver (termination criteria, tolerances, solving primal or dual, presolve etc.) are recommended to reevaluate such tuning. It may be that other, or default, parameter settings will be more beneficial in the current version. The hints in [Sec. 8](#) may be useful for some cases.
- All functions using the enum `MSKaccmodee` were removed. Use corresponding separate functions for manipulating variables and constraints. For example, instead of

```
MSK_putbound(task, MSK_ACC_VAR, ...);  
MSK_putbound(task, MSK_ACC_CON, ...);
```

use

```
MSK_putvarbound(task, ...);  
MSK_putconbound(task, ...);
```

and so on.

- Removed all Near problem and solution statuses i.e. `MSK_SOL_STA_NEAR_OPTIMAL`, `MSK_SOL_STA_NEAR_PRIM_INFEAS_CER`, etc. See [Sec. 13.3.3](#).
- All functions related to the general nonlinear optimizer and Scopt have been removed. See [Sec. 15.10](#).

18.2 Functions

Added

- *MSK_setupthreads*
- *MSK_appendsparsesymmatlist*
- *MSK_generateconenames*
- *MSK_generateconnames*
- *MSK_generatevarnames*
- *MSK_getacolslice*
- *MSK_getacolslicenummz*

- *MSK_getarowslice*
- *MSK_getarowslicenumz*
- *MSK_getatruncatetol*
- *MSK_getbarsslice*
- *MSK_getbarxslice*
- *MSK_getclist*
- *MSK_getskn*
- *MSK_putatruncatetol*
- *MSK_putbaraijlist*
- *MSK_putbararowlist*
- *MSK_putconboundlistconst*
- *MSK_putconboundsliceconst*
- *MSK_putconsolutioni*
- *MSK_putvarboundlistconst*
- *MSK_putvarboundsliceconst*
- *MSK_putvarsolutionj*
- *MSK_readjsonstring*
- *MSK_readlpstring*
- *MSK_readopfstring*
- *MSK_readptfstring*

Removed

- *MSK_checkconvexity*
- *MSK_chgbound*
- *MSK_getaslice*
- *MSK_getaslicenumz*
- *MSK_getbound*
- *MSK_getboundslice*
- *MSK_getnlfunc*
- *MSK_getsolutioni*
- *MSK_printdata*
- *MSK_putbound*
- *MSK_putboundlist*
- *MSK_putboundslice*
- *MSK_putnlfunc*
- *MSK_putsolutioni*

18.3 Parameters

Added

- *MSK_IPAR_INTPNT_ORDER_GP_NUM_SEEDS*
- *MSK_IPAR_INTPNT_PURIFY*
- *MSK_IPAR_LOG_INCLUDE_SUMMARY*
- *MSK_IPAR_LOG_LOCAL_INFO*
- *MSK_IPAR_MIO_CONIC_OUTER_APPROXIMATION*
- *MSK_IPAR_MIO_FEASPUMP_LEVEL*
- *MSK_IPAR_MIO_MAX_NUM_ROOT_CUT_ROUNDS*
- *MSK_IPAR_MIO_PROPAGATE_OBJECTIVE_CONSTRAINT*
- *MSK_IPAR_MIO_SEED*
- *MSK_IPAR_OPF_WRITE_LINE_LENGTH*
- *MSK_IPAR_PREOLVE_MAX_NUM_PASS*
- *MSK_IPAR_PTF_WRITE_TRANSFORM*
- *MSK_IPAR_SIM_SEED*
- *MSK_IPAR_WRITE_COMPRESSION*

Removed

- *MSK_DPAR_DATA_TOL_AIJ*
- *MSK_DPAR_INTPNT_NL_MERIT_BAL*
- *MSK_DPAR_INTPNT_NL_TOL_DFEAS*
- *MSK_DPAR_INTPNT_NL_TOL_MU_RED*
- *MSK_DPAR_INTPNT_NL_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_NL_TOL_PFEAS*
- *MSK_DPAR_INTPNT_NL_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_NL_TOL_REL_STEP*
- *MSK_DPAR_MIO_DISABLE_TERM_TIME*
- *MSK_DPAR_MIO_NEAR_TOL_ABS_GAP*
- *MSK_DPAR_MIO_NEAR_TOL_REL_GAP*
- *MSK_IPAR_MIO_CONSTRUCT_SOL*
- *MSK_IPAR_MIO_MT_USER_CB*
- *MSK_IPAR_OPF_MAX_TERMS_PER_LINE*
- *MSK_IPAR_READ_DATA_COMPRESSED*
- *MSK_IPAR_READ_DATA_FORMAT*
- *MSK_IPAR_WRITE_DATA_COMPRESSED*
- *MSK_IPAR_WRITE_DATA_FORMAT*

18.4 Constants

Added

- *MSK_COMPRESS_ZSTD*
- *MSK_CT_DEXP*
- *MSK_CT_DPOW*
- *MSK_CT_PEXP*
- *MSK_CT_PPOW*
- *MSK_CT_ZERO*
- *MSK_DATA_FORMAT_PTF*
- *MSK_IINF_MIO_NUMBIN*
- *MSK_IINF_MIO_NUMBINCONEVAR*
- *MSK_IINF_MIO_NUMCONE*
- *MSK_IINF_MIO_NUMCONEVAR*
- *MSK_IINF_MIO_NUMCONT*
- *MSK_IINF_MIO_NUMCONTCONEVAR*
- *MSK_IINF_MIO_NUMDEXPCONES*
- *MSK_IINF_MIO_NUMDPOWCONES*
- *MSK_IINF_MIO_NUMINTCONEVAR*
- *MSK_IINF_MIO_NUMPEXPONES*
- *MSK_IINF_MIO_NUMPPOWCONES*
- *MSK_IINF_MIO_NUMQCONES*
- *MSK_IINF_MIO_NUMRQCONES*
- *MSK_IINF_MIO_PRE SOLVED_NUMBINCONEVAR*
- *MSK_IINF_MIO_PRE SOLVED_NUMCONE*
- *MSK_IINF_MIO_PRE SOLVED_NUMCONEVAR*
- *MSK_IINF_MIO_PRE SOLVED_NUMCONTCONEVAR*
- *MSK_IINF_MIO_PRE SOLVED_NUMDEXPCONES*
- *MSK_IINF_MIO_PRE SOLVED_NUMDPOWCONES*
- *MSK_IINF_MIO_PRE SOLVED_NUMINTCONEVAR*
- *MSK_IINF_MIO_PRE SOLVED_NUMPEXPONES*
- *MSK_IINF_MIO_PRE SOLVED_NUMPPOWCONES*
- *MSK_IINF_MIO_PRE SOLVED_NUMQCONES*
- *MSK_IINF_MIO_PRE SOLVED_NUMRQCONES*
- *MSK_IINF_PURIFY_DUAL_SUCCESS*
- *MSK_IINF_PURIFY_PRIMAL_SUCCESS*
- *MSK_LIINF_MIO_ANZ*

Removed

- MSK_DATAFORMAT_XML
- MSK_DINFITEM_MIO_HEURISTIC_TIME
- MSK_DINFITEM_MIO_OPTIMIZER_TIME
- MSK_IINFITEM_MIO_CONSTRUCT_NUM_ROUNDINGS
- MSK_IINFITEM_MIO_INITIAL_SOLUTION
- MSK_IINFITEM_MIO_NEAR_ABSGAP_SATISFIED
- MSK_IINFITEM_MIO_NEAR_RELGAP_SATISFIED
- MSK_LIINFITEM_MIO_SIM_MAXITER_SETBACKS
- MSK_MIONODESELTYPE_HYBRID
- MSK_MIONODESELTYPE_WORST
- MSK_PROBLEMTYPE_GECO
- MSK_PROSTA_NEAR_DUAL_FEAS
- MSK_PROSTA_NEAR_PRIM_AND_DUAL_FEAS
- MSK_PROSTA_NEAR_PRIM_FEAS
- MSK_SENSITIVITYTYPE_OPTIMAL_PARTITION
- MSK_SOLSTA_NEAR_DUAL_FEAS
- MSK_SOLSTA_NEAR_DUAL_INFEAS_CER
- MSK_SOLSTA_NEAR_INTEGER_OPTIMAL
- MSK_SOLSTA_NEAR_OPTIMAL
- MSK_SOLSTA_NEAR_PRIM_AND_DUAL_FEAS
- MSK_SOLSTA_NEAR_PRIM_FEAS
- MSK_SOLSTA_NEAR_PRIM_INFEAS_CER

18.5 Response Codes

Added

- *MSK_RES_ERR_APPENDING_TOO_BIG_CONE*
- *MSK_RES_ERR_CBF_DUPLICATE_POW_CONES*
- *MSK_RES_ERR_CBF_DUPLICATE_POW_STAR_CONES*
- *MSK_RES_ERR_CBF_INVALID_DIMENSION_OF_CONES*
- *MSK_RES_ERR_CBF_INVALID_EXP_DIMENSION*
- *MSK_RES_ERR_CBF_INVALID_NUMBER_OF_CONES*
- *MSK_RES_ERR_CBF_INVALID_POWER*
- *MSK_RES_ERR_CBF_INVALID_POWER_CONE_INDEX*

- *MSK_RES_ERR_CBF_INVALID_POWER_STAR_CONE_INDEX*
- *MSK_RES_ERR_CBF_POWER_CONE_IS_TOO_LONG*
- *MSK_RES_ERR_CBF_POWER_CONE_MISMATCH*
- *MSK_RES_ERR_CBF_POWER_STAR_CONE_MISMATCH*
- *MSK_RES_ERR_CBF_UNHANDLED_POWER_CONE_TYPE*
- *MSK_RES_ERR_CBF_UNHANDLED_POWER_STAR_CONE_TYPE*
- *MSK_RES_ERR_CONE_PARAMETER*
- *MSK_RES_ERR_FORMAT_STRING*
- *MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_CFIX*
- *MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_FREE_CONSTRAINTS*
- *MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_NONLINEAR*
- *MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_RANGED_CONSTRAINTS*
- *MSK_RES_ERR_NUM_ARGUMENTS*
- *MSK_RES_ERR_PTF_FORMAT*
- *MSK_RES_ERR_SHAPE_IS_TOO_LARGE*
- *MSK_RES_ERR_SLICE_SIZE*
- *MSK_RES_ERR_TOO_SMALL_A_TRUNCATION_VALUE*
- *MSK_RES_WRN_EXP_CONES_WITH_VARIABLES_FIXED_AT_ZERO*
- *MSK_RES_WRN_POW_CONES_WITH_ROOT_FIXED_AT_ZERO*

Removed

- *MSK_RES_ERR_CANNOT_CLONE_NL*
- *MSK_RES_ERR_CANNOT_HANDLE_NL*
- *MSK_RES_ERR_INVALID_ACCMODE*
- *MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_GENERAL_NL*
- *MSK_RES_ERR_NONLINEAR_FUNCTIONS_NOT_ALLOWED*
- *MSK_RES_ERR_NR_ARGUMENTS*
- *MSK_RES_ERR_OPEN_DL*
- *MSK_RES_ERR_USER_FUNC_RET*
- *MSK_RES_ERR_USER_FUNC_RET_DATA*
- *MSK_RES_ERR_USER_NLO_EVAL*
- *MSK_RES_ERR_USER_NLO_EVAL_HESSUBI*
- *MSK_RES_ERR_USER_NLO_EVAL_HESSUBJ*
- *MSK_RES_ERR_USER_NLO_FUNC*
- *MSK_RES_TRM_MIO_NEAR_ABS_GAP*
- *MSK_RES_TRM_MIO_NEAR_REL_GAP*
- *MSK_RES_WRN_CONSTRUCT_INVALID_SOL_ITG*
- *MSK_RES_WRN_CONSTRUCT_NO_SOL_ITG*
- *MSK_RES_WRN_CONSTRUCT_SOLUTION_INFEAS*
- *MSK_RES_WRN_NO_NONLINEAR_FUNCTION_WRITE*

Bibliography

- [AA95] E. D. Andersen and K. D. Andersen. Presolving in linear programming. *Math. Programming*, 71(2):221–245, 1995.
- [AGMX96] E. D. Andersen, J. Gondzio, Cs. Mészáros, and X. Xu. Implementation of interior point methods for large scale linear programming. In T. Terlaky, editor, *Interior-point methods of mathematical programming*, pages 189–252. Kluwer Academic Publishers, 1996.
- [ART03] E. D. Andersen, C. Roos, and T. Terlaky. On implementing a primal-dual interior-point method for conic quadratic optimization. *Math. Programming*, February 2003.
- [AY96] E. D. Andersen and Y. Ye. Combining interior-point and pivoting algorithms. *Management Sci.*, 42(12):1719–1731, December 1996.
- [And09] Erling D. Andersen. The homogeneous and self-dual model and algorithm for linear optimization. Technical Report TR-1-2009, MOSEK ApS, 2009. URL: <http://docs.mosek.com/whitepapers/homolo.pdf>.
- [And13] Erling D. Andersen. On formulating quadratic functions in optimization models. Technical Report TR-1-2013, MOSEK ApS, 2013. Last revised 23-feb-2016. URL: <http://docs.mosek.com/whitepapers/qmodel.pdf>.
- [BKVH07] S. Boyd, S.J. Kim, L. Vandenbergh, and A. Hassibi. A Tutorial on Geometric Programming. *Optimization and Engineering*, 8(1):67–127, 2007. Available at http://www.stanford.edu/~boyd/gp_tutorial.html.
- [Chv83] V. Chvátal. *Linear programming*. W.H. Freeman and Company, 1983.
- [GK00] Richard C. Grinold and Ronald N. Kahn. *Active portfolio management*. McGraw-Hill, New York, 2 edition, 2000.
- [Naz87] J. L. Nazareth. *Computer Solution of Linear Programs*. Oxford University Press, New York, 1987.
- [RTV97] C. Roos, T. Terlaky, and J. -Ph. Vial. *Theory and algorithms for linear optimization: an interior point approach*. John Wiley and Sons, New York, 1997.
- [Ste98] G. W. Stewart. *Matrix Algorithms. Volume 1: Basic decompositions*. SIAM, 1998.
- [Wal00] S. W. Wallace. Decision making under uncertainty: is sensitivity of any use. *Oper. Res.*, 48(1):20–25, January 2000.
- [Wol98] L. A. Wolsey. *Integer programming*. John Wiley and Sons, 1998.

Symbol Index

Enumerations

MSKbasindtypee, 427
MSK_BI_RESERVED, 427
MSK_BI_NO_ERROR, 427
MSK_BI_NEVER, 427
MSK_BI_IF_FEASIBLE, 427
MSK_BI_ALWAYS, 427
MSKboundkeye, 427
MSK_BK_UP, 428
MSK_BK_RA, 428
MSK_BK_LO, 427
MSK_BK_FX, 428
MSK_BK_FR, 428
MSKbranchdire, 445
MSK_BRANCH_DIR_UP, 445
MSK_BRANCH_DIR_ROOT_LP, 445
MSK_BRANCH_DIR_PSEUDOCOST, 445
MSK_BRANCH_DIR_NEAR, 445
MSK_BRANCH_DIR_GUIDED, 445
MSK_BRANCH_DIR_FREE, 445
MSK_BRANCH_DIR_FAR, 445
MSK_BRANCH_DIR_DOWN, 445
MSKcallbackcodee, 429
MSK_CALLBACK_WRITE_OPF, 433
MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX_BI, 433
MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX, 433
MSK_CALLBACK_UPDATE_PRIMAL_BI, 433
MSK_CALLBACK_UPDATE_PRESOLVE, 433
MSK_CALLBACK_UPDATE_DUAL_SIMPLEX_BI, 433
MSK_CALLBACK_UPDATE_DUAL_SIMPLEX, 433
MSK_CALLBACK_UPDATE_DUAL_BI, 433
MSK_CALLBACK_SOLVING_REMOTE, 433
MSK_CALLBACK_READ_OPF_SECTION, 433
MSK_CALLBACK_READ_OPF, 433
MSK_CALLBACK_PRIMAL_SIMPLEX, 433
MSK_CALLBACK_NEW_INT_MIO, 433
MSK_CALLBACK_INTPNT, 433
MSK_CALLBACK_IM_SIMPLEX_BI, 433
MSK_CALLBACK_IM_SIMPLEX, 433
MSK_CALLBACK_IM_ROOT_CUTGEN, 433
MSK_CALLBACK_IM_READ, 433
MSK_CALLBACK_IM_QO_REFORMULATE, 433
MSK_CALLBACK_IM_PRIMAL_SIMPLEX, 433
MSK_CALLBACK_IM_PRIMAL_SENSIVITY, 432
MSK_CALLBACK_IM_PRIMAL_BI, 432
MSK_CALLBACK_IM_PRESOLVE, 432
MSK_CALLBACK_IM_ORDER, 432
MSK_CALLBACK_IM_MIO_PRIMAL_SIMPLEX, 432
MSK_CALLBACK_IM_MIO_INTPNT, 432
MSK_CALLBACK_IM_MIO_DUAL_SIMPLEX, 432
MSK_CALLBACK_IM_MIO, 432
MSK_CALLBACK_IM_LU, 432
MSK_CALLBACK_IM_LICENSE_WAIT, 432
MSK_CALLBACK_IM_INTPNT, 432
MSK_CALLBACK_IM_FULL_CONVEXITY_CHECK, 432
MSK_CALLBACK_IM_DUAL_SIMPLEX, 432
MSK_CALLBACK_IM_DUAL_SENSIVITY, 432
MSK_CALLBACK_IM_DUAL_BI, 432
MSK_CALLBACK_IM_CONIC, 432
MSK_CALLBACK_IM_BI, 432
MSK_CALLBACK_END_WRITE, 432
MSK_CALLBACK_END_TO_CONIC, 432
MSK_CALLBACK_END_SIMPLEX_BI, 432
MSK_CALLBACK_END_SIMPLEX, 431
MSK_CALLBACK_END_ROOT_CUTGEN, 431
MSK_CALLBACK_END_READ, 431
MSK_CALLBACK_END_QCQO_REFORMULATE, 431
MSK_CALLBACK_END_PRIMAL_SIMPLEX_BI, 431
MSK_CALLBACK_END_PRIMAL_SIMPLEX, 431
MSK_CALLBACK_END_PRIMAL_SETUP_BI, 431
MSK_CALLBACK_END_PRIMAL_SENSITIVITY, 431
MSK_CALLBACK_END_PRIMAL_REPAIR, 431
MSK_CALLBACK_END_PRIMAL_BI, 431
MSK_CALLBACK_END_PRESOLVE, 431
MSK_CALLBACK_END_OPTIMIZER, 431
MSK_CALLBACK_END_MIO, 431
MSK_CALLBACK_END_LICENSE_WAIT, 431
MSK_CALLBACK_END_INTPNT, 431
MSK_CALLBACK_END_INFEAS_ANA, 431
MSK_CALLBACK_END_FULL_CONVEXITY_CHECK, 431
MSK_CALLBACK_END_DUAL_SIMPLEX_BI, 431
MSK_CALLBACK_END_DUAL_SIMPLEX, 431
MSK_CALLBACK_END_DUAL_SETUP_BI, 431
MSK_CALLBACK_END_DUAL_SENSITIVITY, 431
MSK_CALLBACK_END_DUAL_BI, 431
MSK_CALLBACK_END_CONIC, 431
MSK_CALLBACK_END_BI, 430
MSK_CALLBACK_DUAL_SIMPLEX, 430
MSK_CALLBACK_CONIC, 430
MSK_CALLBACK_BEGIN_WRITE, 430
MSK_CALLBACK_BEGIN_TO_CONIC, 430
MSK_CALLBACK_BEGIN_SIMPLEX_BI, 430
MSK_CALLBACK_BEGIN_SIMPLEX, 430
MSK_CALLBACK_BEGIN_ROOT_CUTGEN, 430
MSK_CALLBACK_BEGIN_READ, 430
MSK_CALLBACK_BEGIN_QCQO_REFORMULATE, 430
MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX_BI, 430

MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX, 430
 MSK_CALLBACK_BEGIN_PRIMAL_SETUP_BI, 430
 MSK_CALLBACK_BEGIN_PRIMAL_SENSITIVITY, 430
 MSK_CALLBACK_BEGIN_PRIMAL_REPAIR, 430
 MSK_CALLBACK_BEGIN_PRIMAL_BI, 430
 MSK_CALLBACK_BEGIN_PRESOLVE, 430
 MSK_CALLBACK_BEGIN_OPTIMIZER, 430
 MSK_CALLBACK_BEGIN_MIO, 430
 MSK_CALLBACK_BEGIN_LICENSE_WAIT, 430
 MSK_CALLBACK_BEGIN_INTPNT, 430
 MSK_CALLBACK_BEGIN_INFEAS_ANA, 430
 MSK_CALLBACK_BEGIN_FULL_CONVEXITY_CHECK, 430
 MSK_CALLBACK_BEGIN_DUAL_SIMPLEX_BI, 429
 MSK_CALLBACK_BEGIN_DUAL_SIMPLEX, 429
 MSK_CALLBACK_BEGIN_DUAL_SETUP_BI, 429
 MSK_CALLBACK_BEGIN_DUAL_SENSITIVITY, 429
 MSK_CALLBACK_BEGIN_DUAL_BI, 429
 MSK_CALLBACK_BEGIN_CONIC, 429
 MSK_CALLBACK_BEGIN_BI, 429
 MSKcheckconvexitytypee, 433
 MSK_CHECK_CONVEXITY_SIMPLE, 434
 MSK_CHECK_CONVEXITY_NONE, 434
 MSK_CHECK_CONVEXITY_FULL, 434
 MSKcompressypee, 434
 MSK_COMPRESS_ZSTD, 434
 MSK_COMPRESS_NONE, 434
 MSK_COMPRESS_GZIP, 434
 MSK_COMPRESS_FREE, 434
 MSKconetypee, 434
 MSK_CT_ZERO, 434
 MSK_CT_RQUAD, 434
 MSK_CT_QUAD, 434
 MSK_CT_PPOW, 434
 MSK_CT_PEXP, 434
 MSK_CT_DPOW, 434
 MSK_CT_DEXP, 434
 MSKdataformat, 435
 MSK_DATA_FORMAT_TASK, 435
 MSK_DATA_FORMAT_PTF, 435
 MSK_DATA_FORMAT_OP, 435
 MSK_DATA_FORMAT_MPS, 435
 MSK_DATA_FORMAT_LP, 435
 MSK_DATA_FORMAT_JSON_TASK, 435
 MSK_DATA_FORMAT_FREE_MPS, 435
 MSK_DATA_FORMAT_EXTENSION, 435
 MSK_DATA_FORMAT_CB, 435
 MSKdinfiteme, 435
 MSK_DINF_TO_CONIC_TIME, 439
 MSK_DINF_SOL_ITR_PVIOLVAR, 439
 MSK_DINF_SOL_ITR_PVIOLCONES, 439
 MSK_DINF_SOL_ITR_PVIOLCON, 439
 MSK_DINF_SOL_ITR_PVIOLBARVAR, 439
 MSK_DINF_SOL_ITR_PRIMAL_OBJ, 439
 MSK_DINF_SOL_ITR_NRM_Y, 439
 MSK_DINF_SOL_ITR_NRM_XX, 439
 MSK_DINF_SOL_ITR_NRM_XC, 439
 MSK_DINF_SOL_ITR_NRM_SUX, 439
 MSK_DINF_SOL_ITR_NRM_SUC, 439
 MSK_DINF_SOL_ITR_NRM_SNX, 439
 MSK_DINF_SOL_ITR_NRM_SLX, 439
 MSK_DINF_SOL_ITR_NRM_SLC, 439
 MSK_DINF_SOL_ITR_NRM_BARX, 439
 MSK_DINF_SOL_ITR_NRM_BARS, 439
 MSK_DINF_SOL_ITR_DVIOLVAR, 439
 MSK_DINF_SOL_ITR_DVIOLCONES, 439
 MSK_DINF_SOL_ITR_DVIOLCON, 439
 MSK_DINF_SOL_ITR_DVIOLBARVAR, 439
 MSK_DINF_SOL_ITR_DUAL_OBJ, 438
 MSK_DINF_SOL_ITG_PVIOLVAR, 438
 MSK_DINF_SOL_ITG_PVIOLITG, 438
 MSK_DINF_SOL_ITG_PVIOLCONES, 438
 MSK_DINF_SOL_ITG_PVIOLCON, 438
 MSK_DINF_SOL_ITG_PVIOLBARVAR, 438
 MSK_DINF_SOL_ITG_PRIMAL_OBJ, 438
 MSK_DINF_SOL_ITG_NRM_XX, 438
 MSK_DINF_SOL_ITG_NRM_XC, 438
 MSK_DINF_SOL_ITG_NRM_BARX, 438
 MSK_DINF_SOL_BAS_PVIOLVAR, 438
 MSK_DINF_SOL_BAS_PVIOLCON, 438
 MSK_DINF_SOL_BAS_PRIMAL_OBJ, 438
 MSK_DINF_SOL_BAS_NRM_Y, 438
 MSK_DINF_SOL_BAS_NRM_XX, 438
 MSK_DINF_SOL_BAS_NRM_XC, 438
 MSK_DINF_SOL_BAS_NRM_SUX, 438
 MSK_DINF_SOL_BAS_NRM_SUC, 438
 MSK_DINF_SOL_BAS_NRM_SLX, 438
 MSK_DINF_SOL_BAS_NRM_SLC, 438
 MSK_DINF_SOL_BAS_NRM_BARX, 437
 MSK_DINF_SOL_BAS_DVIOLVAR, 437
 MSK_DINF_SOL_BAS_DVIOLCON, 437
 MSK_DINF_SOL_BAS_DUAL_OBJ, 437
 MSK_DINF_SIM_TIME, 437
 MSK_DINF_SIM_PRIMAL_TIME, 437
 MSK_DINF_SIM_OBJ, 437
 MSK_DINF_SIM_FEAS, 437
 MSK_DINF_SIM_DUAL_TIME, 437
 MSK_DINF_RD_TIME, 437
 MSK_DINF_QCQO_REFORMULATE_WORST_CHOLESKY_DIAG_SCALING, 437
 MSK_DINF_QCQO_REFORMULATE_WORST_CHOLESKY_COLUMN_SCALING, 437
 MSK_DINF_QCQO_REFORMULATE_TIME, 437
 MSK_DINF_QCQO_REFORMULATE_MAX_PERTURBATION, 437
 MSK_DINF_PRIMAL_REPAIR_PENALTY_OBJ, 437
 MSK_DINF_PRESOLVE_TIME, 437
 MSK_DINF_PRESOLVE_LINDEP_TIME, 437
 MSK_DINF_PRESOLVE_ELI_TIME, 437
 MSK_DINF_OPTIMIZER_TIME, 437
 MSK_DINF_MIO_USER_OBJ_CUT, 437
 MSK_DINF_MIO_TIME, 437
 MSK_DINF_MIO_ROOT_PRESOLVE_TIME, 437
 MSK_DINF_MIO_ROOT_OPTIMIZER_TIME, 437
 MSK_DINF_MIO_ROOT_CUTGEN_TIME, 437
 MSK_DINF_MIO_PROBING_TIME, 436

MSK_DINF_MIO_OBJ_REL_GAP, 436
 MSK_DINF_MIO_OBJ_INT, 436
 MSK_DINF_MIO_OBJ_BOUND, 436
 MSK_DINF_MIO_OBJ_ABS_GAP, 436
 MSK_DINF_MIO_KNAPSACK_COVER_SEPARATION_TIME, 436
 MSK_DINF_MIO_IMPLIED_BOUND_TIME, 436
 MSK_DINF_MIO_GMI_SEPARATION_TIME, 436
 MSK_DINF_MIO_DUAL_BOUND_AFTER_PREOLVE, 436
 MSK_DINF_MIO_CONSTRUCT_SOLUTION_OBJ, 436
 MSK_DINF_MIO_CMIR_SEPARATION_TIME, 436
 MSK_DINF_MIO_CLIQUE_SEPARATION_TIME, 436
 MSK_DINF_INTPNT_TIME, 436
 MSK_DINF_INTPNT_PRIMAL_OBJ, 436
 MSK_DINF_INTPNT_PRIMAL_FEAS, 436
 MSK_DINF_INTPNT_ORDER_TIME, 436
 MSK_DINF_INTPNT_OPT_STATUS, 435
 MSK_DINF_INTPNT_FACTOR_NUM_FLOPS, 435
 MSK_DINF_INTPNT_DUAL_OBJ, 435
 MSK_DINF_INTPNT_DUAL_FEAS, 435
 MSK_DINF_BI_TIME, 435
 MSK_DINF_BI_PRIMAL_TIME, 435
 MSK_DINF_BI_DUAL_TIME, 435
 MSK_DINF_BI_CLEAN_TIME, 435
 MSK_DINF_BI_CLEAN_PRIMAL_TIME, 435
 MSK_DINF_BI_CLEAN_DUAL_TIME, 435
 MSKdparame, 369
 MSKfeaturee, 439
 MSK_FEATURE_PTS, 439
 MSK_FEATURE_PTON, 440
 MSKiinfiteme, 440
 MSK_IINF_STO_NUM_A_REALLOC, 444
 MSK_IINF_SOL_ITR_SOLSTA, 444
 MSK_IINF_SOL_ITR_PROSTA, 444
 MSK_IINF_SOL_ITG_SOLSTA, 444
 MSK_IINF_SOL_ITG_PROSTA, 444
 MSK_IINF_SOL_BAS_SOLSTA, 444
 MSK_IINF_SOL_BAS_PROSTA, 444
 MSK_IINF_SIM_SOLVE_DUAL, 444
 MSK_IINF_SIM_PRIMAL_ITER, 444
 MSK_IINF_SIM_PRIMAL_INF_ITER, 444
 MSK_IINF_SIM_PRIMAL_HOTSTART_LU, 444
 MSK_IINF_SIM_PRIMAL_HOTSTART, 444
 MSK_IINF_SIM_PRIMAL_DEG_ITER, 444
 MSK_IINF_SIM_NUMVAR, 444
 MSK_IINF_SIM_NUMCON, 444
 MSK_IINF_SIM_DUAL_ITER, 444
 MSK_IINF_SIM_DUAL_INF_ITER, 444
 MSK_IINF_SIM_DUAL_HOTSTART_LU, 444
 MSK_IINF_SIM_DUAL_HOTSTART, 444
 MSK_IINF_SIM_DUAL_DEG_ITER, 444
 MSK_IINF_RD_PROTYPE, 444
 MSK_IINF_RD_NUMVAR, 444
 MSK_IINF_RD_NUMQ, 444
 MSK_IINF_RD_NUMINTVAR, 444
 MSK_IINF_RD_NUMCONE, 443
 MSK_IINF_RD_NUMCON, 443
 MSK_IINF_RD_NUMBARVAR, 443
 MSK_IINF_PURIFY_PRIMAL_SUCCESS, 443
 MSK_IINF_PURIFY_DUAL_SUCCESS, 443
 MSK_IINF_OPTIMIZE_RESPONSE, 443
 MSK_IINF_OPT_NUMVAR, 443
 MSK_IINF_OPT_NUMCON, 443
 MSK_IINF_MIO_USER_OBJ_CUT, 443
 MSK_IINF_MIO_TOTAL_NUM_CUTS, 443
 MSK_IINF_MIO_RELGAP_SATISFIED, 443
 MSK_IINF_MIO_PREOLVED_NUMVAR, 443
 MSK_IINF_MIO_PREOLVED_NUMRQCONES, 443
 MSK_IINF_MIO_PREOLVED_NUMQCONES, 443
 MSK_IINF_MIO_PREOLVED_NUMPPOWCONES, 443
 MSK_IINF_MIO_PREOLVED_NUMPEXPONES, 443
 MSK_IINF_MIO_PREOLVED_NUMINTCONEVAR, 443
 MSK_IINF_MIO_PREOLVED_NUMINT, 443
 MSK_IINF_MIO_PREOLVED_NUMDPOWCONES, 443
 MSK_IINF_MIO_PREOLVED_NUMDEXPCONES, 443
 MSK_IINF_MIO_PREOLVED_NUMCONTCONEVAR, 443
 MSK_IINF_MIO_PREOLVED_NUMCONT, 443
 MSK_IINF_MIO_PREOLVED_NUMCONEVAR, 443
 MSK_IINF_MIO_PREOLVED_NUMCONE, 443
 MSK_IINF_MIO_PREOLVED_NUMCON, 442
 MSK_IINF_MIO_PREOLVED_NUMBINCONEVAR, 442
 MSK_IINF_MIO_PREOLVED_NUMBIN, 442
 MSK_IINF_MIO_OBJ_BOUND_DEFINED, 442
 MSK_IINF_MIO_NUMVAR, 442
 MSK_IINF_MIO_NUMRQCONES, 442
 MSK_IINF_MIO_NUMQCONES, 442
 MSK_IINF_MIO_NUMPPOWCONES, 442
 MSK_IINF_MIO_NUMPEXPONES, 442
 MSK_IINF_MIO_NUMINTCONEVAR, 442
 MSK_IINF_MIO_NUMINT, 442
 MSK_IINF_MIO_NUMDPOWCONES, 442
 MSK_IINF_MIO_NUMDEXPCONES, 442
 MSK_IINF_MIO_NUMCONTCONEVAR, 442
 MSK_IINF_MIO_NUMCONT, 442
 MSK_IINF_MIO_NUMCONEVAR, 442
 MSK_IINF_MIO_NUMCONE, 442
 MSK_IINF_MIO_NUMCON, 442
 MSK_IINF_MIO_NUMBINCONEVAR, 442
 MSK_IINF_MIO_NUMBIN, 442
 MSK_IINF_MIO_NUM_REPEATED_PREOLVE, 442
 MSK_IINF_MIO_NUM_RELAX, 442
 MSK_IINF_MIO_NUM_KNAPSACK_COVER_CUTS, 442
 MSK_IINF_MIO_NUM_INT_SOLUTIONS, 442
 MSK_IINF_MIO_NUM_IMPLIED_BOUND_CUTS, 441
 MSK_IINF_MIO_NUM_GOMORY_CUTS, 441
 MSK_IINF_MIO_NUM_CMIR_CUTS, 441
 MSK_IINF_MIO_NUM_CLIQUE_CUTS, 441
 MSK_IINF_MIO_NUM_BRANCH, 441
 MSK_IINF_MIO_NUM_ACTIVE_NODES, 441
 MSK_IINF_MIO_NODE_DEPTH, 441
 MSK_IINF_MIO_CONSTRUCT_SOLUTION, 441
 MSK_IINF_MIO_CLIQUE_TABLE_SIZE, 441
 MSK_IINF_MIO_ABSGAP_SATISFIED, 441
 MSK_IINF_INTPNT_SOLVE_DUAL, 441
 MSK_IINF_INTPNT_NUM_THREADS, 441
 MSK_IINF_INTPNT_ITER, 441

MSK_IINF_INTPNT_FACTOR_DIM_DENSE, 441
 MSK_IINF_ANA_PRO_NUM_VAR_UP, 441
 MSK_IINF_ANA_PRO_NUM_VAR_RA, 441
 MSK_IINF_ANA_PRO_NUM_VAR_LO, 441
 MSK_IINF_ANA_PRO_NUM_VAR_INT, 441
 MSK_IINF_ANA_PRO_NUM_VAR_FR, 441
 MSK_IINF_ANA_PRO_NUM_VAR_EQ, 441
 MSK_IINF_ANA_PRO_NUM_VAR_CONT, 441
 MSK_IINF_ANA_PRO_NUM_VAR_BIN, 441
 MSK_IINF_ANA_PRO_NUM_VAR, 440
 MSK_IINF_ANA_PRO_NUM_CON_UP, 440
 MSK_IINF_ANA_PRO_NUM_CON_RA, 440
 MSK_IINF_ANA_PRO_NUM_CON_LO, 440
 MSK_IINF_ANA_PRO_NUM_CON_FR, 440
 MSK_IINF_ANA_PRO_NUM_CON_EQ, 440
 MSK_IINF_ANA_PRO_NUM_CON, 440
 MSKinfypee, 445
 MSK_INF_LINT_TYPE, 445
 MSK_INF_INT_TYPE, 445
 MSK_INF_DOU_TYPE, 445
 MSKintpntthotstarte, 429
 MSK_INTPNT_HOTSTART_PRIMAL_DUAL, 429
 MSK_INTPNT_HOTSTART_PRIMAL, 429
 MSK_INTPNT_HOTSTART_NONE, 429
 MSK_INTPNT_HOTSTART_DUAL, 429
 MSKiomodee, 445
 MSK_IOMODE_WRITE, 445
 MSK_IOMODE_READWRITE, 445
 MSK_IOMODE_READ, 445
 MSKiparame, 378
 MSKliinfiteme, 440
 MSK_LIINF_RD_NUMQNZ, 440
 MSK_LIINF_RD_NUMANZ, 440
 MSK_LIINF_MIO_SIMPLEX_ITER, 440
 MSK_LIINF_MIO_PRE SOLVED_ANZ, 440
 MSK_LIINF_MIO_INTPNT_ITER, 440
 MSK_LIINF_MIO_ANZ, 440
 MSK_LIINF_INTPNT_FACTOR_NUM_NZ, 440
 MSK_LIINF_BI_PRIMAL_ITER, 440
 MSK_LIINF_BI_DUAL_ITER, 440
 MSK_LIINF_BI_CLEAN_PRIMAL_ITER, 440
 MSK_LIINF_BI_CLEAN_PRIMAL_DEG_ITER, 440
 MSK_LIINF_BI_CLEAN_DUAL_ITER, 440
 MSK_LIINF_BI_CLEAN_DUAL_DEG_ITER, 440
 MSKmarke, 428
 MSK_MARK_UP, 428
 MSK_MARK_LO, 428
 MSKmiocontsolypee, 445
 MSK_MIO_CONT_SOL_ROOT, 445
 MSK_MIO_CONT_SOL_NONE, 445
 MSK_MIO_CONT_SOL_ITG_REL, 445
 MSK_MIO_CONT_SOL_ITG, 445
 MSKmiomodee, 446
 MSK_MIO_MODE_SATISFIED, 446
 MSK_MIO_MODE_IGNORED, 446
 MSKmionodeselypee, 446
 MSK_MIO_NODE_SELECTION_PSEUDO, 446
 MSK_MIO_NODE_SELECTION_FREE, 446
 MSK_MIO_NODE_SELECTION_FIRST, 446
 MSK_MIO_NODE_SELECTION_BEST, 446
 MSKmpsformate, 446
 MSK_MPS_FORMAT_STRICT, 446
 MSK_MPS_FORMAT_RELAXED, 446
 MSK_MPS_FORMAT_FREE, 446
 MSK_MPS_FORMAT_CPLEX, 446
 MSKnametypee, 434
 MSK_NAME_TYPE_MPS, 434
 MSK_NAME_TYPE_LP, 434
 MSK_NAME_TYPE_GEN, 434
 MSKobjsensee, 446
 MSK_OBJECTIVE_SENSE_MINIMIZE, 446
 MSK_OBJECTIVE_SENSE_MAXIMIZE, 446
 MSKonoffkeye, 446
 MSK_ON, 446
 MSK_OFF, 446
 MSKoptimizertypee, 446
 MSK_OPTIMIZER_PRIMAL_SIMPLEX, 447
 MSK_OPTIMIZER_MIXED_INT, 447
 MSK_OPTIMIZER_INTPNT, 446
 MSK_OPTIMIZER_FREE_SIMPLEX, 446
 MSK_OPTIMIZER_FREE, 446
 MSK_OPTIMIZER_DUAL_SIMPLEX, 446
 MSK_OPTIMIZER_CONIC, 446
 MSKorderingtypee, 447
 MSK_ORDER_METHOD_TRY_GRAPHPAR, 447
 MSK_ORDER_METHOD_NONE, 447
 MSK_ORDER_METHOD_FREE, 447
 MSK_ORDER_METHOD_FORCE_GRAPHPAR, 447
 MSK_ORDER_METHOD_EXPERIMENTAL, 447
 MSK_ORDER_METHOD_APPMINLOC, 447
 MSKparametertypee, 447
 MSK_PAR_STR_TYPE, 447
 MSK_PAR_INVALID_TYPE, 447
 MSK_PAR_INT_TYPE, 447
 MSK_PAR_DOU_TYPE, 447
 MSKpresolvemodee, 447
 MSK_PRE SOLVE_MODE_ON, 447
 MSK_PRE SOLVE_MODE_OFF, 447
 MSK_PRE SOLVE_MODE_FREE, 447
 MSKproblemiteme, 447
 MSK_PI_VAR, 447
 MSK_PI_CONE, 447
 MSK_PI_CON, 447
 MSKproblemtypee, 447
 MSK_PROBTYPE_QO, 447
 MSK_PROBTYPE_QCQO, 448
 MSK_PROBTYPE_MIXED, 448
 MSK_PROBTYPE_LO, 447
 MSK_PROBTYPE_CONIC, 448
 MSKprostae, 448
 MSK_PRO_STA_UNKNOWN, 448
 MSK_PRO_STA_PRIM_INFEAS_OR_UNBOUNDED, 448
 MSK_PRO_STA_PRIM_INFEAS, 448
 MSK_PRO_STA_PRIM_FEAS, 448
 MSK_PRO_STA_PRIM_AND_DUAL_INFEAS, 448
 MSK_PRO_STA_PRIM_AND_DUAL_FEAS, 448

MSK_PRO_STA_ILL_POSED, 448
 MSK_PRO_STA_DUAL_INFEAS, 448
 MSK_PRO_STA_DUAL_FEAS, 448
 MSKpurifye, 429
 MSK_PURIFY_PRIMAL_DUAL, 429
 MSK_PURIFY_PRIMAL, 429
 MSK_PURIFY_NONE, 429
 MSK_PURIFY_DUAL, 429
 MSK_PURIFY_AUTO, 429
 MSKrescodee, 409
 MSKrescodetypee, 448
 MSK_RESPONSE_WRN, 448
 MSK_RESPONSE_UNK, 448
 MSK_RESPONSE_TRM, 448
 MSK_RESPONSE_OK, 448
 MSK_RESPONSE_ERR, 448
 MSKscalingmethode, 449
 MSK_SCALING_METHOD_POW2, 449
 MSK_SCALING_METHOD_FREE, 449
 MSKscalingtypee, 448
 MSK_SCALING_NONE, 449
 MSK_SCALING_MODERATE, 449
 MSK_SCALING_FREE, 448
 MSK_SCALING_AGGRESSIVE, 449
 MSKscopre, 434
 MSK_OPR_SQRT, 434
 MSK_OPR_POW, 434
 MSK_OPR_LOG, 434
 MSK_OPR_EXP, 434
 MSK_OPR_ENT, 434
 MSKsensitivitytypee, 449
 MSK_SENSITIVITY_TYPE_BASIS, 449
 MSKsimdegene, 428
 MSK_SIM_DEGEN_NONE, 428
 MSK_SIM_DEGEN_MODERATE, 428
 MSK_SIM_DEGEN_MINIMUM, 428
 MSK_SIM_DEGEN_FREE, 428
 MSK_SIM_DEGEN_AGGRESSIVE, 428
 MSKsimdupvece, 428
 MSK_SIM_EXPLOIT_DUPVEC_ON, 428
 MSK_SIM_EXPLOIT_DUPVEC_OFF, 429
 MSK_SIM_EXPLOIT_DUPVEC_FREE, 429
 MSKsimhotstarte, 429
 MSK_SIM_HOTSTART_STATUS_KEYS, 429
 MSK_SIM_HOTSTART_NONE, 429
 MSK_SIM_HOTSTART_FREE, 429
 MSKsimreforme, 428
 MSK_SIM_REFORMULATION_ON, 428
 MSK_SIM_REFORMULATION_OFF, 428
 MSK_SIM_REFORMULATION_FREE, 428
 MSK_SIM_REFORMULATION_AGGRESSIVE, 428
 MSKsimselftypee, 449
 MSK_SIM_SELECTION_SE, 449
 MSK_SIM_SELECTION_PARTIAL, 449
 MSK_SIM_SELECTION_FULL, 449
 MSK_SIM_SELECTION_FREE, 449
 MSK_SIM_SELECTION_DEVEX, 449
 MSK_SIM_SELECTION_ASE, 449
 MSKsoliteme, 449
 MSK_SOL_ITEM_Y, 449
 MSK_SOL_ITEM_XX, 449
 MSK_SOL_ITEM_XC, 449
 MSK_SOL_ITEM_SUX, 449
 MSK_SOL_ITEM_SUC, 449
 MSK_SOL_ITEM_SNX, 449
 MSK_SOL_ITEM_SLX, 449
 MSK_SOL_ITEM_SLC, 449
 MSKsolstae, 450
 MSK_SOL_STA_UNKNOWN, 450
 MSK_SOL_STA_PRIM_INFEAS_CER, 450
 MSK_SOL_STA_PRIM_ILLPOSED_CER, 450
 MSK_SOL_STA_PRIM_FEAS, 450
 MSK_SOL_STA_PRIM_AND_DUAL_FEAS, 450
 MSK_SOL_STA_OPTIMAL, 450
 MSK_SOL_STA_INTEGER_OPTIMAL, 450
 MSK_SOL_STA_DUAL_INFEAS_CER, 450
 MSK_SOL_STA_DUAL_ILLPOSED_CER, 450
 MSK_SOL_STA_DUAL_FEAS, 450
 MSKsoltypee, 450
 MSK_SOL_ITR, 450
 MSK_SOL_ITG, 450
 MSK_SOL_BAS, 450
 MSKsolveforme, 450
 MSK_SOLVE_PRIMAL, 450
 MSK_SOLVE_FREE, 450
 MSK_SOLVE_DUAL, 450
 MSKsparame, 406
 MSKstakeye, 450
 MSK_SK_UPR, 450
 MSK_SK_UNK, 450
 MSK_SK_SUPBAS, 450
 MSK_SK_LOW, 450
 MSK_SK_INF, 451
 MSK_SK_FIX, 451
 MSK_SK_BAS, 450
 MSKstartpointtypee, 451
 MSK_STARTING_POINT_SATISFY_BOUNDS, 451
 MSK_STARTING_POINT_GUESS, 451
 MSK_STARTING_POINT_FREE, 451
 MSK_STARTING_POINT_CONSTANT, 451
 MSKstreamtypee, 451
 MSK_STREAM_WRN, 451
 MSK_STREAM_MSG, 451
 MSK_STREAM_LOG, 451
 MSK_STREAM_ERR, 451
 MSKsymmattypee, 435
 MSK_SYMMAT_TYPE_SPARSE, 435
 MSKtransposee, 428
 MSK_TRANSPOSE_YES, 428
 MSK_TRANSPOSE_NO, 428
 MSKuploe, 428
 MSK_UPLO_UP, 428
 MSK_UPLO_LO, 428
 MSKvaluee, 451
 MSK_MAX_STR_LEN, 451
 MSK_LICENSE_BUFFER_LENGTH, 451

MSKvariabletypee, 451
 MSK_VAR_TYPE_INT, 451
 MSK_VAR_TYPE_CONT, 451
 MSKxmlwriteroutputtypee, 448
 MSK_WRITE_XML_MODE_ROW, 448
 MSK_WRITE_XML_MODE_COL, 448

Functions

MSK_analyzenames, 213
 MSK_analyzeproblem, 213
 MSK_analyzesolution, 213
 MSK_appendbarvars, 214
 MSK_appendcone, 214
 MSK_appendconeseq, 215
 MSK_appendconesseq, 216
 MSK_appendcons, 216
 MSK_appendsparsesymmat, 216
 MSK_appendsparsesymmatlist, 217
 MSK_appendvars, 218
 MSK_asyncgetresult, 218
 MSK_asyncoptimize, 219
 MSK_asyncpoll, 219
 MSK_asyncstop, 219
 MSK_axpy, 220
 MSK_basiscond, 220
 MSK_bktostr, 221
 MSK_callbackcodetostr, 221
 MSK_calloclbgen, 221
 MSK_calloclbgtask, 221
 MSK_calloclenv, 222
 MSK_calloctask, 222
 MSK_checkinall, 222
 MSK_checkinlicense, 223
 MSK_checkmemenv, 223
 MSK_checkmentask, 223
 MSK_checkoutlicense, 224
 MSK_checkversion, 224
 MSK_chgconbound, 224
 MSK_chgvarbound, 225
 MSK_clonetask, 225
 MSK_commitchanges, 226
 MSK_computesparsescholesky, 226
 MSK_conetypetostr, 227
 MSK_deleteenv, 227
 MSK_deletesolution, 228
 MSK_deletetask, 228
 MSK_dot, 228
 MSK_dualsensitivity, 229
 MSK_echoenv, 229
 MSK_echointro, 229
 MSK_echotask, 230
 MSK_freedbgen, 230
 MSK_freedbgtask, 230
 MSK_freeenv, 231
 MSK_freetask, 231
 MSK_gemm, 231
 MSK_genv, 232
 MSK_generateconenames, 233

MSK_generateconenames, 233
 MSK_generatevarnames, 234
 MSK_getacol, 234
 MSK_getacolnumnz, 234
 MSK_getacolslice, 235
 MSK_getacolslice64, 235
 MSK_getacolslicenumnz, 236
 MSK_getacolslicenumnz64, 236
 MSK_getacolslicetrip, 237
 MSK_getaij, 237
 MSK_getapiecennumnz, 237
 MSK_getarow, 238
 MSK_getarownumnz, 238
 MSK_getarowslice, 239
 MSK_getarowslice64, 239
 MSK_getarowslicenumnz, 240
 MSK_getarowslicenumnz64, 240
 MSK_getarowslicetrip, 240
 MSK_getatruncatetol, 241
 MSK_getbarablocktriplet, 241
 MSK_getbaraidx, 242
 MSK_getbaraidxij, 242
 MSK_getbaraidxinfo, 243
 MSK_getbarasparsity, 243
 MSK_getbarcbblocktriplet, 244
 MSK_getbarcidx, 244
 MSK_getbarcidxinfo, 244
 MSK_getbarcidxj, 245
 MSK_getbarcsparsity, 245
 MSK_getbarsj, 245
 MSK_getbarsslice, 246
 MSK_getbarvarname, 246
 MSK_getbarvarnameindex, 247
 MSK_getbarvarnamelen, 247
 MSK_getbarxj, 247
 MSK_getbarxslice, 248
 MSK_getbuildinfo, 248
 MSK_getc, 248
 MSK_getcallbackfunc, 249
 MSK_getcfix, 249
 MSK_getcj, 249
 MSK_getclist, 249
 MSK_getcodedesc, 250
 MSK_getconbound, 250
 MSK_getconboundslice, 250
 MSK_getcone, 251
 MSK_getconeinfo, 251
 MSK_getconename, 252
 MSK_getconenameindex, 252
 MSK_getconenamelen, 252
 MSK_getconname, 253
 MSK_getconnameindex, 253
 MSK_getconnamelen, 253
 MSK_getcslice, 254
 MSK_getdimbarvarj, 254
 MSK_getdouinf, 254
 MSK_getdoupam, 255
 MSK_getdualobj, 255

MSK_getdualsolutionnorms, 255
 MSK_getdviolbarvar, 256
 MSK_getdviolcon, 256
 MSK_getdviolcones, 257
 MSK_getdviolvar, 257
 MSK_getenv, 258
 MSK_getinfeasiblesubproblem, 258
 MSK_getinfindex, 258
 MSK_getinfmax, 259
 MSK_getinfname, 259
 MSK_getintinf, 259
 MSK_getintparam, 260
 MSK_getlasterror, 260
 MSK_getlasterror64, 260
 MSK_getlenbarvarj, 261
 MSK_getlintinf, 261
 MSK_getmaxnamelen, 261
 MSK_getmaxnumanz, 262
 MSK_getmaxnumanz64, 262
 MSK_getmaxnumbarvar, 262
 MSK_getmaxnumcon, 263
 MSK_getmaxnumcone, 263
 MSK_getmaxnumqnz, 263
 MSK_getmaxnumqnz64, 263
 MSK_getmaxnumvar, 264
 MSK_getmemusagetask, 264
 MSK_getnadouinf, 264
 MSK_getnadoupam, 265
 MSK_getnaintinf, 265
 MSK_getnaintparam, 265
 MSK_getnastrparam, 265
 MSK_getnastrparamal, 266
 MSK_getnumanz, 266
 MSK_getnumanz64, 266
 MSK_getnumbarablocktriplets, 267
 MSK_getnumbaranz, 267
 MSK_getnumbarcblocktriplets, 267
 MSK_getnumbarcnz, 268
 MSK_getnumbarvar, 268
 MSK_getnumcon, 268
 MSK_getnumcone, 268
 MSK_getnumconemem, 269
 MSK_getnumintvar, 269
 MSK_getnumparam, 269
 MSK_getnumqconknz, 269
 MSK_getnumqconknz64, 270
 MSK_getnumqobjnz, 270
 MSK_getnumqobjnz64, 270
 MSK_getnumsymmat, 270
 MSK_getnumvar, 271
 MSK_getobjname, 271
 MSK_getobjnamelen, 271
 MSK_getobjsense, 272
 MSK_getparammax, 272
 MSK_getparamname, 272
 MSK_getprimalobj, 272
 MSK_getprimalsolutionnorms, 273
 MSK_getprobtype, 273
 MSK_getprosta, 273
 MSK_getpviolbarvar, 274
 MSK_getpviolcon, 274
 MSK_getpviolcones, 275
 MSK_getpviolvar, 275
 MSK_getqconk, 276
 MSK_getqconk64, 276
 MSK_getqobj, 277
 MSK_getqobj64, 277
 MSK_getqobjij, 278
 MSK_getreducedcosts, 278
 MSK_getresponseclass, 279
 MSK_getskc, 279
 MSK_getskcslice, 279
 MSK_getskn, 279
 MSK_getskx, 280
 MSK_getskxslice, 280
 MSK_getslc, 280
 MSK_getslcslice, 281
 MSK_getslx, 281
 MSK_getslxslice, 281
 MSK_getsnx, 282
 MSK_getsnxslice, 282
 MSK_getsolsta, 282
 MSK_getsolution, 283
 MSK_getsolutioninfo, 284
 MSK_getsolutionslice, 285
 MSK_getsparsesymmat, 286
 MSK_getstrparam, 286
 MSK_getstrparamal, 286
 MSK_getstrparamlen, 287
 MSK_getsuc, 287
 MSK_getsucslice, 287
 MSK_getsux, 288
 MSK_getsuxslice, 288
 MSK_getsymbcon, 288
 MSK_getsymbcondim, 289
 MSK_getsymmatinfo, 289
 MSK_gettaskname, 290
 MSK_gettasknamelen, 290
 MSK_getvarbound, 290
 MSK_getvarboundslice, 291
 MSK_getvarname, 291
 MSK_getvarnameindex, 291
 MSK_getvarnamelen, 292
 MSK_getvartype, 292
 MSK_getvartypelist, 292
 MSK_getversion, 293
 MSK_getxc, 293
 MSK_getxcslice, 293
 MSK_getxx, 294
 MSK_getxxslice, 294
 MSK_gety, 294
 MSK_getyslice, 294
 MSK_initbasissolve, 295
 MSK_inputdata, 295
 MSK_inputdata64, 296
 MSK_iparvaltosymnam, 297

MSK_isdoupname, 297
 MSK_isinfinity, 298
 MSK_isintparname, 298
 MSK_isstrparname, 298
 MSK_licensecleanup, 298
 MSK_linkfiletoenvstream, 299
 MSK_linkfiletotaskstream, 299
 MSK_linkfunctoenvstream, 299
 MSK_linkfunctotaskstream, 300
 MSK_makeemptytask, 300
 MSK_makeenv, 300
 MSK_makeenvalloc, 301
 MSK_maketask, 301
 MSK_onesolutionsummary, 301
 MSK_optimize, 302
 MSK_optimizermt, 302
 MSK_optimizersummary, 303
 MSK_optimizetrm, 303
 MSK_potrf, 303
 MSK_primalrepair, 303
 MSK_primalsensitivity, 304
 MSK_printparam, 305
 MSK_probtypetostr, 306
 MSK_prostatostr, 306
 MSK_putacol, 306
 MSK_putacollist, 307
 MSK_putacollist64, 307
 MSK_putacolslice, 308
 MSK_putacolslice64, 308
 MSK_putaij, 309
 MSK_putaijlist, 309
 MSK_putaijlist64, 310
 MSK_putarow, 310
 MSK_putarowlist, 310
 MSK_putarowlist64, 311
 MSK_putarowslice, 311
 MSK_putarowslice64, 312
 MSK_putatruncatetol, 312
 MSK_putbarablocktriplet, 313
 MSK_putbaraij, 313
 MSK_putbaraijlist, 314
 MSK_putbararowlist, 314
 MSK_putbarcblocktriplet, 315
 MSK_putbarcj, 315
 MSK_putbarsj, 316
 MSK_putbarvarname, 316
 MSK_putbarxj, 316
 MSK_putcallbackfunc, 317
 MSK_putcfix, 317
 MSK_putcj, 317
 MSK_putclist, 318
 MSK_putconbound, 318
 MSK_putconboundlist, 318
 MSK_putconboundlistconst, 319
 MSK_putconboundslice, 319
 MSK_putconboundsliceconst, 320
 MSK_putcone, 320
 MSK_putconename, 320
 MSK_putconname, 321
 MSK_putconsolutioni, 321
 MSK_putcslice, 321
 MSK_putdoupparam, 322
 MSK_putexitfunc, 322
 MSK_putintparam, 322
 MSK_putlicensecode, 323
 MSK_putlicensedebug, 323
 MSK_putlicensepath, 323
 MSK_putlicensewait, 324
 MSK_putmaxnumanz, 324
 MSK_putmaxnumbarvar, 324
 MSK_putmaxnumcon, 325
 MSK_putmaxnumcone, 325
 MSK_putmaxnumqnz, 325
 MSK_putmaxnumvar, 326
 MSK_putnadoupparam, 326
 MSK_putnaintparam, 326
 MSK_putnastrparam, 327
 MSK_putobjname, 327
 MSK_putobjsense, 327
 MSK_putparam, 327
 MSK_putqcon, 328
 MSK_putqconk, 329
 MSK_putqobj, 329
 MSK_putqobjij, 330
 MSK_putresponsefunc, 330
 MSK_putskc, 330
 MSK_putskcslice, 331
 MSK_putskx, 331
 MSK_putskxslice, 331
 MSK_putslc, 332
 MSK_putslcslice, 332
 MSK_putslx, 332
 MSK_putslxslice, 333
 MSK_putsnx, 333
 MSK_putsnxslice, 333
 MSK_putsolution, 334
 MSK_putsolutionyi, 334
 MSK_putstrparam, 335
 MSK_putsuc, 335
 MSK_putsucslice, 335
 MSK_putsux, 336
 MSK_putsuxslice, 336
 MSK_puttaskname, 336
 MSK_putvarbound, 336
 MSK_putvarboundlist, 337
 MSK_putvarboundlistconst, 337
 MSK_putvarboundslice, 338
 MSK_putvarboundsliceconst, 338
 MSK_putvarname, 338
 MSK_putvarsolutionj, 339
 MSK_putvartype, 339
 MSK_putvartypelist, 340
 MSK_putxc, 340
 MSK_putxcslice, 340
 MSK_putxx, 341
 MSK_putxxslice, 341

- MSK_puty, 341
- MSK_putyslice, 342
- MSK_readdata, 342
- MSK_readdataautoformat, 342
- MSK_readdataformat, 342
- MSK_readjsonstring, 343
- MSK_readlpstring, 343
- MSK_readopfstring, 343
- MSK_readparamfile, 344
- MSK_readptfstring, 344
- MSK_readsolution, 344
- MSK_readsummary, 344
- MSK_readtask, 345
- MSK_removebarvars, 345
- MSK_removecones, 345
- MSK_removecons, 346
- MSK_removevars, 346
- MSK_resize task, 346
- MSK_sensitivityreport, 347
- MSK_setdefaults, 347
- MSK_setupthreads, 347
- MSK_sktostr, 348
- MSK_solstatostr, 348
- MSK_solutiondef, 348
- MSK_solutionsummary, 348
- MSK_solvewithbasis, 349
- MSK_sparsetriangularsolvedense, 350
- MSK_strdupbgtask, 350
- MSK_strduptask, 351
- MSK_strtoconetype, 351
- MSK_strtosk, 351
- MSK_syeig, 351
- MSK_syevd, 352
- MSK_symnamtovalue, 352
- MSK_syrk, 353
- MSK_toconic, 353
- MSK_unlinkfuncfromenvstream, 354
- MSK_unlinkfuncfromtaskstream, 354
- MSK_updatesolutioninfo, 354
- MSK_utf8towchar, 355
- MSK_wchartoutf8, 355
- MSK_whichparam, 355
- MSK_writedata, 356
- MSK_writejsonsol, 356
- MSK_writeparamfile, 356
- MSK_writesolution, 357
- MSK_writetask, 357
- MSKcallbackfunc, 452
- MSKcallocfunc, 452
- MSKexitfunc, 453
- MSKfreefunc, 453
- MSKhreadfunc, 453
- MSKhwritefunc, 454
- MSKmallocfunc, 454
- MSKreallocfunc, 454
- MSKresponsefunc, 454
- MSKstreamfunc, 455

Parameters

- Double parameters, 369
- MSK_DPAR_ANA_SOL_INFEAS_TOL, 369
- MSK_DPAR_BASIS_REL_TOL_S, 369
- MSK_DPAR_BASIS_TOL_S, 369
- MSK_DPAR_BASIS_TOL_X, 369
- MSK_DPAR_CHECK_CONVEXITY_REL_TOL, 370
- MSK_DPAR_DATA_SYM_MAT_TOL, 370
- MSK_DPAR_DATA_SYM_MAT_TOL_HUGE, 370
- MSK_DPAR_DATA_SYM_MAT_TOL_LARGE, 370
- MSK_DPAR_DATA_TOL_AIJ_HUGE, 370
- MSK_DPAR_DATA_TOL_AIJ_LARGE, 370
- MSK_DPAR_DATA_TOL_BOUND_INF, 371
- MSK_DPAR_DATA_TOL_BOUND_WRN, 371
- MSK_DPAR_DATA_TOL_C_HUGE, 371
- MSK_DPAR_DATA_TOL_CJ_LARGE, 371
- MSK_DPAR_DATA_TOL_QIJ, 371
- MSK_DPAR_DATA_TOL_X, 371
- MSK_DPAR_INTPNT_CO_TOL_DFEAS, 371
- MSK_DPAR_INTPNT_CO_TOL_INFEAS, 372
- MSK_DPAR_INTPNT_CO_TOL_MU_RED, 372
- MSK_DPAR_INTPNT_CO_TOL_NEAR_REL, 372
- MSK_DPAR_INTPNT_CO_TOL_PFEAS, 372
- MSK_DPAR_INTPNT_CO_TOL_REL_GAP, 372
- MSK_DPAR_INTPNT_QO_TOL_DFEAS, 372
- MSK_DPAR_INTPNT_QO_TOL_INFEAS, 372
- MSK_DPAR_INTPNT_QO_TOL_MU_RED, 373
- MSK_DPAR_INTPNT_QO_TOL_NEAR_REL, 373
- MSK_DPAR_INTPNT_QO_TOL_PFEAS, 373
- MSK_DPAR_INTPNT_QO_TOL_REL_GAP, 373
- MSK_DPAR_INTPNT_TOL_DFEAS, 373
- MSK_DPAR_INTPNT_TOL_DSAFE, 373
- MSK_DPAR_INTPNT_TOL_INFEAS, 374
- MSK_DPAR_INTPNT_TOL_MU_RED, 374
- MSK_DPAR_INTPNT_TOL_PATH, 374
- MSK_DPAR_INTPNT_TOL_PFEAS, 374
- MSK_DPAR_INTPNT_TOL_PSAFE, 374
- MSK_DPAR_INTPNT_TOL_REL_GAP, 374
- MSK_DPAR_INTPNT_TOL_REL_STEP, 374
- MSK_DPAR_INTPNT_TOL_STEP_SIZE, 375
- MSK_DPAR_LOWER_OBJ_CUT, 375
- MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH, 375
- MSK_DPAR_MIO_MAX_TIME, 375
- MSK_DPAR_MIO_REL_GAP_CONST, 375
- MSK_DPAR_MIO_TOL_ABS_GAP, 375
- MSK_DPAR_MIO_TOL_ABS_RELAX_INT, 376
- MSK_DPAR_MIO_TOL_FEAS, 376
- MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT, 376
- MSK_DPAR_MIO_TOL_REL_GAP, 376
- MSK_DPAR_OPTIMIZER_MAX_TIME, 376
- MSK_DPAR_PRESOLVE_TOL_ABS_LINDEP, 376
- MSK_DPAR_PRESOLVE_TOL_AIJ, 376
- MSK_DPAR_PRESOLVE_TOL_REL_LINDEP, 377
- MSK_DPAR_PRESOLVE_TOL_S, 377
- MSK_DPAR_PRESOLVE_TOL_X, 377
- MSK_DPAR_QCQO_REFORMULATE_REL_DROP_TOL, 377
- MSK_DPAR_SEMIDEFINITE_TOL_APPROX, 377

MSK_DPAR_SIM_LU_TOL_REL_PIV, 377
 MSK_DPAR_SIMPLEX_ABS_TOL_PIV, 377
 MSK_DPAR_UPPER_OBJ_CUT, 378
 MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH, 378
 Integer parameters, 378
 MSK_IPAR_ANA_SOL_BASIS, 378
 MSK_IPAR_ANA_SOL_PRINT_VIOLATED, 378
 MSK_IPAR_AUTO_SORT_A_BEFORE_OPT, 378
 MSK_IPAR_AUTO_UPDATE_SOL_INFO, 378
 MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE, 379
 MSK_IPAR_BI_CLEAN_OPTIMIZER, 379
 MSK_IPAR_BI_IGNORE_MAX_ITER, 379
 MSK_IPAR_BI_IGNORE_NUM_ERROR, 379
 MSK_IPAR_BI_MAX_ITERATIONS, 379
 MSK_IPAR_CACHE_LICENSE, 380
 MSK_IPAR_CHECK_CONVEXITY, 380
 MSK_IPAR_COMPRESS_STATFILE, 380
 MSK_IPAR_INFEAS_GENERIC_NAMES, 380
 MSK_IPAR_INFEAS_PREFER_PRIMAL, 380
 MSK_IPAR_INFEAS_REPORT_AUTO, 380
 MSK_IPAR_INFEAS_REPORT_LEVEL, 380
 MSK_IPAR_INTPNT_BASIS, 381
 MSK_IPAR_INTPNT_DIFF_STEP, 381
 MSK_IPAR_INTPNT_HOTSTART, 381
 MSK_IPAR_INTPNT_MAX_ITERATIONS, 381
 MSK_IPAR_INTPNT_MAX_NUM_COR, 381
 MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS, 381
 MSK_IPAR_INTPNT_MULTI_THREAD, 382
 MSK_IPAR_INTPNT_OFF_COL_TRH, 382
 MSK_IPAR_INTPNT_ORDER_GP_NUM_SEEDS, 382
 MSK_IPAR_INTPNT_ORDER_METHOD, 382
 MSK_IPAR_INTPNT_PURIFY, 382
 MSK_IPAR_INTPNT_REGULARIZATION_USE, 382
 MSK_IPAR_INTPNT_SCALING, 383
 MSK_IPAR_INTPNT_SOLVE_FORM, 383
 MSK_IPAR_INTPNT_STARTING_POINT, 383
 MSK_IPAR_LICENSE_DEBUG, 383
 MSK_IPAR_LICENSE_PAUSE_TIME, 383
 MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS, 383
 MSK_IPAR_LICENSE_TRH_EXPIRY_WRN, 383
 MSK_IPAR_LICENSE_WAIT, 384
 MSK_IPAR_LOG, 384
 MSK_IPAR_LOG_ANA_PRO, 384
 MSK_IPAR_LOG_BI, 384
 MSK_IPAR_LOG_BI_FREQ, 384
 MSK_IPAR_LOG_CHECK_CONVEXITY, 384
 MSK_IPAR_LOG_CUT_SECOND_OPT, 385
 MSK_IPAR_LOG_EXPAND, 385
 MSK_IPAR_LOG_FEAS_REPAIR, 385
 MSK_IPAR_LOG_FILE, 385
 MSK_IPAR_LOG_INCLUDE_SUMMARY, 385
 MSK_IPAR_LOG_INFEAS_ANA, 385
 MSK_IPAR_LOG_INTPNT, 386
 MSK_IPAR_LOG_LOCAL_INFO, 386
 MSK_IPAR_LOG_MIO, 386
 MSK_IPAR_LOG_MIO_FREQ, 386
 MSK_IPAR_LOG_ORDER, 386
 MSK_IPAR_LOG_PREOLVE, 386
 MSK_IPAR_LOG_RESPONSE, 387
 MSK_IPAR_LOG_SENSITIVITY, 387
 MSK_IPAR_LOG_SENSITIVITY_OPT, 387
 MSK_IPAR_LOG_SIM, 387
 MSK_IPAR_LOG_SIM_FREQ, 387
 MSK_IPAR_LOG_SIM_MINOR, 387
 MSK_IPAR_LOG_STORAGE, 388
 MSK_IPAR_MAX_NUM_WARNINGS, 388
 MSK_IPAR_MIO_BRANCH_DIR, 388
 MSK_IPAR_MIO_CONIC_OUTER_APPROXIMATION, 388
 MSK_IPAR_MIO_CUT_CLIQUE, 388
 MSK_IPAR_MIO_CUT_CMIR, 388
 MSK_IPAR_MIO_CUT_GMI, 388
 MSK_IPAR_MIO_CUT_IMPLIED_BOUND, 389
 MSK_IPAR_MIO_CUT_KNAPSACK_COVER, 389
 MSK_IPAR_MIO_CUT_SELECTION_LEVEL, 389
 MSK_IPAR_MIO_FEASPUMP_LEVEL, 389
 MSK_IPAR_MIO_HEURISTIC_LEVEL, 389
 MSK_IPAR_MIO_MAX_NUM_BRANCHES, 389
 MSK_IPAR_MIO_MAX_NUM_RELAXS, 390
 MSK_IPAR_MIO_MAX_NUM_ROOT_CUT_ROUNDS, 390
 MSK_IPAR_MIO_MAX_NUM_SOLUTIONS, 390
 MSK_IPAR_MIO_MODE, 390
 MSK_IPAR_MIO_NODE_OPTIMIZER, 390
 MSK_IPAR_MIO_NODE_SELECTION, 390
 MSK_IPAR_MIO_PERSPECTIVE_REFORMULATE, 390
 MSK_IPAR_MIO_PROBING_LEVEL, 391
 MSK_IPAR_MIO_PROPAGATE_OBJECTIVE_CONSTRAINT, 391
 MSK_IPAR_MIO_RINS_MAX_NODES, 391
 MSK_IPAR_MIO_ROOT_OPTIMIZER, 391
 MSK_IPAR_MIO_ROOT_REPEAT_PREOLVE_LEVEL, 391
 MSK_IPAR_MIO_SEED, 392
 MSK_IPAR_MIO_VB_DETECTION_LEVEL, 392
 MSK_IPAR_MT_SPINCOUNT, 392
 MSK_IPAR_NUM_THREADS, 392
 MSK_IPAR_OPF_WRITE_HEADER, 392
 MSK_IPAR_OPF_WRITE_HINTS, 392
 MSK_IPAR_OPF_WRITE_LINE_LENGTH, 393
 MSK_IPAR_OPF_WRITE_PARAMETERS, 393
 MSK_IPAR_OPF_WRITE_PROBLEM, 393
 MSK_IPAR_OPF_WRITE_SOL_BAS, 393
 MSK_IPAR_OPF_WRITE_SOL_ITG, 393
 MSK_IPAR_OPF_WRITE_SOL_ITR, 393
 MSK_IPAR_OPF_WRITE_SOLUTIONS, 393
 MSK_IPAR_OPTIMIZER, 394
 MSK_IPAR_PARAM_READ_CASE_NAME, 394
 MSK_IPAR_PARAM_READ_IGNORE_ERROR, 394
 MSK_IPAR_PREOLVE_ELIMINATOR_MAX_FILL, 394
 MSK_IPAR_PREOLVE_ELIMINATOR_MAX_NUM_TRIES, 394
 MSK_IPAR_PREOLVE_LEVEL, 394
 MSK_IPAR_PREOLVE_LINDEP_ABS_WORK_TRH, 395
 MSK_IPAR_PREOLVE_LINDEP_REL_WORK_TRH, 395
 MSK_IPAR_PREOLVE_LINDEP_USE, 395
 MSK_IPAR_PREOLVE_MAX_NUM_PASS, 395

MSK_IPAR_PREOLVE_MAX_NUM_REDUCTIONS, 395
 MSK_IPAR_PREOLVE_USE, 395
 MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER, 395
 MSK_IPAR_PTF_WRITE_TRANSFORM, 396
 MSK_IPAR_READ_DEBUG, 396
 MSK_IPAR_READ_KEEP_FREE_CON, 396
 MSK_IPAR_READ_LP_DROP_NEW_VARS_IN_BOU, 396
 MSK_IPAR_READ_LP_QUOTED_NAMES, 396
 MSK_IPAR_READ_MPS_FORMAT, 396
 MSK_IPAR_READ_MPS_WIDTH, 397
 MSK_IPAR_READ_TASK_IGNORE_PARAM, 397
 MSK_IPAR_REMOVE_UNUSED_SOLUTIONS, 397
 MSK_IPAR_SENSITIVITY_ALL, 397
 MSK_IPAR_SENSITIVITY_OPTIMIZER, 397
 MSK_IPAR_SENSITIVITY_TYPE, 397
 MSK_IPAR_SIM_BASIS_FACTOR_USE, 397
 MSK_IPAR_SIM_DEGEN, 398
 MSK_IPAR_SIM_DUAL_CRASH, 398
 MSK_IPAR_SIM_DUAL_PHASEONE_METHOD, 398
 MSK_IPAR_SIM_DUAL_RESTRICT_SELECTION, 398
 MSK_IPAR_SIM_DUAL_SELECTION, 398
 MSK_IPAR_SIM_EXPLOIT_DUPVEC, 398
 MSK_IPAR_SIM_HOTSTART, 399
 MSK_IPAR_SIM_HOTSTART_LU, 399
 MSK_IPAR_SIM_MAX_ITERATIONS, 399
 MSK_IPAR_SIM_MAX_NUM_SETBACKS, 399
 MSK_IPAR_SIM_NON_SINGULAR, 399
 MSK_IPAR_SIM_PRIMAL_CRASH, 399
 MSK_IPAR_SIM_PRIMAL_PHASEONE_METHOD, 399
 MSK_IPAR_SIM_PRIMAL_RESTRICT_SELECTION, 400
 MSK_IPAR_SIM_PRIMAL_SELECTION, 400
 MSK_IPAR_SIM_REFACTOR_FREQ, 400
 MSK_IPAR_SIM_REFORMULATION, 400
 MSK_IPAR_SIM_SAVE_LU, 400
 MSK_IPAR_SIM_SCALING, 400
 MSK_IPAR_SIM_SCALING_METHOD, 401
 MSK_IPAR_SIM_SEED, 401
 MSK_IPAR_SIM_SOLVE_FORM, 401
 MSK_IPAR_SIM_STABILITY_PRIORITY, 401
 MSK_IPAR_SIM_SWITCH_OPTIMIZER, 401
 MSK_IPAR_SOL_FILTER_KEEP_BASIC, 401
 MSK_IPAR_SOL_FILTER_KEEP_RANGED, 401
 MSK_IPAR_SOL_READ_NAME_WIDTH, 402
 MSK_IPAR_SOL_READ_WIDTH, 402
 MSK_IPAR_SOLUTION_CALLBACK, 402
 MSK_IPAR_TIMING_LEVEL, 402
 MSK_IPAR_WRITE_BAS_CONSTRAINTS, 402
 MSK_IPAR_WRITE_BAS_HEAD, 402
 MSK_IPAR_WRITE_BAS_VARIABLES, 402
 MSK_IPAR_WRITE_COMPRESSION, 403
 MSK_IPAR_WRITE_DATA_PARAM, 403
 MSK_IPAR_WRITE_FREE_CON, 403
 MSK_IPAR_WRITE_GENERIC_NAMES, 403
 MSK_IPAR_WRITE_GENERIC_NAMES_IO, 403
 MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_ITEMS, 403
 MSK_IPAR_WRITE_INT_CONSTRAINTS, 403
 MSK_IPAR_WRITE_INT_HEAD, 404
 MSK_IPAR_WRITE_INT_VARIABLES, 404
 MSK_IPAR_WRITE_LP_FULL_OBJ, 404
 MSK_IPAR_WRITE_LP_LINE_WIDTH, 404
 MSK_IPAR_WRITE_LP_QUOTED_NAMES, 404
 MSK_IPAR_WRITE_LP_STRICT_FORMAT, 404
 MSK_IPAR_WRITE_LP_TERMS_PER_LINE, 404
 MSK_IPAR_WRITE_MPS_FORMAT, 405
 MSK_IPAR_WRITE_MPS_INT, 405
 MSK_IPAR_WRITE_PRECISION, 405
 MSK_IPAR_WRITE_SOL_BARVARIABLES, 405
 MSK_IPAR_WRITE_SOL_CONSTRAINTS, 405
 MSK_IPAR_WRITE_SOL_HEAD, 405
 MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES, 405
 MSK_IPAR_WRITE_SOL_VARIABLES, 406
 MSK_IPAR_WRITE_TASK_INC_SOL, 406
 MSK_IPAR_WRITE_XML_MODE, 406
 String parameters, 406
 MSK_SPAR_BAS_SOL_FILE_NAME, 406
 MSK_SPAR_DATA_FILE_NAME, 406
 MSK_SPAR_DEBUG_FILE_NAME, 406
 MSK_SPAR_INT_SOL_FILE_NAME, 406
 MSK_SPAR_ITR_SOL_FILE_NAME, 406
 MSK_SPAR_MIO_DEBUG_STRING, 407
 MSK_SPAR_PARAM_COMMENT_SIGN, 407
 MSK_SPAR_PARAM_READ_FILE_NAME, 407
 MSK_SPAR_PARAM_WRITE_FILE_NAME, 407
 MSK_SPAR_READ_MPS_BOU_NAME, 407
 MSK_SPAR_READ_MPS_OBJ_NAME, 407
 MSK_SPAR_READ_MPS_RAN_NAME, 407
 MSK_SPAR_READ_MPS_RHS_NAME, 408
 MSK_SPAR_REMOTE_ACCESS_TOKEN, 408
 MSK_SPAR_SENSITIVITY_FILE_NAME, 408
 MSK_SPAR_SENSITIVITY_RES_FILE_NAME, 408
 MSK_SPAR_SOL_FILTER_XC_LOW, 408
 MSK_SPAR_SOL_FILTER_XC_UPR, 408
 MSK_SPAR_SOL_FILTER_XX_LOW, 408
 MSK_SPAR_SOL_FILTER_XX_UPR, 408
 MSK_SPAR_STAT_FILE_NAME, 409
 MSK_SPAR_STAT_KEY, 409
 MSK_SPAR_STAT_NAME, 409
 MSK_SPAR_WRITE_LP_GEN_VAR_NAME, 409

Response codes

Termination, 410
 MSK_RES_OK, 410
 MSK_RES_TRM_INTERNAL, 410
 MSK_RES_TRM_INTERNAL_STOP, 410
 MSK_RES_TRM_MAX_ITERATIONS, 410
 MSK_RES_TRM_MAX_NUM_SETBACKS, 410
 MSK_RES_TRM_MAX_TIME, 410
 MSK_RES_TRM_MIO_NUM_BRANCHES, 410
 MSK_RES_TRM_MIO_NUM_RELAXS, 410
 MSK_RES_TRM_NUM_MAX_NUM_INT_SOLUTIONS, 410
 MSK_RES_TRM_NUMERICAL_PROBLEM, 410
 MSK_RES_TRM_OBJECTIVE_RANGE, 410
 MSK_RES_TRM_STALL, 410
 MSK_RES_TRM_USER_CALLBACK, 410

Warnings, 410
 MSK_RES_WRN_ANA_ALMOST_INT_BOUNDS, 412
 MSK_RES_WRN_ANA_C_ZERO, 412
 MSK_RES_WRN_ANA_CLOSE_BOUNDS, 412
 MSK_RES_WRN_ANA_EMPTY_COLS, 412
 MSK_RES_WRN_ANA_LARGE_BOUNDS, 412
 MSK_RES_WRN_DROPPED_NZ_QOBJ, 411
 MSK_RES_WRN_DUPLICATE_BARVARIABLE_NAMES, 412
 MSK_RES_WRN_DUPLICATE_CONE_NAMES, 412
 MSK_RES_WRN_DUPLICATE_CONSTRAINT_NAMES, 412
 MSK_RES_WRN_DUPLICATE_VARIABLE_NAMES, 412
 MSK_RES_WRN_ELIMINATOR_SPACE, 412
 MSK_RES_WRN_EMPTY_NAME, 411
 MSK_RES_WRN_EXP_CONES_WITH_VARIABLES_FIXED_AT_ZERO, 412
 MSK_RES_WRN_IGNORE_INTEGER, 411
 MSK_RES_WRN_INCOMPLETE_LINEAR_DEPENDENCY_CHECK, 412
 MSK_RES_WRN_LARGE_AIJ, 410
 MSK_RES_WRN_LARGE_BOUND, 410
 MSK_RES_WRN_LARGE_CJ, 410
 MSK_RES_WRN_LARGE_CON_FX, 410
 MSK_RES_WRN_LARGE_LO_BOUND, 410
 MSK_RES_WRN_LARGE_UP_BOUND, 410
 MSK_RES_WRN_LICENSE_EXPIRE, 411
 MSK_RES_WRN_LICENSE_FEATURE_EXPIRE, 411
 MSK_RES_WRN_LICENSE_SERVER, 411
 MSK_RES_WRN_LP_DROP_VARIABLE, 411
 MSK_RES_WRN_LP_OLD_QUAD_FORMAT, 411
 MSK_RES_WRN_MIO_INFEASIBLE_FINAL, 411
 MSK_RES_WRN_MPS_SPLIT_BOU_VECTOR, 411
 MSK_RES_WRN_MPS_SPLIT_RAN_VECTOR, 411
 MSK_RES_WRN_MPS_SPLIT_RHS_VECTOR, 411
 MSK_RES_WRN_NAME_MAX_LEN, 411
 MSK_RES_WRN_NO_DUALIZER, 413
 MSK_RES_WRN_NO_GLOBAL_OPTIMIZER, 411
 MSK_RES_WRN_NZ_IN_UPR_TRI, 411
 MSK_RES_WRN_OPEN_PARAM_FILE, 410
 MSK_RES_WRN_PARAM_IGNORED_CMIO, 412
 MSK_RES_WRN_PARAM_NAME_DOU, 411
 MSK_RES_WRN_PARAM_NAME_INT, 411
 MSK_RES_WRN_PARAM_NAME_STR, 411
 MSK_RES_WRN_PARAM_STR_VALUE, 411
 MSK_RES_WRN_POW_CONES_WITH_ROOT_FIXED_AT_ZERO, 412
 MSK_RES_WRN_PRESOLVE_OUTOFSPACE, 412
 MSK_RES_WRN_QUAD_CONES_WITH_ROOT_FIXED_AT_ZERO, 412
 MSK_RES_WRN_RQUAD_CONES_WITH_ROOT_FIXED_AT_ZERO, 412
 MSK_RES_WRN_SOL_FILE_IGNORED_CON, 411
 MSK_RES_WRN_SOL_FILE_IGNORED_VAR, 411
 MSK_RES_WRN_SOL_FILTER, 411
 MSK_RES_WRN_SPAR_MAX_LEN, 411
 MSK_RES_WRN_SYM_MAT_LARGE, 413
 MSK_RES_WRN_TOO_FEW_BASIS_VARS, 411
 MSK_RES_WRN_TOO_MANY_BASIS_VARS, 411
 MSK_RES_WRN_UNDEF_SOL_FILE_NAME, 411
 MSK_RES_WRN_USING_GENERIC_NAMES, 411
 MSK_RES_WRN_WRITE_CHANGED_NAMES, 412
 MSK_RES_WRN_WRITE_DISCARDED_CFIX, 412
 MSK_RES_WRN_ZERO_AIJ, 411
 MSK_RES_WRN_ZEROS_IN_SPARSE_COL, 412
 MSK_RES_WRN_ZEROS_IN_SPARSE_ROW, 412
 Errors, 413
 MSK_RES_ERR_AD_INVALID_CODELIST, 424
 MSK_RES_ERR_API_ARRAY_TOO_SMALL, 423
 MSK_RES_ERR_API_CB_CONNECT, 423
 MSK_RES_ERR_API_FATAL_ERROR, 423
 MSK_RES_ERR_API_INTERNAL, 423
 MSK_RES_ERR_APPENDING_TOO_BIG_CONE, 420
 MSK_RES_ERR_ARG_IS_TOO_LARGE, 418
 MSK_RES_ERR_ARG_IS_TOO_SMALL, 418
 MSK_RES_ERR_ARGUMENT_DIMENSION, 417
 MSK_RES_ERR_ARGUMENT_IS_TOO_LARGE, 425
 MSK_RES_ERR_ARGUMENT_LENNEQ, 417
 MSK_RES_ERR_ARGUMENT_PERM_ARRAY, 420
 MSK_RES_ERR_ARGUMENT_TYPE, 417
 MSK_RES_ERR_BAR_VAR_DIM, 424
 MSK_RES_ERR_BASIS, 419
 MSK_RES_ERR_BASIS_FACTOR, 422
 MSK_RES_ERR_BASIS_SINGULAR, 422
 MSK_RES_ERR_BLANK_NAME, 415
 MSK_RES_ERR_CBF_DUPLICATE_ACOORD, 426
 MSK_RES_ERR_CBF_DUPLICATE_BCOORD, 426
 MSK_RES_ERR_CBF_DUPLICATE_CON, 426
 MSK_RES_ERR_CBF_DUPLICATE_INT, 426
 MSK_RES_ERR_CBF_DUPLICATE_OBJ, 426
 MSK_RES_ERR_CBF_DUPLICATE_OBJACCOORD, 426
 MSK_RES_ERR_CBF_DUPLICATE_POW_CONES, 426
 MSK_RES_ERR_CBF_DUPLICATE_POW_STAR_CONES, 426
 MSK_RES_ERR_CBF_DUPLICATE_PSDVAR, 426
 MSK_RES_ERR_CBF_DUPLICATE_VAR, 426
 MSK_RES_ERR_CBF_INVALID_CON_TYPE, 426
 MSK_RES_ERR_CBF_INVALID_DIMENSION_OF_CONES, 427
 MSK_RES_ERR_CBF_INVALID_DOMAIN_DIMENSION, 426
 MSK_RES_ERR_CBF_INVALID_EXP_DIMENSION, 426
 MSK_RES_ERR_CBF_INVALID_INT_INDEX, 426
 MSK_RES_ERR_CBF_INVALID_NUMBER_OF_CONES, 427
 MSK_RES_ERR_CBF_INVALID_POWER, 426
 MSK_RES_ERR_CBF_INVALID_POWER_CONE_INDEX, 426
 MSK_RES_ERR_CBF_INVALID_POWER_STAR_CONE_INDEX, 426
 MSK_RES_ERR_CBF_INVALID_PSDVAR_DIMENSION, 426
 MSK_RES_ERR_CBF_INVALID_VAR_TYPE, 426
 MSK_RES_ERR_CBF_NO_VARIABLES, 425
 MSK_RES_ERR_CBF_NO_VERSION_SPECIFIED, 426
 MSK_RES_ERR_CBF_OBJ_SENSE, 425
 MSK_RES_ERR_CBF_PARSE, 425

MSK_RES_ERR_CBF_POWER_CONE_IS_TOO_LONG, 426
 MSK_RES_ERR_CBF_POWER_CONE_MISMATCH, 427
 MSK_RES_ERR_CBF_POWER_STAR_CONE_MISMATCH, 427
 MSK_RES_ERR_CBF_SYNTAX, 426
 MSK_RES_ERR_CBF_TOO_FEW_CONSTRAINTS, 426
 MSK_RES_ERR_CBF_TOO_FEW_INTS, 426
 MSK_RES_ERR_CBF_TOO_FEW_PSDVAR, 426
 MSK_RES_ERR_CBF_TOO_FEW_VARIABLES, 426
 MSK_RES_ERR_CBF_TOO_MANY_CONSTRAINTS, 425
 MSK_RES_ERR_CBF_TOO_MANY_INTS, 426
 MSK_RES_ERR_CBF_TOO_MANY_VARIABLES, 426
 MSK_RES_ERR_CBF_UNHANDLED_POWER_CONE_TYPE, 427
 MSK_RES_ERR_CBF_UNHANDLED_POWER_STAR_CONE_TYPE, 427
 MSK_RES_ERR_CBF_UNSUPPORTED, 426
 MSK_RES_ERR_CON_Q_NOT_NSD, 420
 MSK_RES_ERR_CON_Q_NOT_PSD, 420
 MSK_RES_ERR_CONE_INDEX, 420
 MSK_RES_ERR_CONE_OVERLAP, 420
 MSK_RES_ERR_CONE_OVERLAP_APPEND, 420
 MSK_RES_ERR_CONE_PARAMETER, 420
 MSK_RES_ERR_CONE_REP_VAR, 420
 MSK_RES_ERR_CONE_SIZE, 420
 MSK_RES_ERR_CONE_TYPE, 420
 MSK_RES_ERR_CONE_TYPE_STR, 420
 MSK_RES_ERR_DATA_FILE_EXT, 414
 MSK_RES_ERR_DUP_NAME, 415
 MSK_RES_ERR_DUPLICATE_AIJ, 421
 MSK_RES_ERR_DUPLICATE_BARVARIABLE_NAMES, 425
 MSK_RES_ERR_DUPLICATE_CONE_NAMES, 425
 MSK_RES_ERR_DUPLICATE_CONSTRAINT_NAMES, 425
 MSK_RES_ERR_DUPLICATE_VARIABLE_NAMES, 425
 MSK_RES_ERR_END_OF_FILE, 414
 MSK_RES_ERR_FACTOR, 422
 MSK_RES_ERR_FEASREPAIR_CANNOT_RELAX, 422
 MSK_RES_ERR_FEASREPAIR_INCONSISTENT_BOUND, 422
 MSK_RES_ERR_FEASREPAIR_SOLVING_RELAXED, 422
 MSK_RES_ERR_FILE_LICENSE, 413
 MSK_RES_ERR_FILE_OPEN, 414
 MSK_RES_ERR_FILE_READ, 414
 MSK_RES_ERR_FILE_WRITE, 414
 MSK_RES_ERR_FINAL_SOLUTION, 422
 MSK_RES_ERR_FIRST, 422
 MSK_RES_ERR_FIRSTI, 419
 MSK_RES_ERR_FIRSTJ, 419
 MSK_RES_ERR_FIXED_BOUND_VALUES, 421
 MSK_RES_ERR_FLEXLM, 413
 MSK_RES_ERR_FORMAT_STRING, 415
 MSK_RES_ERR_GLOBAL_INV_CONIC_PROBLEM, 422
 MSK_RES_ERR_HUGE_AIJ, 421
 MSK_RES_ERR_HUGE_C, 420
 MSK_RES_ERR_IDENTICAL_TASKS, 424
 MSK_RES_ERR_IN_ARGUMENT, 417
 MSK_RES_ERR_INDEX, 418
 MSK_RES_ERR_INDEX_ARR_IS_TOO_LARGE, 418
 MSK_RES_ERR_INDEX_ARR_IS_TOO_SMALL, 418
 MSK_RES_ERR_INDEX_IS_TOO_LARGE, 417
 MSK_RES_ERR_INDEX_IS_TOO_SMALL, 417
 MSK_RES_ERR_INF_DOU_INDEX, 417
 MSK_RES_ERR_INF_DOU_NAME, 418
 MSK_RES_ERR_INF_INT_INDEX, 418
 MSK_RES_ERR_INF_INT_NAME, 418
 MSK_RES_ERR_INF_LINT_INDEX, 418
 MSK_RES_ERR_INF_LINT_NAME, 418
 MSK_RES_ERR_INF_TYPE, 418
 MSK_RES_ERR_INFEAS_UNDEFINED, 424
 MSK_RES_ERR_INFINITE_BOUND, 421
 MSK_RES_ERR_INT64_TO_INT32_CAST, 424
 MSK_RES_ERR_INTERNAL, 423
 MSK_RES_ERR_INTERNAL_TEST_FAILED, 424
 MSK_RES_ERR_INV_APTRE, 418
 MSK_RES_ERR_INV_BK, 419
 MSK_RES_ERR_INV_BKC, 419
 MSK_RES_ERR_INV_BKX, 419
 MSK_RES_ERR_INV_CONE_TYPE, 419
 MSK_RES_ERR_INV_CONE_TYPE_STR, 419
 MSK_RES_ERR_INV_MARKI, 423
 MSK_RES_ERR_INV_MARKJ, 423
 MSK_RES_ERR_INV_NAME_ITEM, 419
 MSK_RES_ERR_INV_NUMI, 423
 MSK_RES_ERR_INV_NUMJ, 423
 MSK_RES_ERR_INV_OPTIMIZER, 422
 MSK_RES_ERR_INV_PROBLEM, 422
 MSK_RES_ERR_INV_QCON_SUBI, 421
 MSK_RES_ERR_INV_QCON_SUBJ, 421
 MSK_RES_ERR_INV_QCON_SUBK, 421
 MSK_RES_ERR_INV_QCON_VAL, 421
 MSK_RES_ERR_INV_QOBJ_SUBI, 421
 MSK_RES_ERR_INV_QOBJ_SUBJ, 421
 MSK_RES_ERR_INV_QOBJ_VAL, 421
 MSK_RES_ERR_INV_SK, 419
 MSK_RES_ERR_INV_SK_STR, 419
 MSK_RES_ERR_INV_SKC, 419
 MSK_RES_ERR_INV_SKN, 419
 MSK_RES_ERR_INV_SKX, 419
 MSK_RES_ERR_INV_VAR_TYPE, 419
 MSK_RES_ERR_INVALID_AIJ, 421
 MSK_RES_ERR_INVALID_AMPL_STUB, 424
 MSK_RES_ERR_INVALID_BARVAR_NAME, 415
 MSK_RES_ERR_INVALID_COMPRESSION, 423
 MSK_RES_ERR_INVALID_CON_NAME, 415
 MSK_RES_ERR_INVALID_CONE_NAME, 415
 MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_CFIX, 424
 MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_CONES, 425
 MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_FREE_CONSTRAINTS, 424
 MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_NONLINEAR, 425
 MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_RANGED_CONSTRAINTS, 424

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_SYM_MAT, 424
 MSK_RES_ERR_INVALID_FILE_NAME, 414
 MSK_RES_ERR_INVALID_FORMAT_TYPE, 419
 MSK_RES_ERR_INVALID_IDX, 418
 MSK_RES_ERR_INVALID_IOMODE, 423
 MSK_RES_ERR_INVALID_MAX_NUM, 418
 MSK_RES_ERR_INVALID_NAME_IN_SOL_FILE, 417
 MSK_RES_ERR_INVALID_OBJ_NAME, 415
 MSK_RES_ERR_INVALID_OBJECTIVE_SENSE, 421
 MSK_RES_ERR_INVALID_PROBLEM_TYPE, 425
 MSK_RES_ERR_INVALID_SOL_FILE_NAME, 414
 MSK_RES_ERR_INVALID_STREAM, 414
 MSK_RES_ERR_INVALID_SURPLUS, 419
 MSK_RES_ERR_INVALID_SYM_MAT_DIM, 424
 MSK_RES_ERR_INVALID_TASK, 414
 MSK_RES_ERR_INVALID_UTF8, 423
 MSK_RES_ERR_INVALID_VAR_NAME, 415
 MSK_RES_ERR_INVALID_WCHAR, 423
 MSK_RES_ERR_INVALID_WHICH_SOL, 418
 MSK_RES_ERR_JSON_DATA, 417
 MSK_RES_ERR_JSON_FORMAT, 417
 MSK_RES_ERR_JSON_MISSING_DATA, 417
 MSK_RES_ERR_JSON_NUMBER_OVERFLOW, 417
 MSK_RES_ERR_JSON_STRING, 417
 MSK_RES_ERR_JSON_SYNTAX, 417
 MSK_RES_ERR_LAST, 422
 MSK_RES_ERR_LASTI, 419
 MSK_RES_ERR_LASTJ, 419
 MSK_RES_ERR_LAU_ARG_K, 425
 MSK_RES_ERR_LAU_ARG_M, 425
 MSK_RES_ERR_LAU_ARG_N, 425
 MSK_RES_ERR_LAU_ARG_TRANS, 425
 MSK_RES_ERR_LAU_ARG_TRANSA, 425
 MSK_RES_ERR_LAU_ARG_TRANSB, 425
 MSK_RES_ERR_LAU_ARG_UPLO, 425
 MSK_RES_ERR_LAU_INVALID_LOWER_TRIANGULAR_MATRIX, 425
 MSK_RES_ERR_LAU_INVALID_SPARSE_SYMMETRIC_MATRIX, 425
 MSK_RES_ERR_LAU_NOT_POSITIVE_DEFINITE, 425
 MSK_RES_ERR_LAU_SINGULAR_MATRIX, 425
 MSK_RES_ERR_LAU_UNKNOWN, 425
 MSK_RES_ERR_LICENSE, 413
 MSK_RES_ERR_LICENSE_CANNOT_ALLOCATE, 413
 MSK_RES_ERR_LICENSE_CANNOT_CONNECT, 413
 MSK_RES_ERR_LICENSE_EXPIRED, 413
 MSK_RES_ERR_LICENSE_FEATURE, 413
 MSK_RES_ERR_LICENSE_INVALID_HOSTID, 413
 MSK_RES_ERR_LICENSE_MAX, 413
 MSK_RES_ERR_LICENSE_MOSEKLM_DAEMON, 413
 MSK_RES_ERR_LICENSE_NO_SERVER_LINE, 414
 MSK_RES_ERR_LICENSE_NO_SERVER_SUPPORT, 413
 MSK_RES_ERR_LICENSE_SERVER, 413
 MSK_RES_ERR_LICENSE_SERVER_VERSION, 413
 MSK_RES_ERR_LICENSE_VERSION, 413
 MSK_RES_ERR_LINK_FILE_DLL, 414
 MSK_RES_ERR_LIVING_TASKS, 414
 MSK_RES_ERR_LOWER_BOUND_IS_A_NAN, 421
 MSK_RES_ERR_LP_DUP_SLACK_NAME, 416
 MSK_RES_ERR_LP_EMPTY, 416
 MSK_RES_ERR_LP_FILE_FORMAT, 416
 MSK_RES_ERR_LP_FORMAT, 416
 MSK_RES_ERR_LP_FREE_CONSTRAINT, 416
 MSK_RES_ERR_LP_INCOMPATIBLE, 416
 MSK_RES_ERR_LP_INVALID_CON_NAME, 417
 MSK_RES_ERR_LP_INVALID_VAR_NAME, 416
 MSK_RES_ERR_LP_WRITE_CONIC_PROBLEM, 416
 MSK_RES_ERR_LP_WRITE_GECO_PROBLEM, 416
 MSK_RES_ERR_LU_MAX_NUM_TRIES, 423
 MSK_RES_ERR_MAX_LEN_IS_TOO_SMALL, 420
 MSK_RES_ERR_MAXNUMBARVAR, 418
 MSK_RES_ERR_MAXNUMCON, 418
 MSK_RES_ERR_MAXNUMCONE, 420
 MSK_RES_ERR_MAXNUMQNZ, 418
 MSK_RES_ERR_MAXNUMVAR, 418
 MSK_RES_ERR_MIO_INTERNAL, 425
 MSK_RES_ERR_MIO_INVALID_NODE_OPTIMIZER, 427
 MSK_RES_ERR_MIO_INVALID_ROOT_OPTIMIZER, 427
 MSK_RES_ERR_MIO_NO_OPTIMIZER, 422
 MSK_RES_ERR_MISSING_LICENSE_FILE, 413
 MSK_RES_ERR_MIXED_CONIC_AND_NL, 422
 MSK_RES_ERR_MPS_CONE_OVERLAP, 416
 MSK_RES_ERR_MPS_CONE_REPEAT, 416
 MSK_RES_ERR_MPS_CONE_TYPE, 416
 MSK_RES_ERR_MPS_DUPLICATE_Q_ELEMENT, 416
 MSK_RES_ERR_MPS_FILE, 415
 MSK_RES_ERR_MPS_INV_BOUND_KEY, 415
 MSK_RES_ERR_MPS_INV_CON_KEY, 415
 MSK_RES_ERR_MPS_INV_FIELD, 415
 MSK_RES_ERR_MPS_INV_MARKER, 415
 MSK_RES_ERR_MPS_INV_SEC_NAME, 415
 MSK_RES_ERR_MPS_INV_SEC_ORDER, 415
 MSK_RES_ERR_MPS_INVALID_OBJ_NAME, 416
 MSK_RES_ERR_MPS_INVALID_OBJSENSE, 416
 MSK_RES_ERR_MPS_MUL_CON_NAME, 415
 MSK_RES_ERR_MPS_MUL_CSEC, 415
 MSK_RES_ERR_MPS_MUL_QOBJ, 415
 MSK_RES_ERR_MPS_MUL_QSEC, 415
 MSK_RES_ERR_MPS_NO_OBJECTIVE, 415
 MSK_RES_ERR_MPS_NON_SYMMETRIC_Q, 416
 MSK_RES_ERR_MPS_NULL_CON_NAME, 415
 MSK_RES_ERR_MPS_NULL_VAR_NAME, 415
 MSK_RES_ERR_MPS_SPLITTED_VAR, 415
 MSK_RES_ERR_MPS_TAB_IN_FIELD2, 416
 MSK_RES_ERR_MPS_TAB_IN_FIELD3, 416
 MSK_RES_ERR_MPS_TAB_IN_FIELD5, 416
 MSK_RES_ERR_MPS_UNDEF_CON_NAME, 415
 MSK_RES_ERR_MPS_UNDEF_VAR_NAME, 415
 MSK_RES_ERR_MUL_A_ELEMENT, 419
 MSK_RES_ERR_NAME_IS_NULL, 422
 MSK_RES_ERR_NAME_MAX_LEN, 422
 MSK_RES_ERR_NAN_IN_BLC, 421
 MSK_RES_ERR_NAN_IN_BLC, 421
 MSK_RES_ERR_NAN_IN_BUC, 421
 MSK_RES_ERR_NAN_IN_BUX, 421

MSK_RES_ERR_NAN_IN_C, 421
 MSK_RES_ERR_NAN_IN_DOUBLE_DATA, 421
 MSK_RES_ERR_NEGATIVE_APPEND, 422
 MSK_RES_ERR_NEGATIVE_SURPLUS, 422
 MSK_RES_ERR_NEWER_DLL, 414
 MSK_RES_ERR_NO_BARS_FOR_SOLUTION, 424
 MSK_RES_ERR_NO_BARX_FOR_SOLUTION, 424
 MSK_RES_ERR_NO_BASIS_SOL, 422
 MSK_RES_ERR_NO_DUAL_FOR_ITG_SOL, 423
 MSK_RES_ERR_NO_DUAL_INFEAS_CER, 423
 MSK_RES_ERR_NO_INIT_ENV, 414
 MSK_RES_ERR_NO_OPTIMIZER_VAR_TYPE, 422
 MSK_RES_ERR_NO_PRIMAL_INFEAS_CER, 423
 MSK_RES_ERR_NO_SNX_FOR_BAS_SOL, 423
 MSK_RES_ERR_NO_SOLUTION_IN_CALLBACK, 423
 MSK_RES_ERR_NON_UNIQUE_ARRAY, 425
 MSK_RES_ERR_NONCONVEX, 420
 MSK_RES_ERR_NONLINEAR_EQUALITY, 420
 MSK_RES_ERR_NONLINEAR_RANGED, 420
 MSK_RES_ERR_NULL_ENV, 414
 MSK_RES_ERR_NULL_POINTER, 414
 MSK_RES_ERR_NULL_TASK, 414
 MSK_RES_ERR_NUM_ARGUMENTS, 417
 MSK_RES_ERR_NUMCONLIM, 418
 MSK_RES_ERR_NUMVARLIM, 418
 MSK_RES_ERR_OBJ_Q_NOT_NSD, 420
 MSK_RES_ERR_OBJ_Q_NOT_PSD, 420
 MSK_RES_ERR_OBJECTIVE_RANGE, 419
 MSK_RES_ERR_OLDER_DLL, 414
 MSK_RES_ERR_OPF_FORMAT, 416
 MSK_RES_ERR_OPF_NEW_VARIABLE, 417
 MSK_RES_ERR_OPF_PREMATURE_EOF, 417
 MSK_RES_ERR_OPTIMIZER_LICENSE, 413
 MSK_RES_ERR_OVERFLOW, 422
 MSK_RES_ERR_PARAM_INDEX, 417
 MSK_RES_ERR_PARAM_IS_TOO_LARGE, 417
 MSK_RES_ERR_PARAM_IS_TOO_SMALL, 417
 MSK_RES_ERR_PARAM_NAME, 417
 MSK_RES_ERR_PARAM_NAME_DOU, 417
 MSK_RES_ERR_PARAM_NAME_INT, 417
 MSK_RES_ERR_PARAM_NAME_STR, 417
 MSK_RES_ERR_PARAM_TYPE, 417
 MSK_RES_ERR_PARAM_VALUE_STR, 417
 MSK_RES_ERR_PLATFORM_NOT_LICENSED, 413
 MSK_RES_ERR_POSTSOLVE, 422
 MSK_RES_ERR_PRO_ITEM, 419
 MSK_RES_ERR_PROB_LICENSE, 413
 MSK_RES_ERR_PTF_FORMAT, 416
 MSK_RES_ERR_QCON_SUBI_TOO_LARGE, 421
 MSK_RES_ERR_QCON_SUBI_TOO_SMALL, 421
 MSK_RES_ERR_QCON_UPPER_TRIANGLE, 421
 MSK_RES_ERR_QOBJ_UPPER_TRIANGLE, 421
 MSK_RES_ERR_READ_FORMAT, 415
 MSK_RES_ERR_READ_LP_MISSING_END_TAG, 416
 MSK_RES_ERR_READ_LP_NONEXISTING_NAME, 416
 MSK_RES_ERR_REMOVE_CONE_VARIABLE, 420
 MSK_RES_ERR_REPAIR_INVALID_PROBLEM, 422
 MSK_RES_ERR_REPAIR_OPTIMIZATION_FAILED, 422
 MSK_RES_ERR_SEN_BOUND_INVALID_LO, 423
 MSK_RES_ERR_SEN_BOUND_INVALID_UP, 423
 MSK_RES_ERR_SEN_FORMAT, 423
 MSK_RES_ERR_SEN_INDEX_INVALID, 423
 MSK_RES_ERR_SEN_INDEX_RANGE, 423
 MSK_RES_ERR_SEN_INVALID_REGEX, 424
 MSK_RES_ERR_SEN_NUMERICAL, 424
 MSK_RES_ERR_SEN_SOLUTION_STATUS, 424
 MSK_RES_ERR_SEN_UNDEF_NAME, 423
 MSK_RES_ERR_SEN_UNHANDLED_PROBLEM_TYPE, 424
 MSK_RES_ERR_SERVER_CONNECT, 427
 MSK_RES_ERR_SERVER_PROTOCOL, 427
 MSK_RES_ERR_SERVER_STATUS, 427
 MSK_RES_ERR_SERVER_TOKEN, 427
 MSK_RES_ERR_SHAPE_IS_TOO_LARGE, 417
 MSK_RES_ERR_SIZE_LICENSE, 413
 MSK_RES_ERR_SIZE_LICENSE_CON, 413
 MSK_RES_ERR_SIZE_LICENSE_INTVAR, 413
 MSK_RES_ERR_SIZE_LICENSE_NUMCORES, 424
 MSK_RES_ERR_SIZE_LICENSE_VAR, 413
 MSK_RES_ERR_SLICE_SIZE, 422
 MSK_RES_ERR_SOL_FILE_INVALID_NUMBER, 420
 MSK_RES_ERR_SOLITEM, 418
 MSK_RES_ERR_SOLVER_PROBTYPE, 419
 MSK_RES_ERR_SPACE, 414
 MSK_RES_ERR_SPACE_LEAKING, 415
 MSK_RES_ERR_SPACE_NO_INFO, 415
 MSK_RES_ERR_SYM_MAT_DUPLICATE, 424
 MSK_RES_ERR_SYM_MAT_HUGE, 422
 MSK_RES_ERR_SYM_MAT_INVALID, 422
 MSK_RES_ERR_SYM_MAT_INVALID_COL_INDEX, 424
 MSK_RES_ERR_SYM_MAT_INVALID_ROW_INDEX, 424
 MSK_RES_ERR_SYM_MAT_INVALID_VALUE, 424
 MSK_RES_ERR_SYM_MAT_NOT_LOWER_TRINGULAR, 424
 MSK_RES_ERR_TASK_INCOMPATIBLE, 423
 MSK_RES_ERR_TASK_INVALID, 423
 MSK_RES_ERR_TASK_WRITE, 423
 MSK_RES_ERR_THREAD_COND_INIT, 414
 MSK_RES_ERR_THREAD_CREATE, 414
 MSK_RES_ERR_THREAD_MUTEX_INIT, 414
 MSK_RES_ERR_THREAD_MUTEX_LOCK, 414
 MSK_RES_ERR_THREAD_MUTEX_UNLOCK, 414
 MSK_RES_ERR_TOCONIC_CONSTR_NOT_CONIC, 427
 MSK_RES_ERR_TOCONIC_CONSTR_Q_NOT_PSD, 427
 MSK_RES_ERR_TOCONIC_CONSTRAINT_FX, 427
 MSK_RES_ERR_TOCONIC_CONSTRAINT_RA, 427
 MSK_RES_ERR_TOCONIC_OBJECTIVE_NOT_PSD, 427
 MSK_RES_ERR_TOO_SMALL_A_TRUNCATION_VALUE, 421
 MSK_RES_ERR_TOO_SMALL_MAX_NUM_NZ, 418
 MSK_RES_ERR_TOO_SMALL_MAXNUMANZ, 418
 MSK_RES_ERR_UNB_STEP_SIZE, 424
 MSK_RES_ERR_UNDEF_SOLUTION, 419
 MSK_RES_ERR_UNDEFINED_OBJECTIVE_SENSE, 421
 MSK_RES_ERR_UNHANDLED_SOLUTION_STATUS, 425
 MSK_RES_ERR_UNKNOWN, 414
 MSK_RES_ERR_UPPER_BOUND_IS_A_NAN, 421

MSK_RES_ERR_UPPER_TRIANGLE, [425](#)
MSK_RES_ERR_WHICHITEM_NOT_ALLOWED, [418](#)
MSK_RES_ERR_WHICHSOL, [418](#)
MSK_RES_ERR_WRITE_LP_FORMAT, [416](#)
MSK_RES_ERR_WRITE_LP_NON_UNIQUE_NAME, [416](#)
MSK_RES_ERR_WRITE_MPS_INVALID_NAME, [416](#)
MSK_RES_ERR_WRITE_OPF_INVALID_VAR_NAME, [416](#)
MSK_RES_ERR_WRITING_FILE, [416](#)
MSK_RES_ERR_XML_INVALID_PROBLEM_TYPE, [424](#)
MSK_RES_ERR_Y_IS_UNDEFINED, [421](#)

Types

MSKboolean_t, [451](#)
MSKenv_t, [451](#)
MSKint32t, [451](#)
MSKint64t, [452](#)
MSKreal_t, [452](#)
MSKstring_t, [452](#)
MSKtask_t, [451](#)
MSKuserhandle_t, [451](#)
MSKwchart, [452](#)

Index

A

analysis
 infeasibility, 187
attaching
 streams, 15

B

basic
 solution, 73
basis identification, 103, 175
basis type
 sensitivity analysis, 194
BLAS, 110
bound
 constraint, 11, 160, 163
 linear optimization, 11
 variable, 11, 160, 163

C

callback, 83
cardinality constraints, 64, 148
CBF format, 483
ceol
 example, 38
certificate, 74
 dual, 162, 166
 primal, 161, 165
Cholesky factorization, 112, 135
column ordered
 matrix format, 203
compile
 Linux, examples, 8
complementarity, 161, 165
concurrent optimizer, 155
cone
 dual, 164
 dual exponential, 37
 exponential, 37
 power, 33
 quadratic, 28
 rotated quadratic, 28
 semidefinite, 41
conic exponential optimization, 37
conic optimization, 28, 33, 37, 163
 interior-point, 178
 termination criteria, 180
conic problem
 example, 28, 34, 38
conic quadratic optimization, 28

Conic quadratic reformulation, 115
constraint
 bound, 11, 160, 163
 linear optimization, 11
 matrix, 11, 160, 163
 quadratic, 168
correlation matrix, 124
covariance matrix, *see* correlation matrix
cqol
 example, 28
cut, 183

D

defining
 objective, 15
determinism, 119
dual
 certificate, 162, 166
 cone, 164
 feasible, 161
 infeasible, 161, 162, 166
 problem, 161, 164, 167
 solution, 75
 variable, 161, 164
duality
 conic, 164
 linear, 161
 semidefinite, 167
dualizer, 171

E

efficient frontier, 132
eliminator, 171
entropy, 62
 relative, 62
error
 optimization, 73
errors, 77
example
 ceol, 38
 conic problem, 28, 34, 38
 cqol, 28
 lo1, 15
 pow1, 34
 qol, 18
 quadratic objective, 18
examples
 compile Linux, 8
exceptions, 77

exponential, 61
exponential cone, 37

F

factor model, 135

feasible

dual, 161
primal, 160, 173, 179
problem, 160

format, 81

CBF, 483
json, 501
LP, 457
MPS, 462
OPF, 474
PTF, 497
sol, 509
task, 501

full

vector format, 202

G

geometric mean, 61

geometric programming, 53

GP, 53

H

hot-start, 177

I

I/O, 81

infeasibility, 74, 161, 165

analysis, 187
linear optimization, 161
repair, 187
semidefinite, 167

infeasible

dual, 161, 162, 166
primal, 160, 161, 165, 173, 180
problem, 160, 161, 167

information item, 83, 84

installation, 5

makefile, 7
requirements, 5
troubleshooting, 5
Visual Studio, 7

integer

optimizer, 182
solution, 73
variable, 47

integer feasible

solution, 184

integer optimization, 47, 182

cut, 183
initial solution, 51
objective bound, 183
optimality gap, 185
parameter, 47

relaxation, 183

termination criteria, 184

tolerance, 184

integer optimizer

logging, 185

interior-point

conic optimization, 178
linear optimization, 172
logging, 176, 182
optimizer, 172, 178
solution, 73
termination criteria, 174, 180

J

json format, 501

L

LAPACK, 110

license, 121

linear

objective, 15

linear constraint matrix, 11

linear dependency, 171

linear optimization, 11, 160

bound, 11

constraint, 11

infeasibility, 161

interior-point, 172

objective, 11

simplex, 177

termination criteria, 174, 177

variable, 11

linearity interval, 193

Linux

examples compile, 8

lo1

example, 15

log-sum-exp, 62, 152

logarithm, 61

logging, 80

integer optimizer, 185

interior-point, 176, 182

optimizer, 176, 178, 182

simplex, 178

logistic regression, 152

LP format, 457

M

machine learning

logistic regression, 152

market impact cost, 136

Markowitz

model, 123

Markowitz model, 124

portfolio optimization, 123

matrix

constraint, 11, 160, 163
semidefinite, 41

- symmetric, 41
- matrix format
 - column ordered, 203
 - row ordered, 203
 - triplets, 203
- memory management, 119
- MIP, *see* integer optimization
- mixed-integer, *see* integer
- mixed-integer optimization, *see* integer optimization
- model
 - Markowitz, 123
 - portfolio optimization, 123
- modeling
 - design, 8
- monomial, 60
- MPS format, 462
 - free, 473

N

- near-optimal
 - solution, 184
- norm
 - 1-norm, 59
 - 2-norm, 60
 - p-norm, 61
- numerical issues
 - presolve, 171
 - scaling, 171
 - simplex, 177

O

- objective, 160, 163
 - defining, 15
 - linear, 15
 - linear optimization, 11
- objective bound, 183
- OPF format, 474
- optimal
 - solution, 74
- optimality gap, 185
- optimization
 - conic, 163
 - conic quadratic, 163
 - error, 73
 - linear, 11, 160
 - semidefinite, 167
- optimizer
 - concurrent, 155
 - determinism, 119
 - integer, 182
 - interior-point, 172, 178
 - interrupt, 83
 - logging, 176, 178, 182
 - parallel, 70
 - selection, 171, 172
 - simplex, 177

P

- parallel optimization, 70, 155
- parallelization, 119
- parameter, 81
 - integer optimization, 47
 - simplex, 177
- Pareto optimality, 124
- portfolio optimization
 - cardinality constraints, 64, 148
 - efficient frontier, 132
 - factor model, 135
 - market impact cost, 136
 - Markowitz model, 124
 - model, 123
 - Pareto optimality, 124
 - slippage cost, 136
 - transaction cost, 143
- positive semidefinite, 18
- pow1
 - example, 34
- power, 60
- power cone, 33
- power cone optimization, 33
- presolve, 170
 - eliminator, 171
 - linear dependency check, 171
 - numerical issues, 171
- primal
 - certificate, 161, 165
 - feasible, 160, 173, 179
 - infeasible, 160, 161, 165, 173, 180
 - problem, 161, 164, 167
 - solution, 75, 160
- primal-dual
 - problem, 172, 179
 - solution, 161
- problem
 - dual, 161, 164, 167
 - feasible, 160
 - infeasible, 160, 161, 167
 - load, 81
 - primal, 161, 164, 167
 - primal-dual, 172, 179
 - save, 81
 - status, 73
 - unbounded, 162, 166
- PTF format, 497

Q

- qo1
 - example, 18
- quadratic
 - constraint, 168
- quadratic cone, 28
- quadratic objective
 - example, 18
- quadratic optimization, 168
- quality

- solution, 185
- R
- regression
 - logistic, 152
- relaxation, 183
- repair
 - infeasibility, 187
- response code, 77
- rotated quadratic cone, 28
- row ordered
 - matrix format, 203
- S
- scaling, 171
- semicontinuous variable, 63
- semidefinite
 - cone, 41
 - infeasibility, 167
 - matrix, 41
 - variable, 41
- semidefinite optimization, 41, 167
- sensitivity analysis, 192
 - basis type, 194
- shadow price, 193
- simplex
 - linear optimization, 177
 - logging, 178
 - numerical issues, 177
 - optimizer, 177
 - parameter, 177
 - termination criteria, 177
- slippage cost, 136
- softplus, 62
- sol format, 509
- solution
 - basic, 73
 - dual, 75
 - file format, 509
 - integer, 73
 - integer feasible, 184
 - interior-point, 73
 - near-optimal, 184
 - optimal, 74
 - primal, 75, 160
 - primal-dual, 161
 - quality, 185
 - retrieve, 73
 - status, 14, 74
- solving linear system, 107
- sparse
 - vector format, 203
- sparse vector, 203
- status
 - problem, 73
 - solution, 14, 74
- streams
 - attaching, 15

- string
 - UTF8, 122
 - unicode, 122
- symmetric
 - matrix, 41
- T
- task format, 501
- termination, 73
- termination criteria, 83
 - conic optimization, 180
 - integer optimization, 184
 - interior-point, 174, 180
 - linear optimization, 174, 177
 - simplex, 177
 - tolerance, 175, 181, 184
- thread, 119
- time limit, 83
- tolerance
 - integer optimization, 184
 - termination criteria, 175, 181, 184
- transaction cost, 143
- triplets
 - matrix format, 203
- troubleshooting
 - installation, 5
- U
- UTF8
 - string, 122
- unbounded
 - problem, 162, 166
- unicode
 - string, 122
- unicode string, 122
- user callback, *see* callback
- UTF8, 122
- V
- variable, 160, 163
 - bound, 11, 160, 163
 - dual, 161, 164
 - integer, 47
 - linear optimization, 11
 - semicontinuous, 63
 - semidefinite, 41
- vector format
 - full, 202
 - sparse, 203
- Visual Studio
 - installation, 7